

IBM Cúram Social Program Management
Version 7.0.1

*Cúram Citizen Context Viewer
Developer Guide*



Note

Before using this information and the product it supports, read the information in “Notices” on page 9

Edition

This edition applies to IBM Cúram Social Program Management v7.0.1 and to all subsequent releases unless otherwise indicated in new editions.

Licensed Materials - Property of IBM.

© **Copyright IBM Corporation 2012, 2017.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

© Cúram Software Limited. 2011. All rights reserved.

Contents

Figures	v
----------------	----------

Tables	vii
---------------	------------

Developing with the Citizen Context

Viewer	1
---------------	----------

Overview	1
----------	---

Prerequisites	1
---------------	---

Sections in this Guide	1
------------------------	---

Adding Links to Launch the Citizen Context Viewer	1
---	---

Example	1
---------	---

Customizing the Citizen Context Viewer	2
--	---

Injection Points in the CCV	2
-----------------------------	---

ContextNodeRootEvent	2
----------------------	---

ContextCaseHandlerEvent	2
-------------------------	---

Writing a Loader	2
------------------	---

Example	3
---------	---

Writing a Case Handler	5
------------------------	---

Example	5
---------	---

Adding Node Types and Right-click Menu Options	5
--	---

Adding Node Types	5
-------------------	---

Example	6
---------	---

Adding Right-click Menu Options	6
---------------------------------	---

Setting Attributes for Context Menu	6
-------------------------------------	---

Example	7
---------	---

Localizing Citizen Context Viewer Data	7
--	---

Compliance	7
------------	---

Public API	7
------------	---

Identifying the API	7
---------------------	---

Outside the API	7
-----------------	---

Notices	9
----------------	----------

Privacy Policy considerations	11
-------------------------------	----

Trademarks	11
------------	----

Figures

Tables

Developing with the Citizen Context Viewer

Use this information to learn how to create custom UIM pages that launch the Citizen Context Viewer. Injection points for customizing the Citizen Context Viewer exist. Custom loaders and case handlers can be written. Node types and custom right-click menu options for the Citizen Context Viewer elements can be added.

Overview

The purpose of this guide is to provide instructions on how to customize the Citizen Context Viewer (CCV). It includes information on adding links to launch the CCV, on adding new elements to the CCV, and on localizing the CCV.

This guide is intended for developers responsible for integrating the CCV into specific components. Business analysts may find the guide useful in understanding the aspects of the CCV that can be customized to meet business requirements.

Prerequisites

There are two additional guides on the CCV: the *Cúram Citizen Context Viewer Guide* and the *Cúram Citizen Context Viewer Configuration guide*.

Sections in this Guide

The following list describes the sections within this guide:

Adding Links to Launch the Citizen Context Viewer

This section describes how to add links to custom uim pages that can launch the CCV.

Customizing the Citizen Context Viewer

This section describes the injection points for customizing the CCV and provides instructions on writing loaders and case handlers.

Adding Node Types and Right-click Menu Options

This section describes how a node type is defined for each element in the CCV tree and how to add right-click menu options for the CCV elements.

Localizing Citizen Context Viewer Data

This section provides information on localizing the data that appears as text in the CCV.

Adding Links to Launch the Citizen Context Viewer

It may be necessary to launch the CCV from customized pages. This can be achieved by creating links in the customized uims which reference the CCV javascript.

Example

The following code snippet outlines the link that specifies the CCV to be opened. The SOURCE should contain the field that holds the concern role ID for the person to be displayed in the CCV.

The TARGET should be as specified below:

```
<SCRIPT EVENT="ONCLICK"
  ACTION="openContextViewer(this,event)"
  SCRIPT_FILE="ContextViewerPopup.js"/>

<LINK URI="../../flex/Citizen_resolveCitizenViewer.jsp">

<CONNECT>

<SOURCE NAME="DISPLAY" PROPERTY="concernRoleID"/>

<TARGET NAME="PAGE" PROPERTY="concernRoleID"/>

</CONNECT>

</LINK>
```

Customizing the Citizen Context Viewer

This section provides instructions on customizing the Citizen Context Viewer (CCV). The CCV interfaces define default implementations that can be replaced by injecting a custom implementation for that interface.

Injection Points in the CCV

Customization of the Citizen Context Viewer is facilitated via events and listeners. The following sections describe the areas where listeners might be implemented to carry out certain customizations of the CCV.

ContextNodeRootEvent

A listener to the ContextNodeRootEvent can add an implementation of the ContextCategory interface that will be used to populate the data displayed in the CCV. A implementation of the ContextCategory interface will allow loaders to be defined to show information in the CCV.

ContextCaseHandlerEvent

Cases that are displayed in the CCV can be created by a number of different components. Retrieval of information for these cases may therefore need variations depending on the type of case being read. The IContextCaseHandler interface describes case handlers for specific case types. These case handlers will know the specific retrieval methods for getting information such as the case name. A default case handler exists that will get the case name from the case header table.

If the case type is not known by the OOTB CCV, then the default case handler will be used to read information for that case. If the default details for the case shown in the CCV are not specific enough then a customized case handler can be written. This case handler must implement the IContextCaseHandler interface and can be added by listening for the ContextCaseHandlerEvent setContextCaseHandlers method.

Writing a Loader

As previously mentioned, a loader class provides information that can be displayed in the CCV. Typically, a loader is written for each leaf node of the root node in the CCV.

For example, there are specific loaders for each of the leaf node categories including, Care And Protection, Communities, Family, and Dealings. These loaders gather all of the data for these categories. All loader classes must extend the

ContextNode abstract class. A listener of ContextNodeRootEvent can be implemented to add new loaders to the existing set of CCV loaders via the method `setChildNodesForContextType(Map<CONTEXT_TYPEEntry, ContextCategory> contextCategory)`

Example

This loader example shows how a loader might be defined that reads Core interactions and sets up the data to be displayed in the CCV.

Comments are denoted by `/** **/`.

```

class ContextInteractionLoader extends ContextNode {
    /** The load method must be implemented by all loader classes. This
    is what is called when the CCV is opened. */ public ContextNode
    load(Context ID contextID) throws ApplicationException,
    InformationalException { /**Set up and read the list of interactions
    from core for the context id, the context id in this instance is the
    concern role id for the citizen being displayed */
    ClientInteraction clientInteractionObj =
    ClientInteractionFactory.newInstance(); ClientInteractionKey
    clientInteractionKey = new ClientInteractionKey();
    ClientInteractionDtls clientInteractionDtls; ListInteractionKey
    listInteractionKey = new ListInteractionKey();
    listInteractionKey.concernRoleID = contextID.context_id;
    InteractionDetailsList interactionDetailsList =
    clientInteractionObj.list(listInteractionKey); /** If sensitivity
    settings do not allow this citizen to be shown then indicate that no
    interactions can be displayed */ if
    (!ContextUtil.checkUserAuthorizationForParticipant(
    contextID.context_id)) { setLabelAllNotShown(
    ContextUtil.getTextForLocale(BPOCONTEXTINTERACTION.ROOT),
    interactionDetailsList.dtls.size()); return this; } /** Calling the
    setLabelIncludingChildren will display the Interaction label as
    defined in the interaction message file and the number of
    interactions */ setLabelIncludingChildren(
    ContextUtil.getTextForLocale(BPOCONTEXTINTERACTION.ROOT),
    interactionDetailsList.dtls.size()); /** Set the node type. Node
    types define certain characteristics, including the menu that will
    appear on right click */ /** See Chapters 3 & 4 for more
    information on Node Types and Menus */
    setNodeType(CONTEXTNODETYPE.DEFAULTNODE); /** Set the context ID. If
    a context ID is set then this will be used when carrying out a
    specific action. */ /** Such as opening an new page from a menu
    item click */ setContextID(0); if
    (interactionDetailsList.dtls.size() == 0) {
    setLabelIncludingChildren(
    ContextUtil.getTextForLocale(BPOCONTEXTINTERACTION.ROOT),
    interactionDetailsList.dtls.size()); /** if there are no
    interactions then add an empty child */ addDefaultChild(new
    ContextLabelLoader(), ContextUtil.getLocalisableStringForLocale((
    BPOCONTEXT.EMPTY)) .arg(ContextUtil.getTextForLocale(
    BPOCONTEXTINTERACTION.ROOT)).getMessage()); return this; } else {
    Iterator interactionsIter = interactionDetailsList.dtls.iterator();
    InteractionDetails interactionDetails = new InteractionDetails();
    while (interactionsIter.hasNext()) { interactionDetails =
    (InteractionDetails) interactionsIter.next();
    ContextInteractionLoader contextInteractionChild = new
    ContextInteractionLoader(); contextInteractionChild.setLabel(
    curam.util.type.CodeTable.getOneItem( INTERACTIONTYPE.TABLENAME,
    interactionDetails.interactionTypeCode));
    clientInteractionKey.clientInteractionID =
    interactionDetails.clientInteractionID; clientInteractionDtls =
    clientInteractionObj.read(clientInteractionKey); if
    (clientInteractionDtls.relatedType.equals(
    curam.codetable.RELATEDINTERACTIONTYPE.COMMUNICATION)) { /** This is
    a communication interaction so set the corresponding node type and
    menu */ /** See Chapters 3 & 4 for more information on node
    types and menus */ contextInteractionChild.setNodeType(
    CONTEXTNODETYPE.COMM_INTERACTION_NODE); /** Set the context id for
    this child node to be the interaction relatedID. This will be used
    when opening any interaction pages from a CCV interaction menu */
    contextInteractionChild.setContextID(
    clientInteractionDtls.relatedID); } else if
    (clientInteractionDtls.relatedType.equals(
    curam.codetable.RELATEDINTERACTIONTYPE.PAYMENT)) { /** This is a
    payment interaction so set the corresponding node type and menu */
    /** See Chapters 3 & 4 for more information on node types and
    menus */ contextInteractionChild.setNodeType(
    CONTEXTNODETYPE.PAY_INTERACTION_NODE); /** Set the context id for
    this child node to be the interaction relatedID. This will be used
    when opening any interaction pages from a CCV interaction menu */
    contextInteractionChild.setContextID(
    clientInteractionDtls.relatedID); } else {
    contextInteractionChild.setNodeType( CONTEXTNODETYPE.DEFAULTNODE);

```

Writing a Case Handler

A case handler can be used to get the name of a case where the retrieval of the case details is not covered by the CCV default case handler. The case handler can also be used to check property settings defined for a given case type. All case handlers must extend the abstract `ContextCaseHandler` class.

Example

This example outlines how a case handler might be defined for Integrated cases.

Comments are denoted by `/** **/`.

```
class IntegratedCaseHandler extends
    ContextCaseHandler { @Inject private Provider<ContextCore>
    contextCoreProvider; public String getCaseName(long caseID) throws
    ApplicationException, InformationalException { return
    CodeTable.getItem(PRODUCTCATEGORY.TABLENAME,
    this.readType(caseID)); } protected String getShowAllStatuses() {
    /** check to see if CCV is configured to display all IC case
    statuses **/ return ISEConfigurationUtility.getProperty(
    EnvVars.ENV_CCV_CASE_SHOW_ALL_IC_STATUSES,
    EnvVars.ENV_CCV_CASE_SHOW_ALL_IC_STATUSES_DEFAULT); } protected
    String getShowAllTypes() { /** check to see if CCV is configured to
    display all integrated case types **/ return
    ISEConfigurationUtility.getProperty(
    EnvVars.ENV_CCV_CASE_SHOW_ALL_IC_TYPES,
    EnvVars.ENV_CCV_CASE_SHOW_ALL_IC_TYPES_DEFAULT); } protected
    ArrayList<String> listAcceptableCaseStatuses() { return
    ISEConfigurationUtility.getListPropertyValues(
    EnvVars.ENV_CCV_IC_CASE_STATUSES_TO_DISPLAY,
    EnvVars.ENV_CCV_IC_CASE_STATUSES_TO_DISPLAY_DEFAULT); } protected
    ArrayList<String> listAcceptableTypes() { return
    ISEConfigurationUtility.getListPropertyValues(
    EnvVars.ENV_CCV_IC_CASE_TYPES_TO_DISPLAY,
    EnvVars.ENV_CCV_IC_CASE_TYPES_TO_DISPLAY_DEFAULT); } protected
    String readType(long caseID) throws ApplicationException,
    InformationalException { /** read the case type, how this is done
    can be specific to the case type **/ ContextCore contextCore =
    contextCoreProvider.get(); CaseHeaderDtls caseHeaderDtls =
    contextCore.readCaseHeaderByCaseID(caseID); return
    caseHeaderDtls.integratedCaseType; } public String
    getShowAllCaseParticipantRoles() { return
    ISEConfigurationUtility.getProperty(
    EnvVars.ENV_CCV_CASE_SHOW_ALL_IC_CPROLES,
    EnvVars.ENV_CCV_CASE_SHOW_ALL_IC_CPROLES_DEFAULT); } protected
    ArrayList<String> listAcceptableCaseParticipantRoles() {
    return ISEConfigurationUtility.getListPropertyValues(
    EnvVars.ENV_CCV_IC_CPROLE_TYPES_TO_DISPLAY,
    EnvVars.ENV_CCV_IC_CPROLE_TYPES_TO_DISPLAY_DEFAULT); }
}
```

Adding Node Types and Right-click Menu Options

This section provides instructions on adding node types to the Citizen Context Viewer tree and on adding right-click menu options for menu items in each node.

Adding Node Types

When a loader retrieves data to be displayed by the context viewer, each element in the context viewer tree will be assigned a node type. The node type describes the following about the element to which it is assigned.

CONTEXTNODETYPE

This attribute holds the ID for the node type. The ID maps to a code table value in the ContextNodeType code table to allow the node type to be referenced in code via its java identifier.

Loadable

This boolean flag allows the context viewer to decide whether expanding an element results in a server call to retrieve additional context data.

menuID

This is the ID for the menu to which this node type links.

isBranch

This boolean flag allows the context viewer to decide whether the node has children. A node can have children as a result of a read from the CCV, or as a result of a user click (which results in a read from the CCV to get the children). If loadable and isBranch are both true then the element will indicate that children are available, but the children will not be read until the user clicks the element.

Example

Example of a context node type:

```
<?xml version="1.0" encoding="UTF-8"?>
<CONTEXTNODETYPE id="CNDT101">
  <loadable value="true"/>
  <menuID value="CNMU101"/>
  <isBranch value="true"/>
</CONTEXTNODETYPE>
```

Adding Right-click Menu Options

It is possible to add menu items that will appear upon right click of an element in the context viewer. This is done via the contextmenu dmx files loaded as initial data.

Setting Attributes for Context Menu

The following attributes can be set for a context menu:

CONTEXTMENU

This attribute holds the ID for the menu. This ID is referenced from a node type definition.

MENUITEM

There can be none, one, or many menu items and they map to one of the right-click options displayed in the context viewer.

MENUITEMLINK

This attribute defines the page or url that will be opened when the right click option is selected.

Menu item links can contain the following:

PAGEPARAM

This defines the page parameter required by the page being opened.

PAGECONFIG

This specifies the javascript window.open options when opening the page on right-click of the menu item.

Example

Example of a context menu:

```
<?xml version="1.0" encoding="UTF-8"?>

<CONTEXTMENU id="CNMU103">

  <MENUITEM value="View Contact Details">

    <MENUITEMLINK
      value="MultidisciplinaryTeamMember_viewModalPage.do">

      <PAGEPARAM value="multidisciplinaryTeamMemberID"/>

      <PAGECONFIG
        value="height=450,width=800,top=100,
          left=100,resizable=yes"/>

    </MENUITEMLINK>

  </MENUITEM>

</CONTEXTMENU>
```

Localizing Citizen Context Viewer Data

Any data that is displayed by the context viewer that is not read directly from application database tables is read via data loaded from message files.

For example, the text that is displayed when case security is set, and a case cannot be viewed in the context viewer, comes from the Context message file. Since the content of the xml tree displayed by the context viewer is built on the server, the localization substitution must also be performed on the server. “Writing a Loader” on page 2 includes sample code where messages are read in localized form.

Compliance

This section explains how to develop in a compliant manner. By following these considerations, customers will also find it easier to upgrade to future versions of Cúram.

Public API

The Citizen Context Viewer has a public API which you may use in your application code. This public API will not have any components changed or removed without following Cúram standards for handling customer impact.

Identifying the API

The JavaDoc shipped is the sole means of identifying which public classes, interfaces and methods form the public API.

Outside the API

The Citizen Context Viewer also contains some public classes, interfaces and methods, which do not form part of the API.

Important: To be compliant, dependencies on any class or interface should not be made. No methods should be called other than those described in the JavaDoc.

Classes, interfaces and methods outside of the public API are subject to change or removal without notice. Unless otherwise stated in the JavaDoc, you must not place any of your own classes or interfaces in the same package as that of the Citizen Context Viewer.

Notices

This information was developed for products and services offered in the United States.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM[®] product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 US

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan Ltd. 19-21, Nihonbashi-Hakozakicho, Chuo-ku Tokyo 103-8510, Japan

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created

programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 US

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data and client examples cited are presented for illustrative purposes only. Actual performance results may vary depending on specific configurations and operating conditions.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Privacy Policy considerations

IBM Software products, including software as a service solutions, (“Software Offerings”) may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering’s use of cookies is set forth below.

Depending upon the configurations deployed, this Software Offering may use session cookies or other similar technologies that collect each user’s name, user name, password, and/or other personally identifiable information for purposes of session management, authentication, enhanced user usability, single sign-on configuration and/or other usage tracking and/or functional purposes. These cookies or other similar technologies cannot be disabled.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM’s Privacy Policy at <http://www.ibm.com/privacy> and IBM’s Online Privacy Statement at <http://www.ibm.com/privacy/details> the section entitled “Cookies, Web Beacons and Other Technologies” and the “IBM Software Products and Software-as-a-Service Privacy Statement” at <http://www.ibm.com/software/info/product-privacy>.

Trademarks

IBM, the IBM logo, and [ibm.com](http://www.ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at “ Copyright and trademark information ” at <http://www.ibm.com/legal/copytrade.shtml>.

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

Java™ and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other names may be trademarks of their respective owners. Other company, product, and service names may be trademarks or service marks of others.



Printed in USA