

IBM Cúram Social Program Management  
Version 7.0.1

*Cúram Web Client Reference Manual*



**Note**

Before using this information and the product it supports, read the information in “Notices” on page 313

**Edition**

This edition applies to IBM Cúram Social Program Management v7.0.1 and to all subsequent releases unless otherwise indicated in new editions.

Licensed Materials - Property of IBM.

© **Copyright IBM Corporation 2012, 2017.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

© Cúram Software Limited. 2011. All rights reserved.

---

# Contents

<b>Figures</b>	<b>vii</b>
----------------	------------

<b>Tables</b>	<b>ix</b>
---------------	-----------

<b>Cúram web client reference</b>	<b>1</b>
-----------------------------------	----------

Cúram web client overview	1
User interface metadata	1
Page content metadata	2
Application user interface overview	4
Cúram applications	7
Page context	8
Page appearance	9
Application controller JSP	9
Direct browsing	10
Web Client Development	10
Outline of the Client Development Process	10
CDEJ Installation	11
CDEJ Project Folder Structure	11
Application Components	14
Component Folders	14
Component Order	15
Component Artifacts	15
Application Locales	16
Building an Application	17
Build Targets	17
Related Build Targets	18
Full and Incremental Builds	19
Dependency Checking	19
Build Logs	19
Error Reporting	19
Server Interface Reference	20
Page Previews	21
UIM Generator Tool	21
External Client Applications	22
Deployment	22
Overview	22
Configuring the Application	22
Customizing the Web Application Descriptor	26
Customization	28
Overview	28
Adding New Artifacts	28
Overriding or Merging Artifacts	28
Externalized Strings	29
Images	29
Image Mapping	30
CuramLinks.properties	31
XML Runtime Configuration Files	31
Login Pages	32
JavaScript Files	32
Cascading Stylesheets	33
Application Configuration Files	34
General Configuration	35
Custom Resources	43
Localization	43
Numbers	43

File Encoding	44
XML Files	44
Java properties files	44
Non-XML Files	45
Locales	45
Non JavaScript property files	45
JavaScript property files	46
UIM Externalized Strings	46
JavaScript Externalized Strings	47
Accessing properties in JavaScript	47
Image.properties	48
Infrastructure Widget Properties Files	48
Frequency Pattern Selector Localization	49
CDEJResources.properties	51
ApplicationConfiguration.properties	51
Application-wide Menu	51
Tabbed Configuration Artifacts	51
Runtime Messages	51
UIM Reference	52
Creating UIM Documents	52
UIM Document Types	52
UIM Pages	53
UIM Views	53
UIM Page Field Level Validations	53
UIM Pages	53
Externalized Strings	54
UIM Reference for Pages and Views	54
Introduction	54
Connection Types	54
ACTION CONTROL	56
ACTION SET	60
CLUSTER	62
CONDITION	68
CONNECT	69
CONTAINER	69
DETAILS_ROW	70
DESCRIPTION	71
FIELD	72
FOOTER_ROW	76
IMAGE	77
INCLUDE	78
INITIAL	78
INFORMATIONAL	78
INLINE PAGE	79
IS_FALSE	80
IS_TRUE	81
JSP SCRIPTLET	81
LABEL	84
LINK	84
LIST	89
MENU	93
PAGE	98
PAGE_PARAMETER	101
PAGE TITLE	101
SCRIPT	102
SERVER INTERFACE	104

SOURCE . . . . .	105	Associating a user with an application . . . . .	173
TAB_NAME . . . . .	105	Build targets required to create a simple application . . . . .	174
TARGET . . . . .	106	Adding a shortcut panel . . . . .	175
TITLE . . . . .	106	Adding a section . . . . .	175
VIEW . . . . .	107	Defining the contents of a section shortcut panel . . . . .	176
UIM Reference for Widgets . . . . .	107	Defining a search tab . . . . .	176
Introduction . . . . .	107	Build targets required to add a shortcut panel . . . . .	179
WIDGET . . . . .	108	Adding tab content . . . . .	179
WIDGET_PARAMETER . . . . .	109	Defining a person tab . . . . .	179
The EVIDENCE_COMPARE Widget . . . . .	109	Build targets required to add tab content . . . . .	183
The FILE_EDIT Widget . . . . .	110	Configuring modal dialogs . . . . .	183
The FILE_UPLOAD Widget . . . . .	116	Opening a modal dialog . . . . .	184
The FILE_DOWNLOAD Widget . . . . .	118	Defining the content of the modal dialog . . . . .	184
The MULTISELECT Widget . . . . .	119	Adding a wizard progress bar . . . . .	186
The SINGLESELECT Widget . . . . .	122	Build targets required to add modals and wizard progress bars . . . . .	191
The RULES_SIMULATION_EDITOR Widget . . . . .	123	Adding tab navigation . . . . .	191
The IEG_PLAYER Widget . . . . .	125	Defining a navigation bar . . . . .	191
Dynamic UIM Cross Reference . . . . .	125	Build targets required to add tab navigation . . . . .	192
Dynamic UIM System Initialization . . . . .	125	Working with lists . . . . .	192
Application Configuration . . . . .	125	Defining an expandable list . . . . .	193
Configuration files . . . . .	126	Defining a list actions menu . . . . .	193
Web client properties . . . . .	127	Build targets required to add lists and list actions . . . . .	195
Customizing the CDEJResources.properties file . . . . .	128	Session Management . . . . .	195
Configuring the browser title . . . . .	128	Session Overview . . . . .	195
Applications . . . . .	128	Tab Restoration . . . . .	196
Application definition . . . . .	129	Session Configuration . . . . .	197
Application optional header . . . . .	136	Session Timeout Warning . . . . .	198
Application example . . . . .	136	Session timeout warning default values . . . . .	198
Associate an application with a user . . . . .	138	Customizing the session timeout warning in the caseworker application . . . . .	199
Sections . . . . .	138	Customizing the session timeout warning in Universal Access . . . . .	201
Section definition . . . . .	140	Customizing the timeout warning in an application . . . . .	202
Section example . . . . .	141	Configuring a customized logon page . . . . .	203
Section shortcut panel . . . . .	142	Tab Session Limitations . . . . .	204
Section shortcut panel definition . . . . .	142	Browser Specific Session Management . . . . .	204
Section shortcut panel example . . . . .	144	Browser Management . . . . .	205
Tabs . . . . .	145	Optimal Browser Support . . . . .	205
Tab definition . . . . .	146	Feature Configuration . . . . .	206
Context panel UIM . . . . .	152	Text Configuration . . . . .	207
Tab example configuration file . . . . .	152	Configuring Browser Back, Refresh, and Close Button Behavior . . . . .	208
Tab actions menu . . . . .	153	Domain-Specific Controls . . . . .	209
Tab actions menu definition . . . . .	153	Dates . . . . .	210
Tab actions menu dynamic support . . . . .	158	Three Field Date Selector . . . . .	210
File download menu item . . . . .	158	Date-Times . . . . .	211
Tab actions menu example configuration file . . . . .	159	Representing Time-Only Values . . . . .	211
Tab navigation . . . . .	160	Customizing the Time Format . . . . .	212
Tab navigation definition . . . . .	160	Frequency Pattern Selector . . . . .	212
Tab navigation dynamic support . . . . .	164	Selection Lists . . . . .	212
Tab navigation example configuration file . . . . .	165	Populated from a Code-Table . . . . .	212
Opening tabs and sections . . . . .	165	Populated from Server Interface Properties . . . . .	213
Using links to open tabs and sections . . . . .	166	Drop-down, Scrollable and Checkboxed List types . . . . .	213
Page to tab and tab to section associations . . . . .	167		
Tab and section page parameters . . . . .	168		
Tab ordering . . . . .	169		
Working with the Cúram user interface . . . . .	169		
Prerequisites for configuring the user interface . . . . .	169		
Creating a simple application . . . . .	169		
Defining an application . . . . .	170		
Adding a section to an application . . . . .	171		
Adding a tab to a section . . . . .	171		
Add a UIM page to a tab . . . . .	172		

Adding an Empty Entry to a List for Non-Mandatory Fields . . . . .	214	Data Conversion Life Cycle. . . . .	263
Enabling Multiple Selection . . . . .	214	The Domain Hierarchy and Domain Plug-ins	264
Transfer List Widget . . . . .	214	Overview of Domain Plug-ins . . . . .	266
User Preferences Editor . . . . .	215	Common Features of Plug-ins . . . . .	266
Rules Trees . . . . .	215	Converter Plug-ins . . . . .	267
Introduction . . . . .	215	Comparator Plug-ins . . . . .	268
Default Rules View . . . . .	215	Default Value Plug-ins . . . . .	268
Summary Rules View. . . . .	216	Domain Plug-in Configuration . . . . .	269
Failed Rules View . . . . .	216	Out-of-the-Box Domain Plug-ins . . . . .	271
Dynamic Rules View . . . . .	216	Extending Existing Plug-ins . . . . .	271
Dynamic Full Tree Rules View. . . . .	219	Converter Plug-ins . . . . .	272
Rules Editor . . . . .	220	Comparator Plug-ins . . . . .	277
Meeting View . . . . .	222	Default Value Plug-ins . . . . .	280
Overview. . . . .	222	Error Reporting . . . . .	280
Single Selection Mode . . . . .	223	Infrastructure Errors . . . . .	280
Multiple Selection Mode. . . . .	223	Exception Classes . . . . .	281
XML Formats . . . . .	223	Custom Exception Classes . . . . .	281
Charts . . . . .	224	Java Object Representations . . . . .	284
Overview. . . . .	224	Customization Guidelines . . . . .	284
Chart appearance . . . . .	224	Where to Start . . . . .	284
Chart configuration . . . . .	225	Custom Formatting . . . . .	285
Chart Data Formats . . . . .	228	Custom Parsing . . . . .	286
Heatmap Widget . . . . .	230	Custom Validation. . . . .	287
Overview. . . . .	230	Custom Sorting. . . . .	289
Configuration . . . . .	230	Custom Error Reporting. . . . .	293
Workflow. . . . .	231	Custom Default Values . . . . .	294
Overview. . . . .	231	Advanced Topics . . . . .	295
Workflow Details . . . . .	231	Type Checking and Null Checking . . . . .	295
Workflow XML Formats. . . . .	232	Plug-in Instance Management . . . . .	295
Evidence View . . . . .	236	Naming Conventions. . . . .	297
Evidence Display Mode . . . . .	236	Generic Parse Operations . . . . .	297
Evidence Comparison Mode . . . . .	236	Code-Tables . . . . .	297
Configuration . . . . .	236	Online Help Development . . . . .	298
Data Format. . . . .	237	Single Source Development. . . . .	298
Calendar . . . . .	239	Integrated Localization . . . . .	298
Payment Statement View . . . . .	242	Automatic Generation . . . . .	298
Batch Function View . . . . .	243	Accessing the Help Page . . . . .	298
Addresses . . . . .	244	Accessibility Features. . . . .	298
Schedule View . . . . .	245	Alternative Text . . . . .	298
Radio Button Group . . . . .	246	Elements of Online Help . . . . .	298
Pop-up Pages . . . . .	247	Introduction to Curam Client Pages . . . . .	298
Configure the Pop-up Page. . . . .	247	Page Descriptions . . . . .	299
Create the Pop-up Page . . . . .	249	Links and Actions . . . . .	299
Using the Pop-up Page . . . . .	251	Fields and Columns . . . . .	299
Using Multiple Pop-up Search Pages for a Single Field . . . . .	252	Adding or Updating Help content . . . . .	299
Configure the Multiple Pop-up Page . . . . .	253	Updating Help for non 'Domain Specific Controls' . . . . .	299
Using the Multiple Pop-up Page . . . . .	253	Updating Help for 'Domain Specific Controls' 300	
Agenda Player . . . . .	254	Maintaining Dynamic UIM Pages . . . . .	300
Agenda Player screen structure . . . . .	254	Working in a Development Environment . . . . .	300
Navigation modes. . . . .	255	Working in a Running System. . . . .	303
Navigator-less View . . . . .	255	Search for Dynamic UIM Pages by Category 303	
Agenda Player Configuration . . . . .	256	Uploading a Dynamic UIM page to the Resource Store . . . . .	303
Agenda Player Customization. . . . .	256	Editing a Dynamic UIM page in the resource store . . . . .	304
Player data . . . . .	257	Deleting a Dynamic UIM File from the Resource Store . . . . .	304
LOCALIZED_MESSAGE Domain. . . . .	261	Validating a dynamic UIM file in the resource store . . . . .	304
Decision Assist: Decision Matrix Widget . . . . .	261	Publish dynamic UIM files . . . . .	304
Overview. . . . .	261		
Custom Data Conversion and Sorting . . . . .	261		
Data Conversion and Sorting Operations . . . . .	262		

Unsupported Features in Dynamic UIM . . . .	304
PAGE . . . . .	305
PAGE TITLE . . . . .	305
CLUSTER . . . . .	305
LIST . . . . .	305
FIELD . . . . .	306
CONTAINER . . . . .	306
ACTION_SET . . . . .	306
WIDGET . . . . .	307
ACTION_CONTROL . . . . .	307
LINK . . . . .	308

INLINE_PAGE . . . . .	309
MENU . . . . .	309
SERVER_INTERFACE . . . . .	309
INFORMATIONAL . . . . .	309
UIM Support in Universal Access . . . . .	309
UIM Support in UA . . . . .	309

**Notices . . . . . 313**

Privacy Policy considerations . . . . .	315
Trademarks . . . . .	315

# Figures

1. Page UIM Example . . . . .	3
2. Application user interface overview . . . . .	4
3. Sample Application .app File . . . . .	8
4. Web Client Folder Structure . . . . .	12
5. Default Preview Values for Domain Definitions	21
6. external-client invocation . . . . .	22
7. Configuring an Application Locale . . . . .	27
8. A Sample Properties File . . . . .	29
9. A Sample Image.properties File . . . . .	30
10. A Sample ImageMapConfig.xml file . . . . .	31
11. Error_Page Section Example . . . . .	35
12. Error_Page Section Example with one default page . . . . .	35
13. Multiple Select Section Example. . . . .	36
14. Disable Collapsible Clusters Example . . . . .	36
15. Append Colon Section Example. . . . .	36
16. Admin Section Example . . . . .	36
17. Static Content Base URL Example . . . . .	36
18. Relative URL Example . . . . .	37
19. Zip Target Example . . . . .	37
20. Response Headers . . . . .	37
21. Field Error Indicators Example . . . . .	38
22. Security Check on Page Load Example	38
23. Enable Select All Check-box Example . . . . .	39
24. Transfer Lists Mode Example . . . . .	39
25. Hide Conditional Links . . . . .	39
26. Disable Auto Complete . . . . .	39
27. Scrollbar Configuration . . . . .	40
28. Sample Pagination Configuration . . . . .	40
29. Extract from curam-config.xml File (1) . . . . .	41
30. Extract from curam-config.xml File (2) . . . . .	42
31. Sample address-config.xml File . . . . .	42
32. Accessing a property . . . . .	47
33. Connection Types Example . . . . .	55
34. Example Configuration for File Download	57
35. Example of a FOOTER_ROW in a List.	77
36. Example JSP SCRIPTLET Accessing a TextHelper . . . . .	82
37. Example JSP SCRIPTLET Redirecting to a Page	82
38. Example JSP_SCRIPTLET Redirecting and Accessing a TextHelper . . . . .	83
39. Example of a Dynamic LABEL. . . . .	84
40. Example of Dynamic MENU Data . . . . .	95
41. Example of a DYNAMIC Menu Configuration File	95
42. Example of an INTEGRATED_CASE Menu Configuration File . . . . .	95
43. Example of the IN_PAGE_NAVIGATION menu in UIM . . . . .	96
44. An example of wizard-type menu UIM	97
45. Example of the required properties in the resource store property file . . . . .	98
46. Sample Template Details . . . . .	112
47. MULTISELECT Example . . . . .	120
48. Application User Interface Overview	126
49. Simple.app . . . . .	137
50. CT_APPLICATIONCODE.ctx . . . . .	138
51. Application User Interface Overview	139
52. SimpleWorkspaceSection.sec . . . . .	141
53. SimpleShortcutPanel.ssp . . . . .	144
54. Application User Interface Overview	145
55. SimpleTab.tab . . . . .	153
56. FILE_DOWNLOAD Configuration from curam-config.xml . . . . .	159
57. SimpleMenu.mnu . . . . .	159
58. SimpleNavigation.nav. . . . .	165
59. SimpleApp app . . . . .	170
60. SimpleAppHomeSection.sec. . . . .	171
61. SimpleHome.tab . . . . .	172
62. SimpleHome.uim . . . . .	172
63. Users.dmx . . . . .	173
64. CT_APPLICATION_CODE.ctx . . . . .	174
65. SimpleApp.app . . . . .	175
66. SimpleAppWorkspaceSection.sec . . . . .	175
67. SimpleShortcutPanel.ssp . . . . .	176
68. SimpleSearch.tab . . . . .	176
69. Person Search Page . . . . .	177
70. SimpleSearch.uim . . . . .	178
71. SimplePerson tab . . . . .	180
72. SimplePersonContext.uim . . . . .	180
73. SimplePerson uim . . . . .	182
74. SimplePerson uim . . . . .	184
75. CreateEmployments.uim . . . . .	185
76. CreateEmploymentWizard.properties	186
77. CreateEmploymentWizard_pageOne.uim	188
78. CreateEmploymentWizard_pageTwo.uim	190
79. SimplePerson Tab . . . . .	192
80. SimplePersonNav.nav. . . . .	192
81. SimpleSearch.uim . . . . .	193
82. SimpleSearch.uim . . . . .	194
83. Customizing the date format . . . . .	210
84. Customizing the Date-Time format . . . . .	211
85. Selection List on an Insert Page . . . . .	213
86. Selection List on a Modify Page . . . . .	213
87. Enabling multiple selection in curam-config.xml . . . . .	214
88. Sample RulesDecisionConfig.xml File	217
89. Example of Decision ID Sourced from a Bean	218
90. Example of Rules Tree Items with Summary Flag. . . . .	219
91. Sample RulesEditorConfig.xml File . . . . .	221
92. Example of Decision ID Sourced from a Bean	222
93. Sample Horizontal Bar Chart XML . . . . .	229
94. Workflow . . . . .	232
95. Calendar XML Stream . . . . .	240
96. CalendarConfig.xml Example . . . . .	242
97. A Sample PaymentStatement.properties File	243
98. Address Configuration in curam config xml	244
99. UIM Example of Schedule View . . . . .	246
100. Pop-up Configuration Example . . . . .	247
101. Opening a Pop-up from an Insert Page	252
102. Opening a Pop-up from a Modify Page	252
103. Supplying Parameters to a Pop-up Page	252

104. Multiple Pop-up Domains . . . . .	253	115. Custom Parsing for Currency Values	287
105. UIM to Use Multiple Pop-up Windows	254	116. Custom Validation for Odd Numbers	288
106. Condition example: . . . . .	261	117. Custom Validation Failure Message . . . . .	288
107. Sample Domain Configuration . . . . .	269	118. Configuration for Custom Validation	289
108. Custom Exception Class . . . . .	282	119. Sorting Strings Numerically. . . . .	290
109. Custom Message Catalog . . . . .	282	120. Sorting Formatted Values . . . . .	291
110. Throwing a Custom Exception . . . . .	283	121. Sorting Zero Dates. . . . .	292
111. Throwing Multiple Exceptions . . . . .	284	122. Configuration for Custom Sorting. . . . .	292
112. Custom Formatting for Currency Values	285	123. Custom Error Reporting . . . . .	294
113. Configuration for Custom Formatting	286	124. Custom Pattern Match Failure Message	294
114. Custom Formatting without Grouping	286	125. Custom Default Date-Time Value . . . . .	295



# Tables

1. Environment Variables . . . . .	18	50. Child Elements of the TITLE Element	107
2. Pagination configuration options . . . . .	40	51. Child Elements of the VIEW Element	107
3. Placeholders used in Frequency Pattern Selector . . . . .	49	52. Attributes of the WIDGET Element . . . . .	108
4. Properties used for the Frequency Pattern Selector . . . . .	50	53. Child Elements of the WIDGET Element	108
5. Attributes of the ACTION_CONTROL Element	57	54. Attributes of the WIDGET_PARAMETER Element . . . . .	109
6. Child Elements of the ACTION_CONTROL Element. . . . .	60	55. Child Elements of the WIDGET_PARAMETER Element . . . . .	109
7. Attributes of the ACTION_SET Element	61	56. Parameters to the EVIDENCE_COMPARE Widget. . . . .	109
8. Child Elements of the ACTION_SET Element	62	57. Parameters to the FILE_EDIT Widget	111
9. Attributes of the CLUSTER Element . . . . .	62	58. FILE_EDIT Widget Configuration settings summary . . . . .	113
10. Child Elements of the CLUSTER Element	64	59. Parameters to the FILE_UPLOAD Widget	117
11. Attributes of the CONDITION element	68	60. Parameters to the FILE_DOWNLOAD Widget	118
12. Child Elements of the CONDITION Element.	68	61. Parameters to the MULTISELECT Widget	121
13. Child Elements of the CONNECT Element	69	62. Parameters to the SINGLESELECT Widget	123
14. Attributes of the CONTAINER Element	69	63. Parameters to the RULES_SIMULATION_EDITOR Widget. . . . .	124
15. Child Elements of the CONTAINER Element	70	64. Configuration Files. . . . .	127
16. Attributes of the DETAILS_ROW Element	71	65. Attributes of the application Element	129
17. Child Elements of the INFORMATIONAL Element. . . . .	71	66. Supported Child Elements of the application Element . . . . .	131
18. Attributes of the DESCRIPTION Element	71	67. Supported child elements of the application-menu element . . . . .	131
19. Child Elements of the DESCRIPTION Element	71	68. Attributes of the application-search element	132
20. Attributes of the FIELD element . . . . .	72	69. Supported child elements of the application-search element . . . . .	132
21. Child Elements of the FIELD Element. . . . .	75	70. Supported child elements of the search-pages element . . . . .	133
22. Child Elements of the FOOTER_ROW Element	77	71. Attributes of the search-page element	133
23. Attributes of the IMAGE Element . . . . .	77	72. Attributes of the further-options element	134
24. Attributes of the INCLUDE Element . . . . .	78	73. Attributes of the section-ref element . . . . .	134
25. Attributes of the INITIAL Element . . . . .	78	74. Attributes of the timeout-warning element	135
26. Child Elements of the INFORMATIONAL Element. . . . .	79	75. Attributes of the section Element . . . . .	140
27. Attributes of the INLINE_PAGE Element	79	76. Supported Child Elements of the section Element . . . . .	140
28. Child Elements of the INLINE_PAGE Element	80	77. Attributes of the tab element . . . . .	141
29. Attributes of the IS_FALSE Element . . . . .	81	78. Attributes of the shortcut-panel-ref element	141
30. Attributes of the IS_TRUE Element. . . . .	81	79. Attributes of the section-shortcut-panel Element . . . . .	142
31. Child Elements of the LABEL Element . . . . .	84	80. Supported Child Elements of the section-shortcut-panel Element. . . . .	142
32. Attributes of the LINK Element. . . . .	85	81. Attributes of the node element. . . . .	143
33. Child Elements of the LINK Element . . . . .	88	82. Attributes of the tab-config Element . . . . .	147
34. Attributes of the LIST Element . . . . .	89	83. Supported Child Elements of the tab-config Element . . . . .	147
35. Child Elements of the LIST Element . . . . .	92	84. Attributes of the page-param Element	148
36. Attributes of the MENU Element . . . . .	94	85. Attributes of the menu element . . . . .	148
37. Child Elements of the MENU Element . . . . .	94	86. Attributes of the context element . . . . .	148
38. Properties in the wizard defining resource	98	87. Attributes of the navigation element . . . . .	149
39. Attributes of the PAGE Element. . . . .	99	88. Attributes of the smart-panel element	150
40. Child Elements of the PAGE Element	100	89. Supported child elements of the tab-refresh element . . . . .	151
41. Attributes of the PAGE_PARAMETER Element . . . . .	101	90. Attributes of the onload/onsubmit Elements	151
42. Attributes of the PAGE_TITLE Element	102	91. Attributes of the menu-bar element . . . . .	154
43. Child Elements of the PAGE_TITLE Element	102		
44. Attributes of the SCRIPT Element. . . . .	103		
45. Attributes of the SERVER_INTERFACE Element . . . . .	104		
46. Attributes of the SOURCE Element . . . . .	105		
47. Child Elements of the TAB_NAME Element	106		
48. Attributes of the TARGET Element . . . . .	106		
49. Attributes of the TITLE Element . . . . .	106		

92. Supported child elements of the menu-bar element . . . . .	154	115. Attributes for CONFIG element . . . . .	230
93. Attributes of the menu-item element . . . . .	154	116. Attributes of a Node . . . . .	233
94. Attributes of the submenu element . . . . .	156	117. Attributes of an Edge . . . . .	234
95. Supported child elements of the submenu element . . . . .	156	118. Attributes of Workflow CONFIG element . . . . .	235
96. Attributes of the menu-separator element . . . . .	157	119. EVENT attributes in schema . . . . .	240
97. Supported child elements of the loader-registry element . . . . .	157	120. SINGLE_DAY_EVENT attributes in schema . . . . .	241
98. Attributes of the loader Element . . . . .	157	121. Calendar View Type Values . . . . .	241
99. Attributes of the navigation element . . . . .	160	122. Parameters Passed to Event Description Pages . . . . .	242
100. Supported child elements of the navigation element . . . . .	161	123. Address Format configurations . . . . .	245
101. Supported child elements of the nodes element . . . . .	161	124. Attributes of the POPUP_PAGE element. . . . .	248
102. Attributes of the navigation-group element . . . . .	161	125. Child elements of the POPUP_PAGE element. . . . .	248
103. Supported child elements of the navigation-group element . . . . .	162	126. Attributes of the PLAYER element . . . . .	256
104. Attributes of the navigation-page element . . . . .	162	127. Attributes of the page element . . . . .	259
105. Supported child elements of the loader-registry element . . . . .	163	128. Behavior of the Abstract Plug-in Classes . . . . .	271
106. Attributes of the loader element . . . . .	164	129. Out-of-the-Box Converter Plug-ins . . . . .	272
107. Tab Opening Rules. . . . .	168	130. Behavior of the Format Operations . . . . .	273
108. Files required to create an application and corresponding build targets. . . . .	174	131. Behavior of the Parse Operations . . . . .	275
109. Files required to add a shortcut panel and corresponding build targets. . . . .	179	132. Behavior of the Pre-Validate Operations . . . . .	276
110. Files required to add tab content and corresponding build targets. . . . .	183	133. Out-of-the-Box Comparator Plug-ins . . . . .	277
111. Files required to add modal dialogs and corresponding build targets. . . . .	191	134. Collation strength summary . . . . .	279
112. Files required to add tab navigation and corresponding build targets. . . . .	192	135. Out-of-the-Box Default Value Plug-ins . . . . .	280
113. Files required to add an expandable list and a list actions menu, and corresponding build targets . . . . .	195	136. Classes Used for Java Object Representations . . . . .	284
114. Attributes of the CONFIG element . . . . .	227	137. Unsupported PAGE Features . . . . .	305
		138. Unsupported PAGE_TITLE Features . . . . .	305
		139. Unsupported CLUSTER Features . . . . .	305
		140. Unsupported LIST Features . . . . .	306
		141. Unsupported FIELD Features . . . . .	306
		142. Unsupported CONTAINER Features . . . . .	306
		143. Unsupported ACTION_SET Features . . . . .	307
		144. Unsupported WIDGET Features . . . . .	307
		145. Unsupported ACTION_CONTROL Features . . . . .	307
		146. Unsupported LINK Features . . . . .	308
		147. Unsupported INLINE_PAGE Features . . . . .	309
		148. Unsupported MENU Features . . . . .	309
		149. Unsupported SERVER_INTERFACE Features . . . . .	309
		150. UIM in the Universal Access . . . . .	310

---

## Cúram web client reference

Provides a reference for the Cúram web client application. The Cúram web client has an HTML user interface that is generated by a middle-tier web application. It conforms to the Java EE architecture and is driven by JavaServer pages and servlet technology that is based on the Apache Struts framework. This HTML user interface uses standard browser and Web 2.0 technologies, including JavaScript and cascading style sheets.

### Related concepts:

“Working with the Cúram user interface” on page 169

Use this information to develop user interface elements with the Cúram Client Development Environment for Java. User interface elements that can be created with the Cúram Client Development Environment for Java include shortcut panels, tabs, modal dialogs, tab navigation, and lists.

---

## Cúram web client overview

Learn about the concepts and terminology that are related to the Cúram Client Development Environment (CDEJ).

A basic understanding of Java EE development environments, XML and Web technologies such as Hypertext Transfer Protocol (HTTP), JavaServer Pages (JSP), Cascading Style Sheets (CSS) and JavaScript is helpful, but not required.

- Cúram web application development is simplified by describing pages and applications in terms of their content and flow rather than the graphical look-and-feel and layout of the content.
- User interface metadata (UIM) consists of definitions in XML format that describe the contents, and, to a certain extent, the layout, of one of the main elements in the Cúram user interface, a UIM page.
- An application is a collection of user interface elements, predominantly based on UIM pages, combined to create specific content for a particular user or role.
- Graphical layout options available to a developer are restricted to enforce a consistent user interface across the whole application.

## User interface metadata

User interface metadata (UIM) is an XML language that describes the contents and layout of one of the main elements in the Cúram user interface, a UIM page.

UIM limits the variety of interface layout options that are available to developers, and defaults user interface characteristics based on the known formats of server interfaces. Consequently, the UIM is kept simple and the user interface layout has an enforced consistency across the whole application.

The developer creates the UIM page definitions in files with a .uim extension, with each file corresponding to a single page.

Individual pages are made up from different elements such as page titles, labels, buttons, and links as well as the most important element, the data content. UIM focuses on defining elements rather than how they are graphically laid out. The CDEJ provides the tools to generate client screens from UIM definitions.

## Page content metadata

Users can display and enter server data in the main content area of an application. Page content metadata is used to create the content area. The basic unit of data is a field. Each field is either an output or input parameter of a server interface.

Various XML elements correspond to the user interface elements such as `PAGE`, `FIELD`, `CLUSTER`, `LIST`, `ACTION_CONTROL`, `ACTION_SET` and so on. The `CONNECT` element is an important construct that allows fields to be associated with parameters to server interfaces. As well as mapping fields, connections can also map page parameters and static text. The latter is not stored directly in the UIM, but is externalized in a property file which facilitates easier language localization of user interfaces.

Other XML elements, such as `PAGE_PARAMETER` and `SERVER_INTERFACE`, do not have visual representations in a UIM page but are important to the functionality of the page. A server interface is a method that has been implemented using the Cúram Server Development Environment (SDEJ). Each UIM page can be associated with one or more server interface methods. Each method is associated with either the initialization phase or the process phase. When the UIM page is first opened, the initialization phase methods are executed. Typically an initialization phase method uses page parameters as input parameters, and the resulting server data is mapped to output fields on the screen.

The process phase is initiated when an action control of type **Submit** is selected by the user. Data from input fields on the screen are mapped to input parameters of process phase server methods and the methods are invoked. After execution of process phase methods, the flow of control is determined by the **Submit** action, which can specify a link to a new target page, or by the default action which returns to the same page.

The following example shows an extract of UIM used to create the content area. The extract displays how the major elements that make up a screen of content area, such as clusters and lists, are represented in UIM.

```

<PAGE PAGE_ID="Person_search">

  <PAGE_TITLE>
    <CONNECT>
      <SOURCE NAME="TEXT"
        PROPERTY="PageTitle.StaticText1"/>
    </CONNECT>
  </PAGE_TITLE>

  <SERVER_INTERFACE NAME="ACTION"
    CLASS="Person_fo"
    OPERATION="search"
    PHASE="ACTION" />

  <CLUSTER NUM_COLS="2"
    TITLE="Cluster.Title.SearchCriteria">

    <FIELD LABEL="Field.Label.ReferenceNumber">
      <CONNECT>
        <TARGET NAME="ACTION" PROPERTY="referenceNumber"/>
      </CONNECT>
    </FIELD>

    <FIELD CONTROL="SKIP"/>

  </CLUSTER>

  <CLUSTER NUM_COLS="2"
    TITLE="Cluster.Title.AdditionalSearchCriteria">

    <FIELD LABEL="Field.Label.FirstName">
      <CONNECT>
        <TARGET NAME="ACTION" PROPERTY="forename"/>
      </CONNECT>
    </FIELD>

    ... more <FIELD> elements...

  <ACTION_SET ALIGNMENT="CENTER" TOP="false">

    <ACTION_CONTROL LABEL="ActionControl.Label.Search"
      IMAGE="SearchButton"
      TYPE="SUBMIT">
      <LINK PAGE_ID="THIS"/>
    </ACTION_CONTROL>

    <ACTION_CONTROL LABEL="ActionControl.Label.Reset"
      IMAGE="ResetButton">
      <LINK PAGE_ID="Person_search"/>
    </ACTION_CONTROL>

  </ACTION_SET>
</CLUSTER>

<LIST TITLE="List.Title.SearchResults">

  <FIELD LABEL="Field.Title.Name" WIDTH="44">
    <CONNECT>
      <SOURCE NAME="ACTION"
        PROPERTY="personName"/>
    </CONNECT>
  </FIELD>
  ... more <FIELD> elements...
</LIST>

</PAGE>

```

Figure 1. Page UIM Example

## Related reference:

“UIM Reference” on page 52

Learn about the Cúram User Interface Meta-data (UIM) format used to specify the contents of the Cúram web application client pages.

## Application user interface overview

The application user interface contains elements that are implemented through user interface metadata. Other topics in the section describe how each of the user interface elements can be configured in an application.




Figure 2. Application user interface overview

The following list describes the user interface elements with cross-references to the numbered annotations in the previous figure.

### Application banner (1)

An application is defined to present a specific view of the data for a user or user role. The application banner provides the user with the context of the application they are currently accessing. The banner also include a number of application links, such as Help, Logout and Preferences, and an application search facility.

### Application name (1.1)

A name is defined for an application.

### Welcome message (1.2)

A welcome message is displayed.

#### **Application menu (1.3)**

The application menu forms part of the application banner, and allows for the optional addition of up to three links. You can add a link to the application help, a link to logout from the application and a link to open the user preferences dialog.

#### **Application search (1.4)**

The application search element provides a search function.

#### **Application sections (2)**

An application contains a number of sections that allow quick and easy access to some of the more common tasks and activities performed by a user.

#### **Application tab (3)**

Content in a section is displayed in a tab, and each section can open multiple tabs, where each tab represents a business object or logical grouping of information. A tab can also be described as a logical grouping of UIM pages.

#### **Tab title bar (4)**

The tab title bar contains text that identifies the current tab.

#### **Tab actions menu (5)**

The actions menu provides actions associated with the business object represented by the tab.

#### **Tab context panel (6)**

A tab contains a context panel, which contains context information associated with the data displayed in the tab. This context information is always available when working with the data on the tab.

#### **Section shortcut panel (7)**

Each section can optionally have a section shortcut panel, which is collapsed by default. When expanded the shortcut panel provides quick links to open content, in the form of UIM pages, and perform actions within the section. The content in the section shortcut panel is organized into categories of menu items. The section shortcut panel contains section shortcut categories (7.1), each of which contains quick links in the form of section shortcut menu items (7.1.1).

#### **Content area tab navigation bar (8)**

A tab comprises of one or more pages of information, represented by UIM pages. These pages can be navigated using a navigation bar, which contains navigation tabs linking to single pages or sets of pages. Where a navigation tab links to a set of pages, a page group navigation bar is displayed.

#### **Page title (9)**

A title can be defined for a whole UIM page.

#### **Page action control (10)**

An action control can be associated with a UIM page. See Action controls (19).

**Refresh button (11)**

An action control that refreshes the user interface content.

**Print button (12)**

An action control that can be used to print user interface content.

**Help button (13)**

An action control that displays help content in a new window.

**In-page navigation tabs (14)**

A page can contain several tabs of information.

**Page content area (15)**

The page content area displays the currently selected UIM page.

**Page group navigation bar (16)**

Where a tab links to a set of pages, the pages are displayed as a page group navigation bar, with the first one selected by default.

**Fields (17)**

Fields are visually organized into clusters and lists on a UIM page. There may be zero or more of each on a page. Clusters and lists can have a title which describes the type of data displayed.

**Clusters (18)**

A cluster is a rectangular area that displays fields in a tabular format. A cluster can have one or more columns of fields, and fields can be displayed with or without an associated label. Fields can be read-only, or they may be editable. If editable, they appear as a control such as a text area, drop-down menu, or check-box. The figure shows an example of two configured clusters in the page content area, each with a configured title.

**Action controls (19)**

Action controls, displayed as buttons, are used to submit form data, to link to related pages, or to open a modal dialog. Action controls can be organized into action sets which are associated with clusters, lists, or the UIM page (see element 10 in the figure). Individual action controls can also be associated with a single field in a cluster or a column in a list. When an action control is used to link to another page it can also send parameters to the target page which are normally used as keys to retrieve server data that populates the target page. By default action controls appear at the top and bottom of the widget they are associated with.

**Smart panel (20)**

The smart panel displays extra contextual information, such as quick notes that relate to a case, or advice that was given to a client.

**Lists (21)**

A list is used to display rows of repeating or indexed fields. As in clusters, fields can have associated labels which are displayed as column headings in the list. A list action menu (21.1) is displayed at the end of the row for each list item and contains all the actions that are associated with the list item.

**Related concepts:**



“Cúram applications”

When a user logs into the Cúram application they are presented with a view that is specific to their role, which is an application. An application in the Cúram user interface is a collection of user interface elements, mainly based on UIM pages, combined to create specific content for a particular user or role.

**Related reference:**

“Application Configuration” on page 125

An application in the Cúram user interface is a collection of user interface elements, based on UIM pages, that are combined to create specific content for a particular user or role. Develop Cúram web client applications by configuring application configuration files.

## Cúram applications

When a user logs into the Cúram application they are presented with a view that is specific to their role, which is an application. An application in the Cúram user interface is a collection of user interface elements, mainly based on UIM pages, combined to create specific content for a particular user or role.

In addition to defining the layout of the screen, an application controls the flow between pages available in the application. Within an application, links to other pages are available from a section shortcut panel, the tab navigation bar and page group navigation bar, in addition to links on the page displayed in the content area.

Activating any of these links will result in accessing a new page in the content area, or opening a new page in a modal dialog. For new pages in the content area, the application definition is used to determine what tab the page belongs to and what section the relevant tab belongs to. The page is then opened in the context of the relevant section and tab.

Applications are defined in an XML format using a number of different files. For example, an application is defined using an XML file with the extension `.app`. Each section referenced in the application is defined using an XML file with the extension `.sec` and any tabs referenced by the section are defined using an XML file with the extension `.tab`.

In the following example, an application configuration `.app` file creates an application containing two sections, in addition to an application banner with a quick search facility:

```

<?xml version="1.0" encoding="UTF-8"?>
<ac:application
  id="SimpleApp"
  title="SimpleApp.title"
  subtitle="SimpleApp.subtitle"
  user-message="SimpleApp.UserMessage">

  <ac:application-menu>
    <ac:preferences title="preferences.title"/>
    <ac:help title="help.title"/>
    <ac:logout title="logout.title"/>
  </ac:application-menu>

  <ac:application-search>
    <ac:search-pages>
      <ac:search-page type="SAS01"
        description="Search.Person.LastName.Description"
        page-id="Person_searchResolver"
        initial-text="Search.Person.LastName.InitialText"
        default="true"/>
      <ac:search-page type="SAS02"
        description="Search.Person.Gender.Description"
        page-id="Person_listByGender"
        initial-text="Search.Person.Gender.InitialText" />
    </ac:search-pages>
    <ac:further-options-link
      description="Search.Further.Options.Link.Description"
      page-id="Person_search" />
  </ac:application-search>

  <ac:section-ref id="SimpleHomeSection"/>
  <ac:section-ref id="SimpleWorkspaceSection"/>

</ac:application>

```

Figure 3. Sample Application .app File

The separation of configuration into multiple files allows for reuse of different elements across multiple applications. For example, a common inbox section can be defined and referenced by multiple applications.

**Related concepts:**

“Application user interface overview” on page 4

The application user interface contains elements that are implemented through user interface metadata. Other topics in the section describe how each of the user interface elements can be configured in an application.

**Related reference:**

“Application Configuration” on page 125

An application in the Cúram user interface is a collection of user interface elements, based on UIM pages, that are combined to create specific content for a particular user or role. Develop Cúram web client applications by configuring application configuration files.

## Page context

UIM pages are displayed in different contexts within an application. The context the UIM page is displayed in may result in different behavior for some of the elements.

The main contexts that UIM pages are displayed in are outlined in the following list:

- **Content Area**

The content area is where the main content for an application is displayed. When a UIM page is displayed in the content area it will automatically contain a refresh, help and print button within its title bar. Refer to user interface element 15 of “Application user interface overview” on page 4 to see an example of a configured content area.

**Note:** The Cúram application does not support the web browser **File > Print** functionality. A print button is provided for printing the contents of the Content Area only.

- **Context Panel**

A context panel displays a specific kind of UIM page that displays common information for the tab that is always viewable. Refer to user interface element 6 of “Application user interface overview” on page 4 to see a configured example of context panel.

- **List Dropdown Panel**

A list dropdown panel displays a UIM page when a list row is expanded in a list. Expanded rows are a supported feature of lists. Refer to user interface element 21 of “Application user interface overview” on page 4 to see unexpanded list items (toggle buttons) in a list. Refer to “LIST” on page 89 for more information.

- **Modal Dialog**

A modal dialog displays a UIM page in a dialog window, displayed above the main content. While the dialog is open, the parent content cannot be accessed. See “Modal Dialogs” on page 88 for more information.

- **Smart Panel**

A smart panel, is an optional panel that can be added to the right of the content area in a tab and displays a UIM page. For more information see “Tab smart-panel element” on page 149. Refer to see user interface element 20 of “Application user interface overview” on page 4 to see an example of a configured smart panel in an application.

## Page appearance

In the Cúram client development, the application and page metadata provide limited scope to specify the position and layout of user interface elements.

Note the position and layout of the following features:

- The application banner, sections, and tabs are in fixed positions.
- Clusters and lists flow from top to bottom on a page.
- Fields are automatically positioned within the previous user interface elements.

Some control is allowed through attributes of the various elements, but sensible defaults are provided for all these attributes to minimize the situations where they must be used. Refer to user interface element 19 of “Application user interface overview” on page 4 to see how action controls are aligned to the center of a cluster. The action controls were aligned by configuring the ALIGNMENT attribute of the ACTION\_SET element in “Page content metadata” on page 2.

## Application controller JSP

A single JavaServer Pages (JSP) file, AppController.do, renders the Cúram client on the browser. Therefore, the URL in the browser always ends with

AppController.do. The URL does not change as the user navigates between separate pages within the Cúram application. Therefore, the browser back button is not supported.

It is still possible to request the URL of a specific page in the browser. In this scenario, on receipt of the request, the browser is automatically redirected to AppController.do, which loads the requested page. See “Direct browsing” for details.

## Direct browsing

You can access a page directly by typing its full URL into the browser's navigation bar, for example, `http://host:port/Curam/en_US/SomePage.do`. The process by which the page is loaded depends on whether the page is associated with a tab.

If you access a page directly, the session and its associated tabs will first be restored, then a request will be sent for the specified page. The page will then be loaded in its associated section and tab. However, if this page is not associated with a tab, it will be loaded in the currently selected tab. In the case of a new session, this will be the **Home** tab.

Tabs changed in this way can be returned to their default state by closing and reopening the tab where possible. For the **Home** tab; logging out and back into the application will restore the **Home** tab to the user's default home page. See “Tab Restoration” on page 196 for more information about tab restoration and session management.

---

## Web Client Development

Use this information to understand the structure of the Cúram web client application project, including related files in the Cúram server project, and how to develop, build and deploy the application.

The Cúram CDEJ translates files specified in UIM (User Interface Meta-data) format into the JavaServer Pages (JSP) that will be deployed on your web application server. These UIM files are supported by various properties files, configuration files, and others. Collectively, these files are called the application's *artifacts*.

Your Cúram web client application project can be divided into various functional components for ease of development. With this system, application changes and updates can be introduced by dropping in a new component that will automatically override the artifacts of another component, where appropriate. The location and purpose of these artifacts and components will be described in detail in this chapter.

## Outline of the Client Development Process

Much of the client development process is driven by executing specific build scripts. The following is an outline of the typical steps in the process:

1. Install the Cúram Application and the Cúram CDEJ. Directions to the installation guide are provided in “CDEJ Installation” on page 11.
2. The installer creates both an server application and client application project on your file system containing all the source files. These files will include the application configuration files, the XML-based User Interface Metadata (UIM) for all your pages, any images and other resources that the application requires.

3. Create and edit your source files (UIM and application configuration files) or customize existing files.
4. Deploy your application to an application server. During development, this might be a server embedded in your integrated development environment.
5. Once deployed, you can test your application using a web browser, for example using the following URL:  
`http://localhost:9080/'server_name'/AppController.do`

## CDEJ Installation

To install the Cúram CDEJ, follow the instructions contained in the *Cúram Installation Guide*. The installer will install the Cúram CDEJ and the Cúram Application project ready for further development and customization. The Cúram Application is divided into two major parts: the server application that defines the business entities and business logic of the application, and the web client application that defines how this information is presented to the user.

In this manual, the folders into which parts of the application and the infrastructure are installed will be referred to using placeholders, as the actual locations will vary depending on where they are installed and whether or not you are developing the Cúram Application, additional applications or samples.

### Folder Placeholders

#### **<app-dir>**

The top-level application folder containing both the server application and the client application.

#### **<client-dir>**

The folder containing the web client application. Typically this is a folder called `webclient` within the `<app-dir>` folder.

#### **<server-dir>**

The folder containing the server application. Typically this is a folder called `EJBServer` within the `<app-dir>` folder.

#### **<cdej-dir>**

The folder containing the Cúram CDEJ, the tools and infrastructure required to build and run web client applications. Typically this is a folder called `CuramCDEJ`.

#### **<sdej-dir>**

The folder containing the Cúram SDEJ, the tools and infrastructure required to build and run server applications. Typically this is a folder called `CuramSDEJ`. More information on this folder can be found in the *Cúram Server Developers Guide*

For example, if you have installed the Cúram Application into the folder `C:/Curam`, then the `<app-dir>` placeholder refers to this folder, the `<client-dir>` placeholder refers to the `C:/Curam/webclient` folder, the `<server-dir>` refers to the `C:/Curam/EJBServer` folder, and the `<cdej-dir>` refers to the `C:/Curam/CuramCDEJ` folder.

## CDEJ Project Folder Structure

A Cúram web client application project is organized into a folder structure that is recognized by the Cúram CDEJ when the application is built. “CDEJ Project Folder Structure,” shows an outline of this folder structure for the project and the list that follows describes each folder within this structure in more detail. The base folder

of this structure is the <client-dir> folder.

```
<client-dir>
+ build
  + bean-doc
+ buildlogs
+ components
  + core
  + <custom>
    + Images
    + javasource
    + WebContent
+ JavaSource
+ project
+ WebContent
  + <locale>
  + Previews
  + WEB-INF
```

Figure 4. Web Client Folder Structure

### Web Client Folders

**build** Temporary generated artifacts. The only contents of interest are the generated reference documentation for the façade server interfaces.

#### **build/bean-doc**

Generated reference documentation for the façade server interfaces in HTML format. These are regenerated each time the application model changes. See “Server Interface Reference” on page 20 for more details.

#### **buildlogs**

Log files generated from each build. See “Build Logs” on page 19 for more details.

#### **components**

The top-level folder for the application components. Each sub-folder of this folder contains a separate application component. See “Application Components” on page 14 for more information on application components.

#### **components/core**

The pre-defined core Cúram application component artifacts that provide the core functionality. These artifacts should not be modified directly. To change them, you should create new artifacts in another component which will then override the core artifacts.

#### **components/<custom>**

One or more extra application components containing artifacts that add additional application functionality or customize existing functionality.

#### **components/<custom>/Images**

Arbitrary custom resources that you want to deploy with your application. Files and folders within this folder will be copied to the top-level WebContent folder during the build process.

#### **components/<custom>/jasource**

Javasource code and properties files used to add extra functionality to an application or to define externalized strings used across many application pages. There are a number of different customizations that can be applied to files within this directory. These include updates to control one or more of the data conversion or sorting operations. Please refer to “Custom Data Conversion and Sorting” on page 261 for more details on these customizations. This javasource directory is optional, however if this

directory is added, the `webclient/.classpath` file must be updated to reference this new source directory. This ensures that the changes in this directory are recompiled when a client build is run within the specified development environment. The following is an entry in the `webclient/.classpath` file, (where `<custom>` represents the name of a custom directory):

```
<classpathentry kind="src" path="components/<custom>/javasource"/>
```

#### **components/<custom>/WebContent**

Arbitrary custom resources that you want to deploy with your application. Files and folders within this folder will be copied to the top-level `WebContent` folder during the build process.

#### **JavaSource**

Contains the `Initial_ApplicationConfiguration.properties` file, that is described in “Configuring the Application” on page 22.

#### **project**

Configuration files used when customizing the application deployment descriptors. See “Customizing the Web Application Descriptor” on page 26 for more details.

#### **WebContent**

The generated web application files. This contains the generated JSP files and other application artifacts that can be used to start and test an application in the development environment. When an application is to be deployed outside of the development environment, many of the files in this folder are packaged in the application EAR file. See “Deployment” on page 22 for more details.

#### **WebContent/<locale>**

The generated JSP files for each locale supported by the application are placed in folders named after the locales. For example, for American English pages there will be a folder named `en_US`. These JSP files are generated as necessary when the application is built, so they will be replaced automatically if deleted or out of date with respect to the corresponding UIM file. The JSP files are placed in sub-folders of the locale folder using the first two letters of the page ID as the sub-folder name. This reduces the likelihood that an option provided by some application server software to pre-compile the JSP files will fail when trying to pre-compile too many JSP files at the same time.

#### **WebContent/Previews**

Generated HTML files providing a rough preview of what each corresponding JSP will look like when the application is running. These previews can be viewed directly in a web browser without running the application. See “Page Previews” on page 21 for more information.

#### **WebContent/WEB-INF**

The standard folder which must exist in every Java EE web application. No files in this folder will be served by the web container, the files are only used internally by the web client application. It contains a `classes` folder that contains all the compiled Java class files and properties files required by the application. In a Cúram web application project, this includes the classes and properties files from the component specific `javasource` folders and the properties file from the `<client-dir>/JavaSource` directory. It also contains a `lib` folder that contains all required library classes packaged in

JAR files. The CDEJ supplies all the JAR files required for this folder and they are copied during the build process. You should not modify any files in this folder.

In addition to the web client folders, there are a number of folders in the `<server-dir>` project that are relevant to web client application development. The `<server-dir>` project maintains a similar structure to the web client, specifically in relation to the component folder.

### Server Folders

#### **components/<component-name>/clientapps**

Application configuration artifacts. These are the XML configuration files for defining applications, sections, tabs, etc. For more information see “Application Configuration” on page 125.

#### **components/<component-name>/tab**

Application configuration artifacts pre-defined in the Cúram application. XML configuration files shipped with the core and other out-of-the-box components will exist in this folder. These should not be modified. To change these you should create new artifacts in the `clientapps` folder in another component, which will then override these artifacts.

## Application Components

### Component Folders

Cúram web client applications are organized into collections of artifacts called *components*. Each component has its own folder below the `<client-dir>/components` folder. The core component is always present. This contains all of the artifacts needed for the core functionality of the Cúram reference application. The name of the component folder is used as the name of the component.

A component does not necessarily define a discrete part of an application; rather it defines an additional *customization layer* of an application. By adding new components, it is possible to selectively replace pages in the core application, add new pages, change the appearance of the application and alter various settings. It should never be necessary to edit files within the core application, thereby ensuring that when the core application is upgraded, the core changes do not overwrite your custom changes.

Within a component, you can use an arbitrary folder structure to allow you to organize your artifacts as you see fit. Artifacts in a component must have unique file names and the folder structure does not affect this. For example, you cannot place two UIM files with the same name within the same component, even though they would be in different folders. Likewise, a UIM file in one component is considered equivalent to a UIM file in another component, even if the folders within the components containing these UIM files have different names. Technically, a component represents a single namespace for artifacts and the folder structures within the components are mostly ignored.

The only exception to the requirement to use unique file names for artifacts is within the optional `WebContent` folder within a component. Within this folder, you can place arbitrary files in an arbitrary folder structure that you want to deploy with your application. The files will be copied to the main `<client-dir>/WebContent` folder during the build process and the folder structure will be preserved, so files in different folders may share the same name.



## Component Order

There can be any number of application components, but they are processed in a strict *component order*. This order determines the priority that will be given to artifacts that share the same name but appear in different components. This is fundamental to the manner in which Cúram web client applications are customized.

The component order is defined by the `CLIENT_COMPONENT_ORDER` environment variable. This is a comma-separated list of component names. Use only commas; do not use spaces. You must place the component with the highest-priority first in the list and continue in descending order of priority. The core component always has the lowest priority and is implicitly assumed to be at the end of the list; you do not need to add it explicitly.

For example, setting the component order to `"MyComponentOne,MyComponentTwo"` will give the highest priority to artifacts in the `MyComponentOne` folder within `<client-dir>/components`, a lower priority to artifacts in the `MyComponentTwo` folder, and the lowest priority to artifacts in the core folder. Any component folder not listed in the component order will not be included in the build and a warning will be displayed to indicate that these components have been ignored. If you do not set the component order at all, the default component order will include all components in alphabetical order.

**Note:** The `SERVER_COMPONENT_ORDER` order, used for the `<server-dir>` project, will *always* include all component folders existing in the components folder. If they are omitted from the `SERVER_COMPONENT_ORDER` environment variable, they will automatically be added to the end of the component order in alphabetical order. For more information consult the *Cúram Server Developers Guide*.

### Localized Components:

Localized components contains translated artifacts for the base components and are of the format `"<component name>_<locale>"`. It is *not* necessary for these to be added to the `CLIENT_COMPONENT_ORDER` environment variable as the tooling that processes this environment variable will prepend any available components that match entries in the `LOCALE_LIST` environment variable. Localized components are matched both on complete locale entry and on the two-character, lower-case language code. Localized components are prepended before the base component in the complete component order.

## Component Artifacts

Components contain a number of artifacts that are used to build an application. All the artifacts in a single component have the same priority in the component order. The artifacts in one component may be used to customize the artifacts in a lower-priority component, or they may be entirely new artifacts that extend the application. The main type of artifacts are as follows:

### UIM Pages

UIM pages are the principal artifacts of a web client application. Each UIM page describes a web page that users will see when accessing the web client application with their web browsers. The files for these artifacts use the `.uim` extension.

### UIM Views

UIM views define portions of a page that may be re-used by many UIM pages. The files for these artifacts use the `.vim` extension.

### Properties Files

Properties files store the natural language text for a page separately from the pages, views and page groups. When applications are localized into different languages, there will be a separate properties file for each language (or *locale*, see “Application Locales”). This allows a single UIM page, view or page group to be defined for all of the supported languages.

**Note:** UIM properties files do not support any form of visual layout or formatting capabilities such as using carriage returns or inserting HTML elements.

### Application Configuration Files

Application configuration files define the layout of the user interface and how UIM pages are grouped into sections and tabs. The files for these artifacts are defined using the extensions .app, .sec, .tab, .nav, .menu, and .ssp. Note, these files are located in the <server-dir> project. See “Application Configuration” on page 125 for details.

### Image Files

Images file referenced from your UIM pages or views can be added to your component's Images sub-folder. See “Images” on page 29 for details.

### Configuration Files

Configuration files are used to alter the behavior or appearance of the application or of elements of the application. There are a variety of different configuration files that can be used for different purposes.

### Custom Resources

Custom resources are arbitrary files that you want to deploy with your application. For example, you may want to customize the appearance of a page to reference you own image file for a logo; this image file is a custom resource.

## Application Locales

A locale describes a user's language, country and determines what the user will see in the pages they access via their web browser. While the data will largely remain the same (other than in the details of the formatting of numbers and dates) the labels for the data will appear in the appropriate language. Locales are specified using a simple identifier that contains a two-character, lower-case language code optionally followed by an underscore character and a two-character, upper-case country code. For example, “en” indicates the English language, and “en\_US” indicates the regional variation of the English language appropriate for the United States of America. This regional variation may help to identify differences in the dialect or usage of the language, American English in this example, but it may also affect the way dates and numbers are formatted.

The language and country codes have been standardized and support for any specific locale is determined by the Java Runtime Environment (JRE) that you are using for you application and whether you have localized your application appropriately for that locale. Consult the documentation provided by the vendor of your JRE for details on the support locales and see “Localization” on page 43 for full information on the procedure for localizing a Cúram web client application.

Before building a Cúram application that may have been localized for a number of locales, you need to specify what locales you want to include. To do this, you set the LOCALE\_LIST environment variable to a comma-separated list of the locale codes. Use only commas, do not use spaces. For example, “en\_US,es” specifies the

American English locale and the Spanish locale (with no regional variation). The first locale in the list is treated as the *default locale*.

Certain operations, such as the generation of page previews (see “Page Previews” on page 21), are only performed for the default locale.

**Improving Build Performance:** The Cúram CDEJ performs most of the translation work for the application's locales during the build process; from a single UIM file it will produce one JSP file for each locale in the locale list. If your application supports many locales, you may find it convenient when developing the application to omit some of the locale codes from the locale list, as this will improve the build performance. You can replace the locales when you want to view or test all of the localized pages.

## Building an Application

### Build Targets

The client application is built using Apache Ant build scripts. These build scripts define ordered sequences of processing steps called *targets*. To invoke a target, you open a command prompt window and change to the <client-dir> folder and then pass the name of the target to the command you use to start Apache Ant. Typically this command is called **build** or **appbuild**. The name depends on the script provided for your application, but it will be referred to as **build** in this manual. For example, to build the web client application, the command is **buildclient**. You can run more than one target at a time by passing the target names separated by space characters. For example, **buildcleancient** will first clean all the generated output that may be present before building the full web client application again.

The following build targets are available for Cúram client projects:

**client** Builds the client application. See “Full and Incremental Builds” on page 19 for further details.

**clean** Deletes all of output generated by the other build targets. See “Full and Incremental Builds” on page 19 for further details.

**beandoc**

Generates reference documentation for the façade server interfaces. See “Server Interface Reference” on page 20 for further details.

**client-with-previews**

Builds the client application and also generates previews of the pages in HTML format in the <client-dir>/WebContent/Previews folder. See “Page Previews” on page 21 for further details.

**uimgen** Generates skeleton UIM pages from the façade server interface definitions. See “UIM Generator Tool” on page 21 for further details.

A number of environment variables affect the build process for a web client application. Some have been introduced already and others are explained elsewhere, but all are shown below. When you install the Cúram Application, the build command will set most of these for you, as they mostly refer to files and folders that will be in fixed locations relative to where you installed the application. However, for a new application, or if you are modifying the build command, you may need to confirm that these are set correctly.

Table 1. Environment Variables

Name	Required	Description
CURAMCDEJ	Yes	The location of the installed Cúram CDEJ infrastructure. This is the same as the value of the <cdej-dir> placeholder used in this manual. See “CDEJ Installation” on page 11 for details.
CLIENT_DIR	Yes	The location of your web client application. This is the same as the value of the <client-dir> placeholder used in this manual. See “CDEJ Installation” on page 11 for details.
CLIENT_PROJECT_NAME	Yes	Defines the name of the application being built. This name is used as a base name for many generated artifacts, for example, for Java package names. The name is defined in the UML model. For the installed Cúram Application, the value should be “Curam”.
LOCALE_LIST	Yes	Defines the locales that will be supported by the application. See “Application Locales” on page 16 for details.
CLIENT_COMPONENT_ORDER	No	Defines the prioritized order of the application's components. See “Component Order” on page 15 for details. This is not required, but it is highly recommended that you set it explicitly. By default, all components will be processed in alphabetical order.
ENCODING	No	Defines the character encoding that will be used to interpret files that do not explicitly define an encoding. By default, the system's default character encoding will be used. See “File Encoding” on page 44 for details.
MULTIPLE_VALIDATION_ERRORS	No	Controls the number of errors that are reported during the build process before the build terminates. See “Error Reporting” on page 19 for details.

## Related Build Targets

The server application is built using Apache Ant build scripts, in the same way as the client application is built. The application configuration files are located in the <server-dir> project and as a result, the targets for processing these are part of the server project. The following targets are used to process the client application configuration files:

### **inserttabconfiguration**

Combines and imports the client application configuration files onto the database. See “Configuration files” on page 126 for more details.

## database

The last step of the **database** target is to call the **inserttabconfiguration** target. For more information the database target see the *Cúram Server Developers Guide*.

## Full and Incremental Builds

The **client** build target will generate a complete web client application. If no previous build output is present, running this target will build the entire application. This is called a *full build*. Subsequently, on running this target, the build scripts will compare your source files to the previously generated output files to detect what you have changed and will update the minimum number of output files possible. This is called an *incremental build*. An incremental build is performed automatically as long as the output of a previous build is present and is much faster than a full build. To perform a full build again, you must first run the **clean** target to remove all of the outputs from the previous build.

### warning: Building after Upgrading

If you upgrade your Cúram application or Cúram CDEJ, you must perform a full build by first running the **clean** target. Failure to do this could result in unpredictable behavior during the build process or when then application is running.

**Platform Specific Setting:** When executing the **client** build target from a text-only interface (e.g., using a terminal emulator to access a UNIX machine), `-Djava.awt.headless=true` must be added to the `ANT_OPTS` environment setting.

## Dependency Checking

For most changes that you make, you need only run the incremental build, as the changes will be detected automatically and only the dependent output files will be updated. However, some changes are not detected and you may need to run a full build for your changes to take effect. In particular, if you change a setting in the `curam-config.xml` configuration file that affects the build process (typically by affecting the appearance of the pages in a way that is applied at build-time), then you will need to perform a full build manually, as the changes will not be detected automatically.

Dependency checking will identify changes to server interfaces used by UIM pages. Server interfaces are defined in the application's UML model and more information can be found in "Server Interface Reference" on page 20. Only changes to interface properties, not their underlying domain types, are recognized in an incremental build. For example, changing a code-table name will not be detected by dependency checking and a clean build will be required.

## Build Logs

Every time you run the **client** target to build the application, all of the messages produced by the build scripts are written to a file in the `<client-dir>/buildlogs` folder. The files created are named for the date and time on which the build was started. If errors occur during a build, you may find it easier to review them by reading the log file instead of scrolling through messages at the command prompt.

## Error Reporting

One of the main steps performed by the client target is the generation of the JSP files from the UIM files. This process will check the validity of your UIM files as they are processed. The validity of the UIM files is determined in a number of steps:

1. They must contain well-formed XML and must not attempt to include VIM files that do not exist.
2. They must conform to the XML schema for UIM and to some additional context-sensitive rules that cannot be defined in the XML schema.
3. They must refer only to externalized strings that exist in their associated properties files.
4. They must meet a number of other requirements related to the connections made to the properties of server interfaces. For example, the property names must be unambiguous, or an address field must be the only field in a cluster.

Normally, the processing will stop when the first error occurs and the indicated problem must be fixed before the build can be executed again. However, for the errors detected in the second step, the schema and schema-related validation errors, there is an option to continue processing as far as possible after an error occurs to allow you to locate and fix more than one error at a time. Errors reported during the other steps will always stop the build immediately.

To allow multiple validation errors to be reported during a build, set the `MULTIPLE_VALIDATION_ERRORS` environment variable to `true`. If not set, the default value is `false` and the build will terminate after the first validation error occurs.

The number of errors reported is limited by the number of UIM files being validated at one time. The validation is typically performed on files in groups of one hundred, so this option will cause all of the validation errors in the current group to be reported before the build is terminated. No further groups will be processed after a group containing files with validation errors has been encountered.

## Server Interface Reference

When developing UIM pages, you will need to know details about the façade server interfaces and their properties so that you can select the information that you want to display on each page. This information is all defined in the application's UML model, but, for your convenience, you can generate simple reference documentation in HTML format to make the information more easily accessible.

The `beandoc` target generates this reference documentation for all of the available façade server interfaces ("classes"), creating many HTML files in the `<client-dir>/build/bean-doc` folder. To view the documentation, open the `index.html` file created in that folder in a web browser. This document provides links to alphabetical lists of all classes, all operations on those classes, all domain definitions used by properties of those operations, and all code-tables referenced by any of those domain definitions. Each of these lists provides further links for cross-references or providing more details. Viewing a class will display a list of its operations and selecting an operation will show a list of its properties.

In UIM, you do not have to use the full property name; you can use only part of the ending of the name as long as it is unambiguous. In the reference documentation for each operation, both the full property name and the shortest, unique ending of the property name are given. This will help you to choose a name that is short and readable, but that will not cause any build errors later.

Beside many of the class, operation, and property names, you will see a **Copy** button. Clicking this button will copy the name to the clipboard, allowing you to

paste it into your UIM file. For property names, the shortest unique name is copied. Copying to the clipboard using the **Copy** button only works in Microsoft Internet Explorer. In other browsers, you will have to select the text and use the normal copying commands.

## Page Previews

Page previews are produced by running the `client-with-previews` build target. This will generate static HTML pages for the default locale that can be opened in a browser to give you an impression of what the page will look like when the application is running. The HTML pages are located in the `<client-dir>/WebContent/Previews` folder. You do not need to start a server to view the pages. The pages display a default value for each field but do not support any user-interaction (buttons, links, pop-ups, etc. do not function). The preview page represents only the main content area of the page (the part specified in UIM) and not the sidebar or page header or footer.

The default values for the fields are defined by associating a default value with the domain definition of the field. These default values are used only for the preview pages and are defined in the `domain-defaults.xml` file in `<client-dir>/components/core`. Overriding this file in other components is not currently supported so it must be modified in place.

The file uses a simple XML format, a sample of which is shown below. The root element is `DOMAIN_DEFAULTS`. This element contains one `DOMAIN` element for each domain definition for which a default value is to be defined. The `DOMAIN` element requires a `NAME` attribute specifying the domain name, and a `DEFAULT` attribute specifying the default value for that domain.

```
<DOMAIN_DEFAULTS>
  <DOMAIN NAME="MY_DOMAIN" DEFAULT="My value"/>
  <DOMAIN NAME="YOUR_DOMAIN" DEFAULT="Your value"/>
</DOMAIN_DEFAULTS>
```

*Figure 5. Default Preview Values for Domain Definitions*

When generating preview pages, if there is no default value defined for a domain, a warning message will be displayed. These warnings will not prevent the preview page from being generated and a fall-back value will be used in the generated page (for example, “[field-value]”). Note that fields that have a complex domain value are not parsed or processed in the normal manner. Most of these are simply replaced by an image of the typical output and no default value is required. Complex fields like this are described in “Domain-Specific Controls” on page 209.

## UIM Generator Tool

The UIM Generator tool provides a user interface for automatically generating a UIM page for a particular server interface.

To start the UIM Generator tool:

1. Open a command prompt and change to the `<client-dir>` folder.
2. Run `builduimgen`.
3. The first time you run the UIM Generator you will be asked to locate a `ServerAccessBeans.xml` file. This file is generated by the `client` target and can be found in the `<client-dir>/build` folder.

Once the UIM Generator has started, you should see a screen containing the following:

- A **File** menu containing options to view your current configuration settings and to exit the application.
- A tree on the left hand side which lists all the server interfaces in the application.
- Two options, **Display Phase** and **Action Phase**, which determine when the selected server interface is called in the generated page.
- A **Make Page** button which generates the UIM for the current settings.

To generate a page perform the following:

1. Select the interface you wish to test from the tree (e.g. **Register-Person.read**).
2. Select the phase in which the interface should be called, for example, **Action**. Action phase pages call the interface when the page is submitted. Data can be entered for each input field and a button is generated to submit the page.
3. Click the **Make Page** button and you will be asked to specify a location for the generated UIM. You can change the default name if you wish. The location should be in the appropriate component folder of your application.

A UIM file and a properties file are generated. The labels for each field are given defaults based on the name of the server interface property associated with the field.

## External Client Applications

Due to the webclient directory containing a mix of components that are targeted for different EAR packaging, it can be difficult to use the single development environment and component order to develop and test these.

To allow for this a build target `external-client` will allow for creation of an environment and building of the components specified for an EAR entry in the `deployment_packaging.xml`.

The target requires a parameter `-Dapp` which should refer to the name of an EAR entry within the `deployment_packaging.xml`.

```
build external-client -Dapp=SamplePublicAccess
```

*Figure 6. external-client invocation*

The build target will copy the components specified for this EAR entry to a `webclient\build\apps\<app name>` directory and here will both build the project and create the relevant Eclipse project configuration files to allow for the project directory to be imported into Eclipse and development-type testing to be performed on these external client applications.

## Deployment

### Overview

A detailed description of the deployment procedure is provided in the *Cúram Deployment Guide* appropriate for your application server and operating system. However, there are a number of configuration settings available in your web client application project prior to deployment. These settings are described below.

### Configuring the Application

The `ApplicationConfiguration.properties` file defines the most important application configuration settings. The file needs to be located in the `curam/omega3` subfolder of the `<client-dir>/JavaSource` folder. When you create a new



application, this folder contains a sample file named `Initial_ApplicationConfiguration.properties`. You need to copy this file and rename it to `ApplicationConfiguration.properties` and change the settings to match your requirements. For the installed Cúram application, this process is done for you already, but you might still want to change other settings.

The properties that can be set in this file are described in the as follows:

#### **dateformat**

`dateformat=M d yyyy`

The format that is used by the Cúram date selector widget for entry and display of date fields.

The value of can be set to one of the following formats:

- Day-month-year order - `d M yyyy` (the default), `dd MM yyyy`.
- Month-day-year order - `M d yyyy`, `MM dd yyyy`.
- Year-month-day order - `yyyy M d`, `yyyy MM dd`.

In these formats, `d` represents the day number, `dd` represents the two-digit day number (padded with a leading zero if necessary), `M` represents the month number, `MM` represents the two-digit month number (padded with a leading zero if necessary), and `yyyy` represents the four-digit year. An uppercase letter `M` is used for the month, as the lowercase letter `m` is used in Java applications to represent the minute value when formatting times. Using `MMM` or `MMMM` to represent the month name is not supported. The formats are specified by using a space character as a separator. The actual separator character that you want to use is specified separately.

#### **dateseparator**

`dateseparator=/`

The date separator character that is applied to the specified date format. The value can be set to one of the following characters: forward slash (/) (the default), period (.), comma (,), or dash (-).

#### **timeformat**

`timeformat=HH mm`

The value of `timeformat` can be set to one of `h m s a`, `h m a`, `H m`, `hh mm a`, `HH mm`, `hhmm a`, or `HHmm`. Where not specified, `HH mm` is used as the default.

#### **timeseparator**

`timeseparator=:`

The value of `timeseparator` can be set by using either a colon (:) or period (.). Where not specified, the colon (:) is used as the default.

#### **serverConnectionType**

`serverConnectionType=single`

Do not change this value.

#### **addressFormatType**

`addressFormatType=US`

Default address format for addresses in the application.

#### **addressDefaultCountryCode**

`addressDefaultCountryCode=US`

Default, application-wide country code for addresses. This code must match an entry on the server application's Country code table.

**uploadMaximumSize**

`uploadMaximumSize=-1`

Maximum file upload size in bytes. Files that exceed this size are rejected. This limit needs to be set to match the allocated storage in the database for fields that contain uploaded files. This limit cannot be tailored to suit different database fields. The value -1 indicates no maximum limit.

**uploadThresholdSize**

`uploadThresholdSize=1024`

The maximum size in bytes of an uploaded file before a temporary file is created on the server to reduce the memory processor usage of storing the data as it is being processed. By default, the uploaded files are written to temporary disk storage if they exceed 1024 bytes.

**uploadRepositoryPath**

`uploadRepositoryPath=c:/temp`

Temporary files that are created during file upload are written to this location if they exceed the upload threshold size. By default, files are written to the Java system temporary folder (as defined by the Java system property `property java.io.tmpdir`).

**use.synchronizer.token**

`use.synchronizer.token=true`

Whether to use a synchronizer token to prevent accidental resubmission of forms due to use of the browser's **Back** button. The value can be set to true (default) or false.

**synchronizer.token.timeout**

`synchronizer.token.timeout=1800`

A synchronizer token expires if its associated form is never submitted. Values are specified in seconds. The default value for this property is 1,800 seconds.

**errorpage.stacktrace.output**

`errorpage.stacktrace.output=false`

The value for this property is true or false, with true as the default.

Stacktrace output is used in the development environment for debugging purposes. When the value for this property is true, the Java exception errors are output into the HTML error pages.

The property must be set to false in a production environment, for example, `errorpage.stacktrace.output=false`, otherwise it introduces security vulnerabilities into the application. The HTML error pages, which contain the Java exception stack trace, are not subject to the Cúram's application malicious code and filtering checks. This exemption potentially leaves the application open to injection attacks, for example, cross-site scripting and link injection.

**dbtojms.credentials.getter**

`dbtojms.credentials.getter=curam.sample.CredentialsGetter`

Specifies the name of the class that is used to obtain credentials to be used for triggering a DBtoJMS transfer. If not specified, a default set of credentials is used for this operation. For more information about DBtoJMS and how to use this property, see the Security Considerations section of the *Cúram Batch Processing Guide*.

**modal.dialogs.minimum.height**

`modal.dialogs.minimum.height=200`

Specifies the minimum required height for a modal dialog in pixels. The parameter is used when the calculated height of the modal dialog is less than the minimum required height or the specified height is less than the minimum required height. The default value of 100 pixels applies if this parameter is not set.

**tabSessionUpdateCountThreshold**

`tabSessionUpdateCountThreshold=10`

Specifies the number of tab session data updates that must be received before the data is persisted from the web tier to the database. After the threshold is reached, the recent updates are written and counting starts again from zero until the threshold is reached. A value of 1 causes writes on every update. A value of zero (or a negative or invalid value) disables writing based on update counts.

The default is every 10 updates.

For more information, see “Session Management” on page 195.

**tabSessionUpdatePeriodThreshold**

`tabSessionUpdatePeriodThreshold=120`

Specifies the number of seconds that must elapse since the last time session data was persisted from the web tier to the database before a new update triggers another write. A value of zero (or a negative or invalid value) disables writing based on update periods.

The default value is 120 seconds, or 2 minutes.

For more information, see “Session Management” on page 195.

**resourceCacheMaximumSize**

`resourceCacheMaximumSize=16000000`

Specifies the size of the application resource store cache. By default, the cache is limited to 16 MB (approx.) in size. When that limit is reached, the least recently used resources are ejected from the cache to make room for newly requested resources that are not already in the cache. The size of the cache is specified in bytes.

**Note:** A single resource is not cached if it exceeds the size limit for the cache.

**dynamicUIMInitModelOnStart**

`dynamicUIMInitModelOnStart=false`

Indicates whether the Dynamic Cúram User Interface Metadata (UIM) system needs to initialize the required information on the application model during startup or when it is first required for a Dynamic UIM page. The default value is true and it needs to be set to false to cause the model to be initialized when it is first required by a Dynamic UIM page.

For more information, see “Dynamic UIM System Initialization” on page 125.

**sanitize.link.parameter**

`sanitize.link.parameter=true`

Enables protection from link injection attacks. The default value is false.

When the value of this property is set to true, any parameters in the request URL within the Cúram application that are built with this value are validated for security vulnerabilities. If tracing is enabled, any parameters in which possible security vulnerabilities are detected are logged and, to maintain security, the request is terminated at a specially created error page.

**curam.progress.widget.enabled**

curam.progress.widget.enabled=true

Enables the Progress Spinner widget. The default value is true.

When the value of this property is set to true, and the loading of content in any panel or modal dialog takes longer than 2 seconds, a progress spinner will appear to indicate that the system is busy.

**curam.progress.widget.threshold**

curam.progress.widget.threshold=2000

Specifies the time offset in milliseconds for the progress spinner to be displayed. The default value is 2000 milliseconds (or 2 seconds).

This property specifies how long the progress spinner should wait before being displayed. If the page content loads within this period, the progress spinner will not be shown.

**Related reference:**

“Optimal Browser Support” on page 205

Learn about optimal browser support and how to notify the user when they are using a sub-optimal browser with the Cúram application.

**Tracing:**

As described in “Localization” on page 43, the file `CDEJResources.properties` defines properties for localizing certain features of the application. It also contains the setting to enable tracing of server function calls on the web-tier. Add the following property to enable this tracing:

TraceOn=true

When enabled, the inputs to and outputs from all server function calls will be written to “Standard Out”<sup>1</sup>.

## Customizing the Web Application Descriptor

The web application descriptor that is defined in a file named `web.xml` is a standard Java EE web application file. A Cúram web application contains various settings that a developer may wish to change, for example, server connection settings and the session time-out. The default settings can be seen in the following files based on the environment you are running the application from:

**Development Environment**

<cdej-dir>/lib/curam/web/WEB-INF/web.xml

**IBM® WebSphere® Application Server**

<cdej-dir>/ear/WAS/war/WEB-INF/web.xml

**WebLogic Application Server**

<cdej-dir>/ear/WLS/war/WEB-INF/web.xml

---

1. Due to classloader issues with Log4j, the web-tier does not currently provide a configurable logging system in the same way as the server-tier.

Customizing the web.xml file is done differently depending on whether you are changing the version of the file to be included in the Cúram EAR file or the version to be used at development time (e.g. in Apache Tomcat).

Customizing the web.xml for development time can be done by creating a custom version of the web.xml file in the WebContent/WEB-INF directory of a particular component, e.g. custom. Where multiple versions of web.xml exist in different components, the version in the highest precedence component, based on CLIENT\_COMPONENT\_ORDER, will be used.

The web.xml used within a Cúram EAR file can be customized using the deployment\_packaging.xml file located in the Curam Server project/config directory. It is possible to specify a custom web.xml using the custom-web.xml property. For more information on customizing web.xml at runtime please consult the Cúram Deployment Guide for the relevant Application Server.

When customizing web.xml, the existing security, filter and servlet settings should not be modified.

The server and port settings in ApplicationConfiguration.properties are now obsolete and no longer need to be specified. They are now automatically configured as context-param elements in web.xml when the Cúram EAR file is created. The server and port values are set according to the values specified in the AppServer.properties files (see the Cúram Server Deployment Guides for more information), with the exception of the web.xml used at development time. The development web.xml, located in <dej-dir>/lib/curam/web/WEB-INF/web.xml, has the server and port set to localhost and 900 respectively.

To change or add a locale, locate the init-param elements of the ActionServlet and duplicate them, changing the value of the param-name element as appropriate so it is in the form config/<locale-code>. See the example below.

```
<init-param>
  <param-name>config/en</param-name>
  <param-value>/WEB-INF/struts-config.xml</param-value>
</init-param>
```

*Figure 7. Configuring an Application Locale*

By default the web.xml for both WebSphere and WebLogic application servers is configured to enforce secure http (https), i.e. a secure SSL connection between the web client and the server. This can be modified by changing the transport-guarantee from CONFIDENTIAL to NONE. Note, this does not disable access to the Cúram web client over https, but enables additional access via http. Please refer to the Curam Security Handbook for further details.

#### **Customizing the 404 or Page Not Found error response.:**

The 404 or Not Found error message is a HTTP standard response code indicating that the client was able to communicate with the server, but the server could not find what was requested. The default web.xml files for WebSphere, and WebLogic specify a default error page for the Cúram application when an HTTP 404 error is thrown by the application server. The following is the error message displayed on that default page:

- The page you have requested is not available. One possible cause for this is that you are not licensed for the necessary Cúram module - if that is the case, you can use the User Interface administration screens to remove these links.

This message may be customized by adding a `HTTP404Error.properties` file into the `<client-dir>/components/<component_name>/` folder of the application and overriding the `error.message` property specified in that file.

## Customization

### Overview

A Cúram web client application can be customized without modifying the original components or their artifacts. This makes it easier to upgrade a base application while preserving your custom changes to that application. In this section you will see how the customization process works and how you can modify or extend a base application.

Customizations are applied according to the component order. The changes that you make to customize an application should be made in a separate component from the application's original components. The Cúram Application will be installed with a number of components (the core component and a number of other add-on components). To make customizations, create a new component folder containing a new sub-folder called `components`. Add that component's name to the component order (see “Component Order” on page 15). You will always want to add your component name to the beginning of the component order to give it the highest priority when artifacts are being selected at build-time. You can add more than one custom component, but you must decide what their relative position in the component order should be.

To begin with, your custom component will be an empty folder. You make your customizations by adding artifacts (e.g., UIM pages, configuration, files, etc.) to this component folder. You can create arbitrary sub-folders to help you organize these artifacts. You can customize an application by adding new artifacts, *overriding* existing artifacts, or *merging* new content with existing artifacts.

### Adding New Artifacts

You can add new artifacts to extend a base application. To add a new artifact, you simply create the new file in your component folder. The file name of the artifact should not be the same as the file name of an artifact in another component. If it is, the artifact will override another artifact or be merged with one. All types of artifacts can be added to an application in this manner, note artifacts added to the `WebContent` sub-folder will always override other delivered artifacts, as described in Section “Custom Resources” on page 43.

### Overriding or Merging Artifacts

Some types of artifacts can be overridden (effectively replaced) by adding an artifact with the same file name as an artifact in another component to your custom component. When building the application, the artifact in the highest priority component will be selected and the others ignored. Not all types of artifacts are overridden so completely. Other types of artifacts are merged with the same named artifacts in the lower priority components. The content of all of the artifacts is combined and, where the content is related, the content from the highest priority component is selected. The customized artifacts only need to share the same file name, they do not have to share the same relative folder location, though you may find it advantageous to organize them in a similar manner.

For example, for UIM files that share the same name, the file in the highest priority component will be selected and the others ignored; but for properties files that share the same name, all of the properties are merged together and, where the files contain properties with the same key name, the value of the property from the file

in the highest priority component will be used. When building an application, the artifacts in the components are not modified. The selection and merging of artifacts is performed in temporary locations, leaving the original artifacts intact.

The different ways in which artifacts are merged or overridden is covered in the sections below.

## Externalized Strings

All string values in UIM documents and JavaScript must be externalized. This aids maintenance and allows the application to be localized. JavaScript, UIM pages and UIM views can reference externalized strings.

The syntax of a properties file is simple. Each line contains a *name=value* pair, where the name is an arbitrary name for the string (it should not contain the “=” character), and the value is the localized string value. Blank lines and lines beginning with a “#” character are ignored. “Externalized Strings” contains an example. The syntax is defined by the `java.util.Properties` class provided with your Java Runtime Environment; you can consult the API documentation for that class for more details.

It is worth noting that the property value will be reproduced in the final application page exactly as you have typed it in the properties file. The value can contain any character from any language and it does not matter if that character is reserved in XML, HTML or anywhere else it will be safely processed and displayed as you intended in the application.

If you find that you need to enter a character in a property value that you cannot generate from the keyboard, the only one way to do it is to use the Unicode value of that character in a *Unicode escape sequence* a backslash and a “u” followed by the four-digit hexadecimal character code. For example, if you want to enter a non-breaking space, the corresponding Unicode escaped sequence is “\u00a0”. An example of this is included in the sample properties file below.

```
# Main Titles
MyPage.Title=My First Page
Cluster.User.Title=User Details

# Field labels
Field.FirstName.Label=First Name
Field.Surname.Label=Surname

# Other
Separator=\u00a0
```

*Figure 8. A Sample Properties File*

As you can see, using “.” characters is a useful way to add some structure to the properties in the file, though it is not a requirement.

When customizing an application, you can customize properties independently of pages and views by adding the appropriately named properties file to your custom component and defining the externalized string properties. You do not need to add the corresponding page or view file to your component and you do not need to redefine any of the properties that you do not want to change.

## Images

All references to icons or other graphics within a UIM document are externalized in a manner similar to normal strings. The `Image.properties` file (you can include

one in each component, if you wish) uses the same format as the string properties files to associate image references with image file names. The image files should be stored in the component's Images sub-folder and can be organized into a folder structure below this folder if desired. Most web browsers will support images in the portable network graphics (PNG) format, the graphics interchange format (GIF), and the joint photographic experts group (JPEG) format.

The Image.properties file simply associates a key with a path to the corresponding image file specified relative to the component folder. A sample of this file is shown below. To use these images, the key is used as the value of the IMAGE attribute on the ACTION\_CONTROL element in the UIM page.

```
Button.Ok=Images/ok.gif  
Button.Cancel=Images/cancel.gif  
MyPage.Title.Icon=Images/bluedot.gif
```

*Figure 9. A Sample Image.properties File*

The entries in the Image.properties file in the core component can be overridden individually or in total by creating an Image.properties file in your custom component and overriding the properties as required. You can override the image files themselves by creating files in your custom component with the same names as the files in the core component.

If you need to localize your images for different languages, you can add several Image.properties files using a different locale code as the file name suffix. See “Locales” on page 45 for details on locale code suffixes. Each properties file should define the same keys, but the image files can be different for each locale. If only some of the images need to be localized, the common images can be defined in the default Image.properties file (the one without the locale code suffix) and only properties for the localized images in the other properties files.

## Image Mapping

Images can also be used within the Cúram application to represent different values of displayed fields instead of presenting the value as text. For example, a typical boolean value of true or false could be represented by two images of, say, a green check mark and a red X.

The mapping between values and images is stored in the ImageMapConfig.xml file. There is no need to specify this in any way in UIM. If you use a property with a domain listed in the ImageMapConfig.xml file, it will automatically be displayed as an image.



```

<map>
  <domain name="MY_BOOLEAN">
    <locale name="en">
      <mapping value="true"
        image="Images/ValuesToImages/true.gif"
        alt="True"/>
      <mapping value="false"
        image="Images/ValuesToImages/false.gif"
        alt="False"/>
    </locale>
    <locale name="fr">
      <mapping value="true"
        image="Images/ValuesToImages/true.gif"
        alt="Vrai"/>
      <mapping value="false"
        image="Images/ValuesToImages/false.gif"
        alt="Pas Vrai"/>
    </locale>
  </domain>
</map>

```

Figure 10. A Sample ImageMapConfig.xml file

In the example, a field with domain type MY\_BOOLEAN has been assigned an image mapping. Note that you should specify an image mapping for each available locale even if the images used are identical. This is because the alternative text (“alt text”) attached to the image will be different for different locales. This text is important for accessibility reasons (users who have visual difficulties might use an audio browser, for example, which will read out the “alt text”).

ImageMapConfig.xml files in different components are merged with all unique image mappings preserved. If the same value in the same locale is mapped in two ImageMapConfig.xml files in two different components, the mapping from the higher priority component prevails.

## CuramLinks.properties

The UIM LINK element allows links to other client pages to be specified indirectly. The PAGE\_ID\_REF attribute is a key into the CuramLinks.properties file that returns the actual ID of the linked page.

Many links can point to the same page reference. The advantage of using a page reference is that all the links can be updated by changing a single entry in this file.

Each component can have its own CuramLinks.properties file. During generation, these individual files will be merged. As usual, if a particular key is present in more than one CuramLinks.properties file, the component priority order is used to decide which value is retained.

## XML Runtime Configuration Files

There are a few miscellaneous XML files that are used by the running client application. To change any of these files, copy the original file into the custom component sub-directory and modify the copied file. The default files can be found in <cdej-dir>/lib.. The client generators will use the xml file from the highest priority as specified by the CLIENT\_COMPONENT\_ORDER environment variable. The following is a list of these files:

- CalendarConfig.xml
- DynamicMenuConfig.xml
- ICDynamicMenuConfig.xml

- MeetingViewConfig.xml
- RatesTableConfig.xml
- RulesDecisionConfig.xml
- RulesEditorConfig.xml

Further details on the customization of these configuration files are given in “Domain-Specific Controls” on page 209.

## Login Pages

A default login page is supplied, called `logon.jsp` and located in the `lib/curam/web/jsp` directory of the Cúram Client Development Environment. This can be overridden by placing a copy, with the required changes, in a `webclient/components/<custom component>/WebContent` folder. However, there are some guidelines that should be followed.

Firstly, the following JavaScript should be included in the head section of the page:

```
<jsp:include page="no-dialog.jsp"/>
<script type="text/javascript"
  src="${pageScope.path1}/CDEJ/jscript/curam/util/Logon.js">
  //script content</script>
<script type="text/javascript">
  curam.util.Logon.ensureFullPageLogon();
  function window_onload() {
    document.loginform.j_username.focus();
    return true;
  }
</script>
```

This prevents the login page from being loaded in a dialog window.

Secondly, if it is desired to use the `j_security_check` login mechanism, the form submitted from the page should have an `action` attribute of `j_security_check`, a user name input with the name attribute `j_username` and a password input with the name attribute `j_password`.

The *Cúram Server Developers Guide* contains details of some common customizations to the `logon.jsp` file to support an external user client application and automatic login.

The styling of `logon.jsp` can be customized in the usual way. Simply add relevant CSS to any `.css` file in the custom component.

## JavaScript Files

The UIM SCRIPT element allows events on the page to trigger JavaScript functions. You can simply provide a path to the JavaScript file that is relative to your component folder. For example, if you have a JavaScript file in a sub-folder of your component folder: `MyComponent/scripts/myScript.js`, you can just refer to this in the SCRIPT tag as follows:

```
<SCRIPT SCRIPT_FILE="scripts/myScript.js" ...>
```

The paths you have specified will be fully preserved during application generation.

JavaScript allows HTML and CSS to be queried and manipulated. The underlying HTML and CSS source code used to style the Cúram application is not documented. No guarantees are made about its stability across Cúram releases. Therefore, custom JavaScript may have to be updated in line with changes to HTML structure.

A number of JavaScript APIs for use in the custom JavaScript code are provided within the Cúram application. They are documented in the following location in your CDEJ installation: CuramCDEJ\doc\Javascript\index.html. Use of any other Cúram JavaScript APIs, discovered through web developer tools for example, is not supported. The same is true of the JavaScript APIs and functions of third party frameworks used within the Cúram application. While there is nothing prevent a developer using these, using them means the code will be impacted by changes to the Cúram application in future releases.

Using the techniques described above to add new JavaScript files to the custom component, new third party APIs could be added to Cúram pages. This is at the customers discretion, as no guarantees can be made on third-party APIs that have not been used and verified within the Cúram application.

## Cascading Stylesheets

Stylesheets (\*.css) define the appearance (colors, fonts, etc.) of the client pages when viewed in a web browser. Default stylesheets are provided for the Cúram client application. It should never be necessary to edit these files, you can view them in the WebContent/WEB-INF/css folder. Instead, you can override particular styles or add new styles by creating new CSS files in one of your application components. Any CSS file located in the component/<some-component> folder (or sub-folder) will be automatically concatenated into the custom.css file. The custom.css file is included on all pages in the Cúram client application.

The underlying HTML and associated CSS used to style the Cúram user interface can easily be viewed in a variety of ways, such as using developer tools like the Internet Explorer Developer Toolbar. An example of customization would be to view the CSS used to apply a color to a field's label. The same CSS style can then be added to your custom CSS file and a different color specified. For example, assuming the HTML and CSS has been analyzed and the CSS rule `.field.label` applies the label color, the following CSS could be used to override the default:

```
.field .label {  
    color: red;  
}
```

This will take precedence over the Cúram style because custom CSS is included on the page after Cúram's default CSS. Another customization technique would be to create a new rule that is an extension of a Cúram rule. Continuing the above example, a developer analyzes the HTML and sees that within the Cúram application a span element is generated as a child of the `.label` element. It is possible to create a new rule that is specific to this span, even if Cúram has not done so. The complete customization will now look like this:

```
.field .label {  
    color:red;  
}  
.field .label span{  
    color:blue;  
}
```

The underlying HTML and CSS source code used to style the Cúram user interface is not documented (hence the use of developer tools to view it). No guarantee is made about its stability across Cúram releases. Therefore, customizations as described above or any customization based on analysis of the Cúram application's underlying HTML and CSS may be lost as new releases are taken on. The customizations may have to be re-applied by analyzing the HTML and CSS again.

**Note:** Some UIM elements support the STYLE tag which allows specific styling to be added to any instance of that element. This styling will always override that included in .CSS files. For more information, see “UIM Reference” on page 52.

#### **Application Specific CSS:**

CSS can be specific to the application being viewed. The id of the application (.app file) currently being viewed is added as a class on the BODY element of each HTML page, allowing application specific styling to be added to that page.

For example, a System Administrator views the SYSADMAPP application. The following is an example of CSS specific to that application:

```
.SYSADMAPP .field .label {  
    color:red;  
}
```

#### **Media Specific CSS:**

CSS can be specific to the type of media being used to view the web page. So, for example, it is possible to have some styles that only apply when a page is printed and others that only apply on-screen. It is possible to include CSS specific to a media using the following pattern:

```
<STYLE type="text/css">  
    @media print {  
        BODY {font-size: 10pt; background: white;}  
    }  
    @media screen {  
        BODY {font-size: medium;}  
    }  
</STYLE>
```

#### **Browser Specific CSS:**

CSS can be specific to the browser used to view the web page. Internet Explorer specific CSS files can be created in any folder in a component. A naming convention is used to distinguish between versions of Internet Explorer. Specifically, the following suffix is used:

##### **\_ie.css**

This file will be included in all versions of Internet Explorer.

Note that developers should continue to strive to use the same CSS on all browsers. Internet Explorer specific styling should only be used as a last resort.

### **Application Configuration Files**

The application configuration files for defining application, section and tabs can be added to the <server-dir>\components\<component-name>\clientapps directory, where <component-name> is a custom component. Sub-folders are supported within the clientapps folder. Any artifacts added to this directory will override files of the same name in the <server-dir>\components\<component-name>\tab directory. The tab directory contains files that are shipped with existing components within the Cúram application and these files should not be modified.

**Note:** The OOTB Cúram application uses fragments of configuration artifacts that are merged into single files at build time, this is not supported for custom application configuration artifacts. (i.e.) you should not have a tab folder in EJBServer\components\custom.

When customizing application configuration files that ship with the Cúram application, the XML configuration file and.properties file should always be customized as a unit. For example, a change to the SimpleApp.properties file,

associated with the SimpleApp.app file, should result in adding both SimpleApp.app and SimpleApp.properties to the clientapps folder. These files should be based on the merged version of the files. The **inserttabconfiguration** target can be used to get a development copy of the merged file. See the *Cúram Server Developer Guide* for more information.

There are a few general rules and best practices when working with the application configuration files:

- The id attribute on the root element of each configuration file must match the name of the file. E.g. SimpleApp.app must have an id of SimpleApp.
- The id attributes should not contain the period (.) or underscore (\_) characters.
- Localizable text should be added to a .properties file which matches the name of the configuration file. E.g. SimpleApp.app will have a corresponding SimpleApp.properties.
- Properties files can be re-used across configuration files. E.g. Person.nav and Person.tab can share the same Person.properties file.
- Ensure when developing the XML files to add the proper namespace information. This will allow for validation. For example:

```
<ac:application
...
</ac:application>
```

## General Configuration

### Overview:

The curam-config.xml file contains a number of general-purpose configuration options that affect the appearance or behavior of the web client application. Each of the following sections describe in detail the main elements of this configuration file.

### POPUP\_PAGES:

See “Pop-up Pages” on page 247.

### MULTIPLE\_POPUP\_DOMAINS:

See “Pop-up Pages” on page 247.

### ERROR\_PAGE:

If an error occurs at run-time, the user will be redirected to a page defined here. Depending on the error cause, two types of error page could be provided for reporting system or application failure (or a default page for reporting both kind of errors could be configured instead).

```
<ERROR_PAGE TYPE="SYSTEM" PAGE_ID="CuramSystemError"/>
  <ERROR_PAGE TYPE="APPLICATION" PAGE_ID="CuramError"/>
```

Figure 11. Error\_Page Section Example

```
<ERROR_PAGE PAGE_ID="CuramError"/>
```

Figure 12. Error\_Page Section Example with one default page

Please note: when overriding the ERROR\_PAGE setting it is not possible for a custom configuration to define an ERROR\_PAGE element without a TYPE attribute if a low priority component defines an ERROR\_PAGE element with a TYPE attribute. In that case, the custom component needs to use a TYPE attribute and must override both supported types of error page to get the desired effect

**MULTIPLE\_SELECT:**

Domains which should display as multiple select list boxes in forms are specified here. The MULTIPLE attribute, if true, allows multiple selection in the list.

```
<MULTIPLE_SELECT>
  <DOMAIN NAME="PRIMARY_ID" MULTIPLE="true"/>
  <DOMAIN NAME="OTHER_ID" MULTIPLE="true"/>
</MULTIPLE_SELECT>
```

*Figure 13. Multiple Select Section Example*

**FILE\_DOWNLOAD\_CONFIG:**

See “File Downloads” on page 56.

**ENABLE\_COLLAPSIBLE\_CLUSTERS:**

Set to false to disable collapsible clusters. By default this value is set to true.

```
<ENABLE_COLLAPSIBLE_CLUSTERS>false</ENABLE_COLLAPSIBLE_CLUSTERS>
```

*Figure 14. Disable Collapsible Clusters Example*

**APPEND\_COLON:**

Set to true to automatically append colons to FIELD and CONTAINER labels within CLUSTER elements.

```
<APPEND_COLON>true</APPEND_COLON>
```

*Figure 15. Append Colon Section Example*

**ADDRESS\_CONFIG:**

See “Domain-Specific Controls” on page 209.

**ADMIN:**

The ADMIN element can contain any number of CODETABLE\_UPDATE, TAB\_CONFIG\_UPDATE and RESOURCE\_UPDATE elements. The PAGE\_ID attribute of these elements specifies the page that will clear the relevant caches whenever its submit action is called.

```
<ADMIN>
  <CODETABLE_UPDATE PAGE_ID="CodeTableAdmin" />
</ADMIN>
  <TAB_CONFIG_UPDATE PAGE_ID="ApplicationConfigAdmin"/>
  <RESOURCE_UPDATE PAGE_ID="publishResourceChanges"/>
```

*Figure 16. Admin Section Example*

Please note: The caches are only cleared for the current instance of the web application. Other instances will have to be restarted to receive the code table updates. This feature applies at development time only.

**STATIC\_CONTENT\_SERVER:**

This option specifies a base URL for static content such as images, CSS files and JavaScript files. The option enables the relocation of static content to a separate server to allow for performance optimizations.

```
<STATIC_CONTENT_SERVER>
  <URL>http://www.myserver.com/staticresources/</URL>
</STATIC_CONTENT_SERVER>
```

*Figure 17. Static Content Base URL Example*

The forward slash at the end of the URL in the example is optional. It is also possible to use a relative URL.

```
<STATIC_CONTENT_SERVER>  
  <URL>/CuramStatic/</URL>  
</STATIC_CONTENT_SERVER>
```

Figure 18. Relative URL Example

**Note:** A full build is required to pick up this setting.

Where this option is used, the static content can be packaged using the *zip-static-content* target available in the webclient project. This target will create a zip file, *StaticContent.zip*, in the webclient\build directory. The *StaticContent.zip* file will contain all relevant static content to be relocated when the *STATIC\_CONTENT\_SERVER* setting is enabled. The *-Dstatic.content.zip* setting can be used to overwrite the default zip location. All content in the zip is stored under a root folder called *WebContent*.

```
build zip-static-content -Dstatic.content.zip=myzipfile.zip
```

Figure 19. Zip Target Example

The following content is included in the zip file:

- WebContent/\*\*/\*.\*.html
- WebContent/\*\*/\*.\*.htm
- WebContent/CDEJ/\*\*/\*.\*.png
- WebContent/CDEJ/\*\*/\*.\*.gif
- WebContent/CDEJ/\*\*/\*.\*.jpg
- WebContent/CDEJ/\*\*/\*.\*.jpeg
- WebContent/CDEJ/\*\*/\*.\*.ico
- WebContent/CDEJ/\*\*/\*.\*.css
- WebContent/CDEJ/\*\*/\*.\*.js
- WebContent/CDEJ/\*\*/\*.\*.svg
- WebContent/CDEJ/jscript/\*\*/\*.\*
- WebContent/CDEJ/themes/\*\*/\*.\*
- WebContent/Images/\*\*/\*.\*
- WebContent/genImages/\*\*/\*.\*
- WebContent/themes/\*\*/\*.\*

The relocation of static content to a separate server allows for specific cache control response headers to be set for this content. Setting a cache control response header provides an instruction to the browser to cache this content for a period of time; the aim of which is to reduce network traffic and improve performance. The *Expires* and *Cache-control* headers are generally recommended to encourage the browser to cache static content.

```
Expires: Thu, 15 Apr 2010 20:00:00 GMT  
Cache-control: max-age=86400
```

Figure 20. Response Headers

**Note:** The Expires value must match the specific formatting above to be recognized. The max-age attribute value is in seconds.

When the above headers are set the browser will cache the content until the *max-age* value is reached or the *Expires* date is reached. When cached, no request will be made to the server.

It is worth noting that there are exceptions to this, which can be browser dependent. A key exception is on a user triggered refresh (F5); Internet Explorer and Chrome will both perform conditional requests for all content in this instance, regardless of the freshness of the content in the cache. A conditional request is a request to determine if the resource has been modified and will usually result in a 304 response, which will be faster than a full resource request (200 response).

#### **FIELD\_ERROR\_INDICATOR:**

This option indicates if field level error indicators are to be displayed when an error occurs. The error message is the alt text of the image and is available as a tool-tip when the mouse is hovered over the image. The feature only applies to text input and date-time fields. Also, this feature only applies to web-tier generated messages (data-type validation, mandatory fields etc.), it does not apply to messages generated from server side code since there is no way to associate a server exception with a client side field.

```
<FIELD_ERROR_INDICATOR>true</FIELD_ERROR_INDICATOR>
```

*Figure 21. Field Error Indicators Example*

Please note if the FIELD\_ERROR\_INDICATOR element is not specified, it defaults to FALSE.

#### **SECURITY\_CHECK\_ON\_PAGE\_LOAD:**

All server functions used on a Cúram screen are checked for authorization rights when the page is initially loaded. If a user fails authorization for *any* of the server functions, an authorization error message will be displayed and the user will be prevented from viewing the page. For example, if a user has authorization rights to access the DISPLAY phase server function, but not the ACTION phase, they will not be able to view the page.

The SECURITY\_CHECK\_ON\_PAGE\_LOAD setting in curam-config.xml, which is true by default, indicates that authorization checks should be performed before the page is loaded to ensure the user has access rights to *all* server functions referenced by SERVER\_INTERFACE elements on the UIM page.

Setting the SECURITY\_CHECK\_ON\_PAGE\_LOAD attribute to false will disable this initial authorization check and defer authorization to the point at which the server function is invoked. As a result, on an edit page for example, a user would require authorization rights for the DISPLAY phase server function at a minimum. If they did not have authorization rights for the ACTION phase server function, the page will display, but the user will receive an authorization error message when the page is submitted.

To set SECURITY\_CHECK\_ON\_PAGE\_LOAD, and disable authorization on page load, add the following to the curam-config.xml file:

```
<SECURITY_CHECK_ON_PAGE_LOAD>false</SECURITY_CHECK_ON_PAGE_LOAD>
```

*Figure 22. Security Check on Page Load Example*

Please note if the SECURITY\_CHECK\_ON\_PAGE\_LOAD element is not specified, it defaults to TRUE.



There is no security risk associated with this change, but the change has implications for auditing. When the authorization check is performed on page load, by default authorization failures are not added to the AuthorisationLog database table. This behavior can be modified by setting `curam.enable.logging.client.authcheck` to true using the Property Administration screens.

When the authorization check is deferred to the invocation of the server function, i.e. `SECURITY_CHECK_ON_PAGE_LOAD` is false, authorization failures are always logged. It is not possible to control or disable this behavior. As a result, the risk is that the AuthorisationLog database table will be filled with noise in the form of authorization failures that are valid failures based on usage.

#### **ENABLE\_SELECT\_ALL\_CHECKBOX:**

The multi-select check-box WIDGET described “The MULTISELECT Widget” on page 119 displays a column of check-boxes used to select items in a LIST. The following configuration setting causes a check-box to be displayed in the column header that can be used to select or de-select all of the check-boxes at once.

```
<ENABLE_SELECT_ALL_CHECKBOX>true</ENABLE_SELECT_ALL_CHECKBOX>
```

*Figure 23. Enable Select All Check-box Example*

Please note if the `ENABLE_SELECT_ALL_CHECKBOX` element is not specified, it defaults to FALSE.

#### **TRANSFER\_LISTS\_MODE:**

When set to true all multiple selection controls in an application are displayed as Transfer List widgets.

```
<TRANSFER_LISTS_MODE>true</TRANSFER_LISTS_MODE>
```

*Figure 24. Transfer Lists Mode Example*

Please note if the `TRANSFER_LISTS_MODE` element is not specified, it defaults to FALSE.

#### **HIDE\_CONDITIONAL\_LINKS:**

When set to true all conditional links that evaluate to false are not displayed. When set to false all conditional links that evaluate to false are displayed as disabled links.

```
<HIDE_CONDITIONAL_LINKS>true</HIDE_CONDITIONAL_LINKS>
```

*Figure 25. Hide Conditional Links*

Please note if the `HIDE_CONDITIONAL_LINKS` element is not specified, it defaults to TRUE.

#### **DISABLE\_AUTO\_COMPLETE:**

When set to true auto complete on all input fields is disabled. When set to false auto complete on all input fields is enabled.

```
<DISABLE_AUTO_COMPLETE>true</DISABLE_AUTO_COMPLETE>
```

*Figure 26. Disable Auto Complete*

Please note if the `DISABLE_AUTO_COMPLETE` element is not specified, it defaults to FALSE.

### SCROLLBAR\_CONFIG:

The SCROLLBAR\_CONFIG element allows a vertical scrollbar to appear on a LIST or CLUSTER element after a maximum height is reached. It can contain two or less ENABLE\_SCROLLBARS elements. The ENABLE\_SCROLLBARS element has the following attributes:

- TYPE : Specifies the element in which vertical scrollbars are to be enabled. Can only be set to LIST or CLUSTER.
- MAX\_HEIGHT : Specifies the maximum height a CLUSTER or LIST can reach before a vertical scrollbar is displayed.

```
<SCROLLBAR_CONFIG>
  <ENABLE_SCROLLBARS TYPE="LIST" MAX_HEIGHT="150" />
  <ENABLE_SCROLLBARS TYPE="CLUSTER" MAX_HEIGHT="100" />
</SCROLLBAR_CONFIG>
```

Figure 27. Scrollbar Configuration

Please note if the SCROLLBAR\_CONFIG element is not specified no LIST or CLUSTER element will display a vertical scrollbar.

### PAGINATION:

This element configures the LIST pagination options for the whole application. Individual lists can override the global settings.

```
<PAGINATION ENABLED="true">
  <DEFAULT_PAGE_SIZE>15</DEFAULT_PAGE_SIZE>
  <PAGINATION_THRESHOLD>15</PAGINATION_THRESHOLD>
</PAGINATION>
```

Figure 28. Sample Pagination Configuration

Table 2. Pagination configuration options

Option Name	Required	Default	Description
ENABLED	No	true	Enables the ability to page through lists displayed in Cúram pages. Any LIST longer than the configured minimum size will display only the first "page" of data and the pagination controls will be displayed below the list.
DEFAULT_PAGE_SIZE	No	15	Specifies the page size the list will get by default. The page size can be then changed at runtime by the user.
PAGINATION_THRESHOLD	No	Based on the DEFAULT_PAGE_SIZE value.	Specifies the minimum list size at which pagination will be enabled. For shorter lists there will be no pagination, even if otherwise pagination is switched on.

### Customizing Configuration Settings:

The core component contains a copy of the curam-config.xml file, but you are free to augment and override the settings by including your own curam-config.xml file in your custom component. All of the individual curam-config.xml files will be merged into one at generation. The effect of this merging depends on each particular setting.

Some entries are global settings for the application and so must only appear once in the final output. These entries are as follows:

- HELP
- ERROR\_PAGE
- APPEND\_COLON
- ADMIN
- POPUP\_PAGES/CLEAR\_TEXT\_IMAGE
- MULTIPLE\_POPUP\_DOMAINS/CLEAR\_TEXT\_IMAGE
- STATIC\_CONTENT\_SERVER

If you define one of these in a custom component, it will completely override that of the core component.

The other entries will be merged. This applies to the following elements:

- MULTIPLE\_POPUP\_DOMAINS
- POPUP\_PAGES
- MULTIPLE\_SELECT
- FILE\_DOWNLOAD\_CONFIG
- PAGINATION
- ADDRESS\_CONFIG

Note, however, that particular address formats can be overridden. So, for example, if the core component had the following address format definition:

```
<ADDRESS_FORMAT NAME="US" COUNTRY_CODE="US">
  <ADDRESS_ELEMENT NAME="ADD1"
    LABEL="Core.Label.Address.1"
    MANDATORY="true"/>
  <ADDRESS_ELEMENT NAME="ADD2"
    LABEL="Core.Label.Address.2" />
  <ADDRESS_ELEMENT NAME="CITY"
    LABEL="Core.Label.City" />
  <ADDRESS_ELEMENT NAME="STATE"
    LABEL="Core.Label.State"
    CODETABLE="AddressState"
    MANDATORY="true"/>
  <ADDRESS_ELEMENT NAME="ZIP"
    LABEL="Core.Label.Zip" />
</ADDRESS_FORMAT>
```

*Figure 29. Extract from curam-config.xml File (1)*

and if your custom component had the following address format definition:

```

<ADDRESS_FORMAT NAME="US" COUNTRY_CODE="US">
  <ADDRESS_ELEMENT NAME="ADD1"
    LABEL="Custom.Label.Address.1"
    MANDATORY="true"/>
  <ADDRESS_ELEMENT NAME="ADD2"
    LABEL="Custom.Label.Address.2" />
  <ADDRESS_ELEMENT NAME="CITY"
    LABEL="Custom.Label.City" />
  <ADDRESS_ELEMENT NAME="STATE"
    LABEL="Custom.Label.State"
    CODETABLE="AddressState"
    MANDATORY="true"/>
  <ADDRESS_ELEMENT NAME="ZIP"
    LABEL="Custom.Label.Zip" />
</ADDRESS_FORMAT>

```

Figure 30. Extract from *curam-config.xml* File (2)

then it is the second one (i.e., the custom definition) that will appear in the final merged *curam-config.xml* file. This is because both address formats have the same name ("US").

### Dividing the Configuration File:

The *curam-config.xml* file can be divided into manageable chunks. If you like, you can take one part of the configuration and save it in a file with a different name. Taking the previous address format configuration as an example, you can create a file with the following contents:

```

<APP_CONFIG>
  <ADDRESS_CONFIG>
    <LOCALE_MAPPING LOCALE="en_US"
      ADDRESS_FORMAT_NAME="US">
      <ADDRESS_FORMAT NAME="US" COUNTRY_CODE="US">
        <ADDRESS_ELEMENT NAME="ADD1"
          LABEL="Custom.Label.Address.1"
          MANDATORY="true"/>
        <ADDRESS_ELEMENT NAME="ADD2"
          LABEL="Custom.Label.Address.2" />
        <ADDRESS_ELEMENT NAME="CITY"
          LABEL="Custom.Label.City" />
        <ADDRESS_ELEMENT NAME="STATE"
          LABEL="Custom.Label.State"
          CODETABLE="AddressState"
          MANDATORY="true"/>
        <ADDRESS_ELEMENT NAME="ZIP"
          LABEL="Custom.Label.Zip" />
      </ADDRESS_FORMAT>
    </ADDRESS_CONFIG>
  </APP_CONFIG>

```

Figure 31. Sample *address-config.xml* File

You would then save this with a file name that ends with *-config.xml* anywhere within your component, say, *address-config.xml*. Note that the file must have the same *APP\_CONFIG* root element as the full *curam-config.xml* file. As long as you follow these conventions, all of your configuration files will be merged into a single *address-config.xml* file at build time.

**Configuration File Names:** Two naming patterns are used for most configuration files. Some use the pattern *XConfig.xml* and others *X-config.xml*, where "X" is some prefix. For example, *ImageMapConfig.xml* and *address-config.xml*. The

former pattern indicates a standalone configuration file that is not related to other configuration files. The latter pattern indicates that the file is really just part of the `curam-config.xml` file.

## Custom Resources

Arbitrary files can be included in the web application by doing the following:

1. At the root of a component, created a folder called `WebContent`, for example `<client-dir>/components/MyComponent/WebContent`.
2. Place files in this folder using any folder structure you wish.
3. When you run the **client** build target these files will be copied directly to the `<client-dir>/WebContent` which represents the root of the web application. The folder structure will be maintained during the copy.

### warning:

Before making use of this functionality care should be taken to understand the effects. It is advised to firstly view the generated `WebContent` folder (located `webclient/WebContent`) and to be aware of what files exist in it. Placing a similar file in the `WebContent` folder of a component will overwrite the currently existing file in the generated `WebContent` folder.

Files included in the application in this way take precedence over the merging and overriding process as described in previous sections for other resources. For example, if you include a CSS file in this way, the contents of the file will not be included in the CSS overriding process described in “Cascading Stylesheets” on page 33.

The copying of custom resources occurs after other source artifacts are built and merged, so it is possible to replace existing resources. Care should be taken in this case. For example, it would be possible to have a component with a file in `WebContent/WEB-INF/struts-config.xml` that would completely replace the Struts configuration file generated by the client build and therefore break the application.

It is also important to note that the files placed in a `WebContent` folder within a component are completely ignored during the build process and are not processed. They are merely copied across. For example, if you have JavaScript properties file in the `WebContent` folder of your component it will not be processed.

Finally, when multiple components have a `WebContent` folder they are copied based on component priority, but the copy is time-stamp based. The copy command always uses verbose output for these files so the developer can see exactly what files are being copied.

---

## Localization

Use this information to learn about the various files that need to be updated when translating a Cúram application into a new language.

To simplify the translation process, the language-specific parts of the application are separated out from the application code.

## Numbers

Numbers are language-specific and so a Cúram application treats numbers in a locale-specific manner depending on the preferred language of the user. For

example, a decimal number can be represented as 7,99 or 7.99 depending on whether the user's locale is French or English.

## File Encoding

OOTB Cúram supports the development of applications localized into many languages. The Cúram CDEJ generators support files encoded in the various character encodings appropriate for those languages. Definition of the encoding for a file is dependent on the type of file and the following sections describe how to set the encoding for the different types of supported files.

### XML Files

The encoding for XML-format files is declared explicitly within the XML file itself, where the first line, the XML declaration, may look like this:

```
<?xml version="1.0" encoding="ISO-8859-1"?>
```

This tells the XML parser that the file uses the ISO-8859-1 encoding, a typical encoding for Western European languages. If the XML declaration is omitted, the parser will assume UTF-8 encoding, which covers most modern languages and many others, besides being based on the Unicode standard. It is very important that the XML declaration matches the actual file encoding. The declaration does not determine the encoding, it only identifies it; changing the declaration does not automatically change the file encoding. If you use a specialized XML editor application, then it will probably recognize the declaration and change the file encoding for you. Most plain-text editors will not do this, so you must ensure that you select the correct encoding in your editor before saving the file.

It is **highly** recommended that UTF-8 encoding is used for XML files.

### Java properties files

For Java properties files (used in the application, for example, to define the text strings that appear on client screens), there is no equivalent of the explicit XML declaration. The client generator must assume an encoding for the client properties files. The assumption the generator makes is that Java properties files are encoded in the default system encoding of the machine that the build is running on. This is a reasonable assumption given that the files themselves were likely created on the same machine or a machine of similar type in the same country. On a Microsoft Windows machine in Western Europe, for example, the system encoding is probably Cp1252, the Windows variant of ISO-8859-1. This encoding will handle the accented characters of Western European languages but does not cover, say, Cyrillic or Chinese characters.

If, for some reason, you are building on a machine that does not share its system encoding with the files that are being processed, you must indicate this by setting the `ENCODING` environment variable. For example, to build a Chinese language web client application on an English language Microsoft Windows machine, you might choose to save your properties files in the UTF-8 encoding, so you would set the `ENCODING` environment variable to UTF-8. During the build, you can see that the generator overrides its normal default setting:

```
System encoding is Cp1252.  
Using encoding UTF-8 to read properties files.
```

The Java Runtime Environment will always assume that properties files use the ISO-8859-1 encoding. This is not very helpful if you want to create properties files using the UTF-8 encoding for localization to, say, Chinese. To overcome this

limitation, the Cúram CDEJ will automatically translate properties files from your preferred encoding (either the system default encoding, or the encoding specified via the ENCODING environment variable) into the encoding required by Java. This is performed automatically during the build process and your original properties files will not be affected.

**Troubleshooting:** Where a properties file has been saved in UTF-8 encoding, and this does not match the system encoding, build failures can occur. The build failure will report a `PageGenerationException`, where the build could not find a property even though the property exists in the relevant file. This happens where the properties file has been saved by a UTF-8 editor which adds the Byte Order Mark (BOM) at the beginning of the file. The property reported in the error will be the first property in the file. To resolve the issue the file should be saved in the correct encoding, ensuring the BOM character has been removed.

**Note:** The properties files shipped by default with Cúram use ISO-8859-1 encoding, and where necessary use Unicode characters.

### Non-XML Files

The non-XML files in the Cúram Reference Application are encoded in the ASCII encoding. ASCII has the useful property of being a subset of most other common file encodings. This means you do not generally need to convert the English language files that ship with the OOTB Cúram application in a new encoding in order to build them in a different language environment.

## Locales

A Java locale identifier has three parts:

### Language

A lower-case, two-letter, ISO-639 code.

See <http://www.unicode.org/onlinedat/languages.html>.

### Country

An upper-case, two-letter, ISO-3166 code.

See <http://www.unicode.org/onlinedat/countries.html>.

### Variant

A vendor-specific or browser-specific code.

The language code is required, but the other parts are optional. The individual parts are separated by an underscore character. Some examples of valid locales are: “en” (English language), “en\_US” (English language for the United States), zh\_HK (Chinese language for Hong Kong). This system is used within the Cúram application to identify locales. Most locale-specific information in the application are contained in properties files.

### Non JavaScript property files

When localizing an application (see “JavaScript property files” on page 46 for details on localizing JavaScript), you will need to create new properties files for each locale. The files for the default locale are named simply as `SomeFile.properties`. The files for other locales are identified by appending the locale identifier to the end of the file name after a separating “\_” (underscore) character (i.e., between the name of the page and the `.properties` extension). For example, `SomeFile_es.properties` would be the name of the Spanish language version of `SomeFile.properties`.

It is useful to note that if a particular property is not found by the application in `SomeFile_es.properties`, the properties file for the default locale, i.e. `SomeFile.properties`, will be searched. This is particularly handy in the case of `Image.properties`, described below, where only some of your images contain text and thus need to be localized. Properties for the other images can be defined once in the default locale properties file and they will be picked up in all locales.

Once done adding localized `.properties` files, update the `LOCALE_LIST` environment variable as appropriate (this variable defines the list of locales the client will be built for), for example, set it to `"en,es"` for a default English language application and a Spanish language application. See "Application Locales" on page 16 for more details on this setting.

The merging of localized properties files from different components happens in exactly the same way as it does for default locale properties files. See "Externalized Strings" on page 29 for more details on the merging of properties files.

### JavaScript property files

When localizing JavaScript files in the application, you will need to create new JavaScript property files for each locale. The files for the default locale are named simply as `*.js.properties`. The files for other locales are identified by appending the locale identifier - after a separating `"_"` (underscore) character - between the `.js` extension and the `.properties` extension. For example, `SomeJSFile.js_es.properties` would be the name of the Spanish language version of `SomeJSFile.js.properties` file. This file will be automatically processed by a client build. Similar to the non JavaScript property files, if a particular property is not found by the application in `SomeJSFile.js_es.properties` file, then the property from the default properties file (`SomeJSFile.js.properties`) will be used.

## UIM Externalized Strings

As described in "Externalized Strings" on page 29, all string values in UIM files are externalized to `.properties` files.

If `MyPage.uim` is the UIM file, then `MyPage.properties` is the corresponding properties file. To add localized properties files, please see "Locales" on page 45.

The strings are stored in a properties file in the same folder as the page or view file. This file must have the same name as the page or view file but with the extension `.properties`. For example, if the page is stored in a file called `MyPage.uim`, the strings will be stored in the file `MyPage.properties` in the same folder. Similarly, views will see the `.vim` extension changed to `.properties`.

While UIM documents in the highest priority component override those in all other components, properties files in different components are merged together. Individual properties override those with the same property name defined in lower priority components. Also, when a UIM page includes a UIM view (a `.vim` file), all of the properties defined for both the page and the view are merged and the properties for the page override those defined for the view where they share the same property name. These two merging steps happen separately with the component order applied first for each properties file and the page-view order applied on the resulting properties. A property defined for a page will override a property of the same name defined for a view, even if the property for the view was defined in a higher priority component.



## JavaScript Externalized Strings

As described in “Externalized Strings” on page 29, all string values in JavaScript files should be externalized to JavaScript property files (.js.properties files).

By convention the name of the resource file for your JavaScript must be derived from name of the.js file itself. For example if your JavaScript file is called SomeJSFile.js then related localizable resources should be placed in SomeJSFile.js.properties file. A \*.js.properties file can be placed anywhere in the component directory, but by convention it should be in the same directory as the related \*.js file.

The exception to this is that a \*.js file within a WebContent directory cannot have its associated \*.js.properties file within the same directory. The associated \*.js.properties file must be placed within a directory outside of the WebContent directory. To add localized JavaScript properties files, please see “Locales” on page 45.

JavaScript Properties files with the same name across all components will be merged together during processing. Any property with the same name will be overwritten by the highest component in the component order.

The use of placeholders within a property value is supported. The placeholders must be in the format %ns or '%ns' where n represents an integer from 1...n, and n must be within a defined range. The range is defined by the number of placeholders used within a property value. For example, if there are three placeholders within a property value then the placeholders must be numbered from 1 to 3 (e.g. %1s, %2s, %3s) and anything outside of this range is not supported.

### Accessing properties in JavaScript

There are three requirements for accessing a JavaScript property.

```
// 1.
dojo.requireLocalization("curam.application", "SomeJSFile");

// 2.
dojo.require("curam.util.ResourceBundle");
var bundle = new curam.util.ResourceBundle("SomeJSFile");

// 3.
var localizedMessage = bundle.getProperty("myPropertyKey");
var localizedMessageWithSubstitutions
    = bundle.getProperty("my.sub.key", ["a", "b"]);
```

curam.application is the default package into which all localizable resources are placed by the Curam infrastructure. SomeJSFile is derived from the name of the related JavaScript properties file.  
*Figure 32. Accessing a property*

#### 1. Load the resources using dojo.requireLocalization().

Refer to comment 1 in “Accessing properties in JavaScript” for an example of this.

#### 2. Create an instance of the curam.util.ResourceBundle object.

This is required in order to be able to access the localized resources. Refer to comment 2 in “Accessing properties in JavaScript” for an example of this.

#### 3. Access a property

The `getProperty()` method can be used to access a property on the instantiated `ResourceBundle`. Refer to comment 3 in “Accessing properties in JavaScript” on page 47 for an example of how to get a property and a substituted (2 substitutions) property respectively.

## Image.properties

The `Image.properties` file (see “Images” on page 29) can be localized as per other properties files, please see “Locales” on page 45 for more information on localizing properties files. Once the localized properties file is created, place this beside the `Image.properties` file.

It is useful to note that if the application does not find a particular property in a localized properties file, it will check the default locale properties file. This is generally true for all properties files but it is particularly useful in the case of `Image.properties`. You might find that some of your images can be used no matter what language is displayed, whereas other images contain text and thus must be altered. It is only these latter images that need to be mentioned in the localized properties file.

## Infrastructure Widget Properties Files

The following is a list of `.properties` files associated with Infrastructure widgets, e.g. the `AgendaPlayer.properties` file is associated with the `AgendaConfig.xml` file, which defines the Agenda Player widget.

- `AgendaPlayer.properties`
- `BarChart.properties`
- `Calendar.properties`
- `ComparedEvidence.properties`
- `DateTimeSelector.properties`
- `DecisionMatrixAddMessage.properties`
- `DisplayEvidence.properties`
- `EvidenceComparison.properties`
- `EvidenceReview.properties`
- `EvidenceTabContainer.properties`
- `FrequencyPatternSelector.properties`
- `GanttChart.properties`
- `IEGPlayer.properties`
- `Logon.properties`
- `MeetingView.properties`
- `PaymentStatement.properties`
- `RatesTable.properties`
- `Rules.properties`
- `TypicalPictureEditor.properties`
- `Workflow.properties`
- `FileEdit.properties`

**Note:** The names of the properties files associated with infrastructure widgets are reserved names and must not be used for the name of any other client properties file. No warning is printed to the console in this scenario, therefore care must be taken when naming other properties files.

To customize a widget properties file, create a new version under the `webclient/components/custom component` folder, where the default content for the file can be found in the corresponding sample widget properties file located in the `<cdej-dir>/doc/defaultproperties/` folder. For each entry in Cúram's version of the file you wish to change, add a corresponding entry to your custom file. These properties files can be localized as per "Locales" on page 45.

## Frequency Pattern Selector Localization

The Frequency Pattern Selector infrastructure widget is used to construct frequency patterns such as:

the first day of every 1 month(s)

This sentence is made up of fixed text from its associated `FrequencyPatternSelector.properties` file as well as values selected by a user from an input field and two drop-downs in the widget, refer to this example frequency pattern in "Frequency Pattern Selector" on page 212.

Because of the grammar differences between different languages, the construction of this example frequency pattern sentence can be dramatically changed in other languages, like the values selected by a user can be re-ordered in it. Therefore, the placeholders are introduced to represent these user selected values so that we can localize every frequency pattern as "whole" into every single property in the properties file.

Here is the property entry from the `FrequencyPatternSelector.properties` for this example frequency pattern:

```
Text.monthly.freq.type.two= The %ordinal% %dayOfWeekExtended%  
of every %monthInterval% month(s)
```

The strings `%ordinal%`, `%dayOfWeekExtended%` and `%monthInterval%` in this property entry are the placeholders that map to the values that will be selected from two drop-downs and one input field in the widget. The detailed explanation of these three placeholders will be covered later in a table.

In order to use these placeholders properly, you need to stick to the following two rules:

- **The placeholders control the layout of the widget**

Any change of the location of a placeholder in a localized text for a certain frequency pattern would cause the change of the layout of this frequency pattern to be displayed on the Frequency Pattern Selector widget.

- **The placeholders that can be used for every frequency pattern are fixed**

You could not change, add or reduce placeholders used for a certain frequency pattern. It will cause this widget failing to work.

A description of all these placeholders used in the properties file of this widget is listed as follows:

*Table 3. Placeholders used in Frequency Pattern Selector*

Placeholder Name	Description
<code>%dayInterval%</code>	A day interval. It maps to an input field where you can enter a number for a day interval for a frequency pattern.

Table 3. Placeholders used in Frequency Pattern Selector (continued)

Placeholder Name	Description
%weekInterval%	A week interval. It maps to an input field where you can enter a number for a week interval for a frequency pattern.
%dayOfWeek%	A set of days in a week. It maps to a collection of check boxes where you can multi select the days in a week for a frequency pattern.
%dayOfWeekExtended%	It is an extension of the values represented by %dayOfWeek%, which also includes the weekday, weekend day and day value. It maps to a drop-down where you can select one of those day values for a frequency pattern.
%monthInterval%	A month interval. It maps to an input field where you can enter a number for a month interval for a frequency pattern.
%ordinal%	an ordinal, e.g. first, second. It maps to a drop-down where you can select an ordinal for a frequency pattern.
%dayIntervalOne%, %dayIntervalTwo%	Two day intervals in a frequency pattern. They should be used together and map to two input field where you can enter a number for a day interval respectively for a frequency pattern.
%ordinalOne%, %ordinalTwo%	Two ordinals in a frequency pattern. They should be used together and map to two drop-downs where you can select an ordinal respectively for a frequency pattern.
%monthOfYear%	A month in a calendar year. It maps to a drop-down where you can select a month for a frequency pattern.

As stated in the second rule above, the placeholders used for every frequency pattern are fixed. So you need to take care that you have used them properly when localizing the properties in this widget properties file. As long as you keep this in mind, the customization of this widget properties file is also no difference from other infrastructure widgets. The following table lists all the properties and the placeholders they contain for every frequency pattern sentence displayed on the Frequency Pattern Selector.

Table 4. Properties used for the Frequency Pattern Selector

Property Name	Placeholders it contains
Text.daily.freq.type.one	%dayInterval%
Text.daily.freq.type.two	None.
Text.weekly.freq.type	%weekInterval%, %dayOfWeek%
Text.monthly.freq.type.one	%dayInterval%, %monthInterval%
Text.monthly.freq.type.two	%ordinal%, %dayOfWeekExtended%, %monthInterval%
Text.bimonthly.freq.type.one	%dayIntervalOne%, %dayIntervalTwo%
Text.bimonthly.freq.type.two	%ordinalOne%, %ordinalTwo%, %dayOfWeek%
Text.yearly.freq.type.one	%monthOfYear%, %dayInterval%

Table 4. Properties used for the Frequency Pattern Selector (continued)

Property Name	Placeholders it contains
Text.yearly.freq.type.two	%ordinal%, %dayOfWeekExtended%, %monthOfYear%

## CDEJResources.properties

This properties file can be localized as per “Locales” on page 45. Images defined in this file can also be customized per locale.

### Related reference:

“Optimal Browser Support” on page 205

Learn about optimal browser support and how to notify the user when they are using a sub-optimal browser with the Cúram application.

## ApplicationConfiguration.properties

This properties file does not, in itself, need to be localized but there are a couple of settings within this file which are related to the localization of date and address formatting. See “Configuring the Application” on page 22 for details.

## Application-wide Menu

The contents of the application-wide menu (that normally appears in the top-right of the screen) are defined in `curam-config.xml`. It is possible to put the text that will appear on screen directly into this file, in the LABEL attribute of the LINK element. That approach, however, is not suitable if the application should be viewable in multiple languages, so the application will first check if the LABEL attribute is actually a key into the `CDEJResources.properties` file. If it finds the key, it will use the corresponding value in the menu. To localize the menu, therefore, simply include the same key in the localized version of `CDEJResources.properties`. This properties file can be localized as per “Locales” on page 45.

## Tabbed Configuration Artifacts

Each tabbed configuration artifact will have a corresponding properties file for any text that may be localizable. To localize this text for a specific language, you must add the locale-specific properties file beside its associated tabbed configuration artifact in your <custom> component. These properties file can be localized as per “Locales” on page 45.

## Runtime Messages

The Cúram CDEJ runtime messages can be localized or customized by creating a `RuntimeMessages.properties` file within the component folder, i.e. the `<client-dir>/components/<component_name>` folder. The default content for this file can be found in the `<cdej-dir>/doc/defaultproperties/` folder. Any messages present in this file will override the corresponding messages from the `RuntimeMessages.properties` shipped with the Cúram CDEJ. The standard file naming convention for Java properties files can be used to add locale-specific messages. For example, to create a Spanish version, a file `RuntimeMessages_es.properties` would be created.

It is not necessary to copy all of the messages into the custom message catalog when customizing only some of them. Only the messages that are customized need to be defined in the custom message catalog; the other messages will be loaded from the default message catalog.

When resolving error messages, the custom message catalog is checked first and all the locale fall-backs are applied. If a message is not found, then the default message catalog (from the Cúram CDEJ) is checked. Therefore, a message in a custom message catalog will take precedence over one in a default catalog even if the locale of the default catalog is more specific.

When customizing a message, the message argument placeholders cannot be changed. The message argument placeholders have the form %ns where n is the argument number. The message arguments can be moved around and their order changed, but no new arguments may be added and none may be removed.

---

## UIM Reference

Learn about the Cúram User Interface Meta-data (UIM) format used to specify the contents of the Cúram web application client pages.

UIM is an XML dialect and all UIM files are well-formed XML. The Cúram CDEJ will translate UIM files into JSP files that can be deployed to your web application server.

### Creating UIM Documents

You can use any text editor to write UIM documents, but it is usually easier if a specialized XML editor is used. The CDEJ includes an XML Schema file defining the syntax of a UIM document and when this is combined with a schema-aware XML editor, you will have access to many time-saving facilities such as auto-completion, syntax checking, etc.

### UIM Document Types

When creating UIM documents, there are four root elements that are valid: PAGE, VIEW, PAGE\_GROUP and APPLICATIONS. These root elements are used to create the two types of UIM document:

- PAGE** This defines a UIM page that will be translated into a JSP page. The file name must be the same as the value of the PAGE\_ID attribute of the root element. The file extension to use is .uim. UIM pages can be organized arbitrarily into sub-folders within a component folder for convenience in managing a large number of files. Ultimately, all UIM pages are generated into JSP pages in a single folder, so the PAGE\_ID attribute of the PAGE element and consequently the file names of all the .uim files must be unique within a component.
- VIEW** This defines a portion of a page that can be included into a PAGE element in another UIM document. This allows common sequences of elements to be reused. The file name is not restricted. The file extension to use is .vim. Like UIM pages, views can be organized into an arbitrary folder structure within a component folder, but the file names must be unique within that component.

## UIM Pages

“Cúram web client overview” on page 1 covered the basic concepts behind UIM pages and what clusters, lists, action sets, action controls, containers, and fields are, so this information will not be repeated here.

The elements in a page must follow a strict order imposed by the XML Schema definition of UIM. However, this order is only imposed when editing using a schema-aware XML editor. The JSP generator does not check the ordering at present. The order in which elements are presented in the child element tables in this reference is the order in which the elements should be used in the UIM documents unless otherwise indicated. There is no specific ordering for attribute values.

## UIM Views

A PAGE element can contain an INCLUDE element anywhere at the top level that allows commonly used fragments of UIM to be inserted at that point during translation. The included elements are defined in a UIM document called a *view*. The view document uses VIEW as the root element. Elements included from a view must be valid in the context in which they have been included. For example, a PAGE element that already contains a PAGE\_TITLE element, cannot include a view that also defines a PAGE\_TITLE element. Similarly, the schema rules governing the order of elements in a page must be observed when elements are included from a view.

Views are similar to pages in what they can contain, the only differences are as follows:

- A view cannot contain an INCLUDE element to include another view.
- A view does not have any PAGE\_ID attribute, this is defined in the page that includes the view.

All other elements that are valid in a PAGE element at the top level, are also valid in a VIEW.

When including views, the name of the view file must be specified. Regardless of where in the component the file including the view is, only the name of the view file is required, not its path.

## UIM Page Field Level Validations

Field level validation appear in a cluster above the fields. The validation messages do not appear in the same order as the fields are displayed.

### UIM Pages

“Cúram web client overview” on page 1 covered the basic concepts behind UIM pages and what clusters, lists, action sets, action controls, containers, and fields are, so this information will not be repeated here.

The elements in a page must follow a strict order imposed by the XML Schema definition of UIM. However, this order is only imposed when editing using a schema-aware XML editor. The JSP generator does not check the ordering at present. The order in which elements are presented in the child element tables in this reference is the order in which the elements should be used in the UIM documents unless otherwise indicated. There is no specific ordering for attribute values.

## Externalized Strings

All string values and image references in UIM documents must be externalized, i.e., the actual values are stored in files separated from the UIM. This aids maintenance and allows the application to be localized.

See “Externalized Strings” on page 29 for details on externalizing strings.

## UIM Reference for Pages and Views

### Introduction

This section describes the PAGE and VIEW elements and all of the child elements that they can contain with the exception of WIDGET elements. These are treated in the next section.

Most elements have a list of attributes that can be used in any order. Some attributes are optional and have default values when omitted. Others can have one of a range of values. Boolean attributes can only have the values true and false (case-sensitive).

Many elements can have child elements and these are listed in the order in which they must be added and include details on their cardinality. Cardinalities use “0” to indicate that the element is optional, “1” to indicate that it can appear only once, and “n” to indicate that it can appear any number of times. The “..” indicates the range of the cardinality. For example, “0..1” indicates that the element can appear zero or one times in this location, i.e., it is optional, while “1..n” indicates that an element must appear at least once, but can appear any number of times thereafter.

### Connection Types

UIM pages use connections for associating components on a page with actual data. The connection type is reflected in the connection tag name and is roughly equivalent to data direction. The three types of connection available are SOURCE, TARGET and INITIAL (see “SOURCE” on page 105, “TARGET” on page 106, and “INITIAL” on page 78, respectively).

Connection endpoints are further distinguished by the setting of the NAME attribute. The value of this attribute may be the name of the server interface used, TEXT, CONSTANT, or JSCRIPT\_REF or PAGE. These values designate objects which supply or consume data. JSCRIPT\_REF can only be a TARGET connection with either PAGE or a server interface defined in the DISPLAY phase, as the SOURCE connection. TEXT or CONSTANT can only be used when TARGET has a server interface defined in the ACTION phase.



```

<PAGE PAGE_ID="APage">
  <PAGE_TITLE>
    <CONNECT>
      <SOURCE NAME="TEXT" PROPERTY="Page.Title.Static"/>
    </CONNECT>
  </PAGE_TITLE>

  <SERVER_INTERFACE NAME="DISPLAY_SI"
                    CLASS="sourceClass"
                    OPERATION="read"
                    PHASE="DISPLAY"/>
  <SERVER_INTERFACE NAME="ACTION_SI"
                    CLASS="targetClass"
                    OPERATION="modify"
                    PHASE="ACTION"/>

  <PAGE_PARAMETER NAME="P_PARAM"/>

  <CONNECT>
    <SOURCE NAME="CONSTANT"
          PROPERTY="From.Constants.Props"/>
    <TARGET NAME="ACTION_SI"
          PROPERTY="aProperty"/>
  </CONNECT>

  <ACTION_SET BOTTOM="true" TOP="false">
    <ACTION_CONTROL TYPE="SUBMIT" LABEL="Button.Submit">
      <LINK_PAGE_ID="APage">
        <CONNECT>
          <SOURCE NAME="DISPLAY_SI" PROPERTY="PARAM"/>
          <TARGET NAME="PAGE" PROPERTY="P_PARAM"/>
        </CONNECT>
      </LINK>
    </ACTION_CONTROL>
  </ACTION_SET>

  <CLUSTER NUM_COLS="1" SHOW_LABELS="false">
    <FIELD LABEL="Label.Text">
      <CONNECT>
        <SOURCE NAME="DISPLAY_SI" PROPERTY="sourceField"/>
      </CONNECT>
      <CONNECT>
        <TARGET NAME="ACTION_SI" PROPERTY="targetField"/>
      </CONNECT>
    </FIELD>
  </CLUSTER>
</PAGE>

```

*Figure 33. Connection Types Example*

Most frequent is a connection to a server interface. Here, the NAME attribute corresponds to an existing (i.e. declared on the page) SERVER\_INTERFACE NAME attribute value (DISPLAY\_SI and ACTION\_SI in the example above).

A value of TEXT means data is sourced from a properties file. The PROPERTY attribute in this case contains the name of an externalized string in a page-specific property file. In the example, the file APage.uim has a page title which references the Page.Title.Static property in the associated APage.properties file.

A value of CONSTANT provides similar functionality to TEXT but the externalized string is component-specific rather than page-specific and is sourced from a file called Constants.properties. In the example, there is a page level connection to a From.Constants.Props property.

A connection might also source its data from a page parameter (i.e., a variable declared on a page, P\_PARAM in the example). In this case PAGE is used as the value of the NAME attribute.

There are limitations and restrictions on the use of the various connection types in various contexts. The UIM element descriptions below detail these limitations where they arise.

## **ACTION CONTROL**

The ACTION\_CONTROL element defines a link (text based), button or file download link that the user can activate on a page.

### **Cancel Button:**

An UIM action control with TYPE of ACTION and no explicit link specified ('previous' control further in the text) implicitly leads to the page which linked to it and had the "SAVE\_LINK=true" specified in UIM for that link. This type of action is used for the Cancel Button.

However, as no page history is memorised and supported, only a single implicit transfer back is possible. Therefore in a situation when consecutive screens contain 'previous' controls, only the 'previous' control on the last screen would correctly pass the flow back with the subsequent attempt to get to the page before it will result in an error.

The screen flow with 'previous' controls is not recommended in the content pane of the tabbed v6 application as it breaks usability, however it could still be used in the modal wizard type flows or other contexts not bound to the tabbed navigation (like nested pages). Therefore, if such a screen flow contains more than one consecutive "previous" controls, they must explicitly link to the page to go to when clicked.

### **File Downloads:**

An ACTION\_CONTROL with the TYPE set to FILE\_DOWNLOAD results in the generation of a hyperlink on the page. Clicking on the hyperlink invokes a special FileDownload servlet included in the Cúram CDEJ that returns the contents of a file from the database. The FileDownload servlet is configured with the server interface to call to get the file contents and the parameters to pass to identify that file. The configuration is performed in the curam-config.xml file. A single server interface can be configured for each page of the application that includes file download action controls. An example configuration is shown in "File Downloads," below:

A WIDGET with the TYPE set to FILE\_DOWNLOAD can also be used to generate a hyperlink to download a file. You should use the ACTION\_CONTROL element when the hyperlink text is the fixed LABEL value. The FILE\_DOWNLOAD WIDGET allows the hyperlink text to be a dynamic value retrieved from a server interface property.

```

<APP_CONFIG>
  <FILE_DOWNLOAD_CONFIG>
    <FILE_DOWNLOAD_PAGE_ID="FileDownload"
      CLASS="curam.interfaces.FilePkg.File_read_TH">
      <INPUT PAGE_PARAM="fileID" PROPERTY="key$fileID"/>
      <FILE_NAME PROPERTY="dtls$fileName"/>
      <FILE_DATA PROPERTY="dtls$fileData"/>
    </FILE_DOWNLOAD>
  </FILE_DOWNLOAD_CONFIG>
</APP_CONFIG>

```

Figure 34. Example Configuration for File Download

Each configuration for downloading files is contained in a FILE\_DOWNLOAD element within the FILE\_DOWNLOAD\_CONFIG element in the configuration file. There should be one FILE\_DOWNLOAD element for each page that contains file download action controls.

The FILE\_DOWNLOAD element takes two attributes: PAGE\_ID for the identifier of the page containing the action controls to which this configuration will be applied, and CLASS containing the name of the server interface that will be called by the FileDownload servlet when the generated hyperlink is invoked.

The FILE\_DOWNLOAD element can contain zero or more INPUT elements specifying the key values to set before the server interface is called. These INPUT elements associate page parameters with properties of the server interface. The PAGE\_PARAM attribute specifies the name of the page parameter whose value will be used as a key value, and the PROPERTY attribute specifies the key property of the server interface that must be set to identify the file. The page parameters are set by the LINK element within the ACTION\_CONTROL, as you will see below.

The other three elements, FILE\_NAME and FILE\_DATA, and CONTENT\_TYPE all have PROPERTY attributes that indicate the properties of the server interface that will contain the name of the file, the contents of the file, and the content type of the file respectively, after the server interface is called. This data is returned to the client in response to the activation of the hyperlink and the user's browser will present them with the download dialog box prompting them to save or open the file.

Where property names are specified, the names must be written in full and cannot be abbreviated like they can in UIM documents.

#### Attributes:

The ACTION\_CONTROL element has the following attributes. The LABEL attribute must be present.

Table 5. Attributes of the ACTION\_CONTROL Element

Attribute Name	Required	Default	Description
LABEL	See above.		A reference to an externalized string containing the label text for this action control. If the TYPE is ACTION, this will be the text of the hyperlink. If the TYPE is SUBMIT, this will be caption of the submit button.
LABEL_ABBREVIATION	No		A reference to an externalized string containing the label abbreviation text for this action control. This label abbreviation is placed only on table headers in a LIST.

Table 5. Attributes of the ACTION\_CONTROL Element (continued)

Attribute Name	Required	Default	Description
TYPE	No	ACTION	The type of action control to create. There are six types: ACTION (the default) defines a link to another page, SUBMIT forwards the page's form data to the action phase for processing, DISMISS closes a pop-up page, SUBMIT_AND_DISMISS combines a submit with closing a pop-up page (see "Pop-up Pages" on page 247 for details on working with pop-up pages), FILE_DOWNLOAD defines a link that triggers the download of a file from the server, and CLIPBOARD places a predefined value to the system clipboard. Please note, the CLIPBOARD type control is only functional in Internet Explorer as it relies on the JavaScript specific to that browser.
STYLE	No		The class name of the CSS style to use when formatting the action control. Supported by action controls in action sets only.
CONFIRM	No		Use the CONFIRM attribute of ACTION_CONTROL to force a confirmation dialog when the action control is activated.  The value of the CONFIRM attribute is a reference to the confirmation message in the page properties file.
DEFAULT	No	false	If there is more than one submit action on a page, it is useful to specify which one is executed when the user hits the Enter key. This is especially recommended when the submitting action controls are contained within the different action sets as in this case the default action could be different than the first submit action declared on the page. The default action can be specified by setting this attribute to true. Note that only one submit action on a page can have a DEFAULT value of true.

Table 5. Attributes of the ACTION\_CONTROL Element (continued)

Attribute Name	Required	Default	Description
ACTION_ID	No		<p>A custom identifier for action controls of TYPE = SUBMIT. It is used in conjunction with ACTION_ID_PROPERTY attribute of SERVER_INTERFACE element to inform the server side code which action control was used to make the server call.</p> <p>This attribute is only valid on action controls of TYPE = SUBMIT.</p> <p>The value of this attribute among the action controls within the page must be unique.</p> <p>The value of this attribute must be in the format suitable for the domain associated with the property specified in the ACTION_ID_PROPERTY attribute of SERVER_INTERFACE.</p> <p>This attribute must be either specified on all action controls within the page or not specified on any of them.</p> <p>If this attribute is specified then the ACTION_ID_PROPERTY attribute of SERVER_INTERFACE must also be specified.</p>
IMAGE	No		<p>The value of this attribute refers to an externalized string which maps to a specific icon or graphic in the application. An action control with this attribute can only be used within a CONTAINER element.</p>
ALIGNMENT	No	RIGHT	<p>When contained in a page level ACTION_SET of a Modal Dialog, the ALIGNMENT attribute is supported. This will define the individual horizontal alignment of the action control. It can be set to LEFT or RIGHT. The default is to right aligned.</p>

**Child Elements:**

The ACTION\_CONTROL element can contain the following child elements:

Table 6. Child Elements of the ACTION\_CONTROL Element

Element Name	Cardinality / Description
LINK	<p>0..1. An action control with a TYPE of ACTION that has no LINK element will create a link to the previous page in the history that had SAVE_LINK set to true on the link that led to this page (this is typically used for <b>Cancel</b> buttons). However this type of ACTION_CONTROL should not be present on a page that is directly referenced by any tabbed configuration artifact. Also, if this type of ACTION_CONTROL is preceded by another ACTION_CONTROL of the same type in the page history, there is the potential of a circular reference between these pages.</p> <p>An action control with a TYPE of SUBMIT that has no LINK element will submit the field values to the action phase and then return to the previous page in the history that had SAVE_LINK set to true on the link that led to this page.</p> <p>An action control with a TYPE of FILE_DOWNLOAD only requires a link if it must provide the page parameter values specified in the INPUT elements of its configuration. Each CONNECT element in the link can contain a SOURCE element to specify the value and a TARGET element specifying the page parameter to which to map the value. The PROPERTY attribute value of the page parameter must match the PAGE_PARAM attribute value of the INPUT element in the configuration.</p>
CONNECT	<p>0..1. A CONNECT element specifying a single SOURCE end-point. As a direct child it is used only for an action control with a TYPE of CLIPBOARD. Such an action control places predefined textual data into the system clipboard when clicked.</p> <p>Text to be copied to clipboard can be sourced from the server, the request or a properties file.</p> <p>The CONNECT element used can only contain a SOURCE element with a NAME property of PAGE, TEXT or the name of a server interface defined within the page.</p>
SCRIPT	<p>0..n. A script element associated with an action control. For a detailed description of this element see “SCRIPT” on page 102.</p> <p>SCRIPT elements are not supported on ACTION_CONTROL elements with a type of CLIPBOARD.</p>
CONDITION	<p>0..1. Affects whether or not the ACTION_CONTROL is displayed.</p>

When linking to another page, the link must specify all page parameters declared on the target page.

## ACTION SET

The ACTION\_SET element groups a number of ACTION\_CONTROL elements together. Depending on the context in which the action set is defined, the action controls will be displayed in differing ways.

At the page level, action controls are displayed at the left side of the page title bar, see the Page Level Action Control in User Interface Element 10 of “Application user interface overview” on page 4. If the action set contains two or less action controls, then each link is displayed side by side with a new item icon to the left of it. The SEPARATOR child element has no affect.

If three or more action controls exist at the page level, then a drop down menu will display each action control as a menu item. In this case, the SEPARATOR element inserts a gray separator into the drop down menu at the position indicated in the UIM file.

At the list level, all action controls will be displayed in a menu drop down. The SEPARATOR element inserts a gray separator into the drop down menu.

For action sets defined at the cluster or list level, the action controls can be displayed above and/or below the element with which the action set is associated and are aligned horizontally.

In all scenarios, conditional links that evaluate to false will not display if HIDE\_CONDITIONAL\_LINKS attribute is set to true, otherwise the conditional link displays but is disabled.

#### Attributes:

The ACTION\_SET element has the following attributes:

*Table 7. Attributes of the ACTION\_SET Element*

Attribute Name	Required	Default	Description
TOP	No	true	Defines whether the action controls will be displayed above the associated element. Can be set to true (the default) or false.
BOTTOM	No	true	Defines whether the action controls will be displayed below the associated element. Can be set to true (the default) or false.
ALIGNMENT	No	DEFAULT	Defines the horizontal alignment of the set of action controls with respect to the associated element. Can be set to LEFT, RIGHT, CENTER, or DEFAULT The value DEFAULT corresponds to the CSS class <i>ac_default</i> in <i>curam_common.css</i> . The default is to be left aligned. In addition, for a page level ACTION_SET in a Modal Dialog, LEFT, RIGHT and DEFAULT values are supported.
TYPE	No	DEFAULT	Defines the location of the action set. This can be set to LIST_ROW_MENU or DEFAULT.  LIST_ROW_MENU is applicable where the ACTION_SET is contained within a LIST. It indicates that the action set should be displayed as a list actions menu within each list row entry.

**Note:** An ACTION\_SET of type LIST\_ROW\_MENU should not be used to open a “Using the Pop-up Page” on page 251.

**Child Elements:**

The ACTION\_SET element can contain the following child element:

*Table 8. Child Elements of the ACTION\_SET Element*

Element Name	Cardinality / Description
ACTION_CONTROL	1..n. See the description of ACTION_SET 's parent element to see what ACTION_CONTROL elements are valid in each context.
CONDITION	0..1. Affects whether or not the ACTION_SET is displayed.
SEPARATOR	0..n. allows the for ability to add a visual separator between action controls that display in the page action drop down menu.

## CLUSTER

The CLUSTER element defines a group of input and/or output fields containing data from any data source (server interface property values, externalized string values, or page parameter values) and supplying data to other data targets (server interface properties, or page parameters). Clusters generally show the fields with labels to the left and these label/field pairs in a number of columns. Clusters can also include other clusters and lists in place of fields to allow more complex layouts.

**Attributes:**

The CLUSTER element has the following attributes:

*Table 9. Attributes of the CLUSTER Element*

Attribute Name	Required	Default	Description
TITLE	No		A reference to an externalized string containing the title string for this cluster.
NUM_COLS	No (see the note in the description)	1	The number of columns to display in the cluster, where a cluster column includes both the label and the field. <b>Note:</b> The NUM_COLS attribute is required in the case where a cluster contains a field element that has the ADDRESS_DATA domain data type. The NUM_COLS attribute is optional for all other domain data types.
TAB_ORDER	No	COLUMN	Indicates the order to layout elements in a multi-column cluster. The elements can be ordered by ROW or COLUMN (default). Please note, if a CLUSTER has NUM_COLS set to 2 or above and is going to contain a mix of LIST and FIELD elements, the TAB_ORDER must be set to ROW.
SHOW_LABELS	No	true	Can be set to true (the default) to show labels beside the field values or false to show no labels at all.



Table 9. Attributes of the CLUSTER Element (continued)

Attribute Name	Required	Default	Description
LAYOUT_ORDER	No	LABEL	Labels can be displayed to the left or to the right of their associated fields. Set the attribute value to LABEL to show labels to the left (this is the default behavior). Set the attribute value to FIELD to show labels to the right.
WIDTH	No	100	The percentage of the width of the containing area that the cluster should occupy.
STYLE	No		The class name of the CSS style to associate with this cluster for formatting.
DESCRIPTION	No		A reference to an externalized string that provides more details about the cluster than the title alone. This will be displayed below the title on the page.
LABEL_WIDTH	No		<p>The percentage of the width of a cluster column that the label should occupy. By default, the web browser will determine the widths as appropriate.</p> <p>This attribute has an effect even if SHOW_LABELS is set to false. It is possible, say, to use action controls in place of text labels. You might want to control the width of these action control columns and you can do that by setting the LABEL_WIDTH attribute. The specified width will be applied to every other column. Whether this starts with the first or second column depends on the LAYOUT_ORDER attribute.</p> <p>The LABEL_WIDTH attribute will not apply to codetable hierarchy fields when SHOW_LABELS is set to false or the FIELD attribute CONFIG has a value of CT_DISPLAY_LABELS. See the CONFIG attribute in “FIELD” on page 72 for more information on code table hierarchies.</p>

Table 9. Attributes of the CLUSTER Element (continued)

Attribute Name	Required	Default	Description
BEHAVIOR	No	EXPANDED	Collapsible clusters can be initially displayed expanded or collapsed on a page. Set the attribute value to EXPANDED to display a collapsible cluster fully expanded. Set the attribute to COLLAPSED to display a collapsible cluster collapsed. To remove the collapsible functionality from a cluster set the attribute to NONE. Note that this attribute is only applicable when the property ENABLE_COLLAPSIBLE_CLUSTERS is not set or is set to true in curam_config.xml. For details see “General Configuration” on page 35. This feature is currently not supported on clusters containing Charts, Evidence Review Widgets, Evidence Comparison Widgets, or Evidence Tab Containers.
SUMMARY	No		A reference to an externalized string containing the summary of this cluster. The SUMMARY attribute describes the purpose and/or structure of a cluster.
SCROLL_HEIGHT	No		Specifies in pixels the desired maximum height of a scrollable cluster.

#### Child Elements:

The CLUSTER element must contain one of the following elements; ACTION\_SET, FIELD, WIDGET, CONTAINER, CLUSTER or LIST.

Table 10. Child Elements of the CLUSTER Element

Element Name	Cardinality / Description
CONDITION	0..1. Affects whether or not the cluster is displayed.
TITLE	0..1. The TITLE element will be displayed above the CLUSTER.
DESCRIPTION	0..1 The “DESCRIPTION” on page 71 element has the same behavior as the DESCRIPTION attribute but allows the description to be built up from a number of sources. If both are specified, this element takes precedence over the corresponding attribute.
ACTION_SET	0..1. The action set can contain ACTION_CONTROL elements of any type. The action controls will be displayed above or below the entire cluster.
FIELD	0..n. The FIELD, CONTAINER, WIDGET, CLUSTER, and LIST elements can be freely intermingled.
WIDGET	0..n. The FIELD, CONTAINER, WIDGET, CLUSTER, and LIST elements can be freely intermingled.
CONTAINER	0..n. The FIELD, CONTAINER, WIDGET, CLUSTER, and LIST elements can be freely intermingled.
CLUSTER	0..n. The FIELD, CONTAINER, WIDGET, CLUSTER, and LIST elements can be freely intermingled.
LIST	0..n. The FIELD, CONTAINER, WIDGET, CLUSTER, and LIST elements can be freely intermingled.

### Dynamic Conditional Clusters:

Up until now UIM supported the `CONDITION` element but only in the context of static data. For more information, see “`CONDITION`” on page 68. The term “static” data referred to the fact that the data which evaluated whether a cluster on a page was displayed or hidden, could only come from previous page(s) not from any fields on the current page. UIM now supports the `CONDITION` element within the context of dynamic data, otherwise known as dynamic conditional clusters. A new attribute is supported on the `CONDITION` element to mark a conditional cluster as being dynamic, for more information, see “Attributes” on page 68.

The fundamental concept of a dynamic conditional cluster is that input field controls within one cluster on a page can control whether another cluster is displayed or not at runtime. In essence the way in which this works is that the input field controls are mapped to a JavaScript function for a cluster. When the JavaScript function is evaluated at runtime, the selected value of the input field controls can be accessed to determine whether the cluster should be displayed or not.

There are three potential sources of data for dynamic conditional clusters. One source of data is dynamic and comes from user interactions with input field controls on that page. The two other sources of data are static in nature and come from page connections and server interface connections.

For dynamic data the following input field controls can be used to control the behavior of a dynamic conditional cluster;

1. Drop Down Lists.

These can be populated from a code table, for more information, see “Populated from a Code-Table” on page 212. Alternatively they can be populated from a display phase server interface, for more information, see “Selection Lists” on page 212.

2. Radio Button Group,

For more information, see “Radio Button Group” on page 246.

3. Check box Fields.

Single check box fields based on the `SVR_BOOLEAN` domain are supported

Data from a page connection or display phase server interface connection can be used in addition to dynamic data, to evaluate whether a dynamic conditional cluster gets displayed or not. For more information, see “Connection Types” on page 54. For more information about display phase server interfaces, see “Attributes” on page 104. In order for data from a page connection to control a dynamic conditional cluster, there needs to be a source page connection mapped to a `JSCRIPT_REF` target connection. In order for data from a display phase server interface connection to control a dynamic conditional cluster, there needs to be a display phase server interface connection mapped to a `JSCRIPT_REF` target connection

Only data types derived from the following underlying domains are supported:

- `CURAM_BOOLEAN`
- `SVR_DATE`
- `SVR_DATETIME`
- `THREE_FIELD_DATE`
- `CURAM_TIME`
- `SVR_DOUBLE`

- SVR\_FLOAT
- SVR\_INT8
- SVR\_INT16
- SVR\_INT32
- SVR\_INT64
- SVR\_CHAR
- SVR\_STRING
- FREQUENCY\_PATTERN

A dynamic conditional cluster can be displayed when a page is initially loaded (without any user interaction) if the data that controls the cluster evaluates to true within the configured JavaScript. When a user interacts with a input field control and selects a particular value from it, it is the raw value that will be immediately passed to a configured JavaScript function which can be used to evaluate whether the cluster will be displayed or hidden. When data is submitted to the server, regardless of whether it's source is static or dynamic, it is the raw value that will be sent. For example, a raw boolean value will be sent for boolean data, a raw unformatted string will be sent for frequency pattern data, a raw integer value will be sent for integer data, e.t.c

Data entered into the fields of a dynamic conditional cluster will only be submitted to the server if the cluster is displayed. If the cluster is hidden when the data is submitted, then default values will be submitted to the server. For example, for input field controls with integer data, the raw value '0' will be submitted. For input fields with string data, the raw the raw value " will be submitted e.t.c. If a user changes their selection value to display a cluster that was previously hidden, any data entered into the fields within the cluster will be reset to the default value. Dynamic conditional clusters can also be pre-populated with initial values when the cluster in initially loaded. Initial data that has been specified in fields contained within dynamic conditional clusters will only be submitted to the server if that cluster is shown. However if a user changes their selection value to display a cluster with initial data that was previously hidden, the initial data will be displayed again to the user.

There are guidelines for configuring dynamic conditional clusters within the application:

- Nested dynamic conditional clusters are supported but it is recommended that there should be a limit of three nested levels deep, otherwise the performance and responsiveness of the page may be impacted.

Additionally when configuring nested dynamic conditional clusters, the value of the CONTROL\_REF attribute on each field must be unique and the value of each EXPRESSION attribute must be unique. For more information on the CONTROL\_REF, see "Attributes" on page 72. For more information on EXPRESSION see "Attributes" on page 102.

- Multiple fields can control a single dynamic conditional cluster and the opposite is also true where one field can control multiple dynamic conditional clusters.
- A controlling field in VIM referenced in a UIM Page can control a dynamic conditional cluster present in that UIM page. The opposite also holds true where a controlling field in a UIM can control a dynamic conditional cluster present in a referenced VIM.

The following are unsupported for dynamic conditional clusters:

- Only the three aforementioned input field controls are supported for dynamic data. No other input field controls are supported.
- When configuring static data for dynamic conditional clusters, only single values are supported, not lists of values.
- Mandatory fields within dynamic conditional clusters are not supported.
- When configuring the values of the CONTROL\_REF and EXPRESSION attributes, please ensure that it is not a JavaScript reserved word, otherwise a JavaScript error will occur.

## Configuring Conditional Clustering

As stated static data can be configured to control dynamic conditional clusters by configuring a page connection or display phase server interface connection as a SOURCE connection and JSCRIPT\_REF as the TARGET connection.

The value of the PROPERTY attribute on the JSCRIPT\_REF target connection will be transformed in to a JavaScript variable with the same name and which can be referenced as *curam.dcl.getField('PROPERTY\_VALUE')*, where PROPERTY\_VALUE refers to the value of the PROPERTY attribute on the JSCRIPT\_REF target. Likewise the value of the CONTROL\_REF attribute will be transformed into a JavaScript variable with the same name and which can be referenced as *curam.dcl.getField('CONTROL\_REF\_VALUE')*, where CONTROL\_REF\_VALUE refers to the value of the CONTROL\_REF attribute. The *curam.dcl.getField()* function gets the value from a data source as described above. See more information on this function within the JavaScript documentation.

The following steps are required to configure dynamic conditional clusters:

1. Configure the SCRIPT\_FILE attribute of the PAGE element to configure the JavaScript file that contains the configured JavaScript functions. For more information, see “Attributes” on page 102
2. The following example shows how to configure static data from a page connection and display server interface connection respectively.
 

```
<CONNECT>
  <SOURCE NAME="PAGE" PROPERTY="param1"/>
  <TARGET NAME="JSCRIPT_REF" PROPERTY="staticRef1"/>
</CONNECT>
<CONNECT>
  <SOURCE NAME="DISPLAY" PROPERTY="stringField1">
  <TARGET NAME="JSCRIPT_REF" PROPERTY="staticRef2">
</CONNECT>
```
3. To configure a field that will control a dynamic conditional cluster, add the CONTROL\_REF attribute on the appropriate FIELD element. The following example shows this.
 

```
<FIELD LABEL="Field.Label" CONTROL_REF="widgetRef1">
  ...
</FIELD>
```
4. At the cluster level, set the TYPE attribute to DYNAMIC on the CONDITION element. For more information, see “Attributes” on page 68. An example of the setting is as follows:
 

```
<CLUSTER TITLE="Cluster.Title" ... />
  <CONDITION TYPE="DYNAMIC">
    <SCRIPT EXPRESSION="displayCluster1"/>
  </CONDITION>
</CLUSTER>
```
5. The recommended location for the JavaScript file that is referenced by the SCRIPT\_FILE attribute and which contains the function to evaluate whether the

cluster(s) are displayed or not. It should be located in the same location as the UIM page or an appropriate jsript directory that contains other JavaScript files. Any variables referenced by *curam.dcl.getField()* must refer to a JSCRIPT\_REF property value or the value of a CONTROL\_REF attribute or a JavaScript error will occur. The following example shows how a JavaScript function consumes the data configured and may be evaluated to display or hide a cluster.

```
function displayCluster1() {
    // field1 is the value defined in the CONTROL_REF attribute
    if(curam.dcl.getField('staticRef1') == true && curam.dcl.getField('staticRef1') == 'Astring' &&
    {
        return curam.dcl.CLUSTER_SHOW;;
    }
    return curam.dcl.CLUSTER_HIDE;
}
```

## CONDITION

The CONDITION element represents the condition under which an ACTION\_SET, ACTION\_CONTROL, LIST, or a CLUSTER is displayed. If a condition evaluates to true, then the parent element will be displayed; if the condition evaluates to false, then the parent element is not displayed with the following exception: an ACTION\_SET or ACTION\_CONTROL element will display disabled links if the condition evaluates to false and the HIDE\_CONDITIONAL\_LINKS attribute on the PAGE element or in the curam\_config.xml file has been set to false. Conditional ACTION\_SETS and ACTION\_CONTROLS are mutually exclusive from one another and therefore the CONDITION element should be set for either one (depending on the requirements) but not both.

Finally, if the condition equates to false for those conditional action sets or action controls which appear as drop down menu items, then a single disabled menu item titled, 'No Contents' is displayed (upon selecting the drop down menu icon).

### Attributes:

The CONDITION element has the following attributes:

Table 11. Attributes of the CONDITION element

Attribute Name	Required	Default	Description
TYPE	No		Configuring the TYPE to be DYNAMIC enables cluster be dynamically displayed depending on input from the current UIM page.

### Child Elements:

The CONDITION element must contain either an IS\_TRUE element or an IS\_FALSE element. It must not be empty and it must not contain more than one element.

Table 12. Child Elements of the CONDITION Element.

Element Name	Cardinality / Description
IS_TRUE	0..1 If the property referenced by the IS_TRUE element returns true then the condition is true.

Table 12. Child Elements of the **CONDITION** Element. (continued)

Element Name	Cardinality / Description
IS_FALSE	0..1 If the property referenced by the IS_FALSE element returns false then the condition is true.
SCRIPT	0..1 This is used to configure a JavaScript function that evaluates a Dynamic Conditional Cluster.

For Agenda Player specific use, see “Agenda Player” on page 254

## CONNECT

The **CONNECT** element defines a data connection between two connection end points such as server interface bean properties, page parameters, screen controls, localized string values, etc.

### Attributes:

The **CONNECT** element has no attributes.

### Child Elements:

The **CONNECT** element must contain at least one of the child elements from the table below, but the details of how these elements are used depends on the context in which the **CONNECT** element is defined. See the specific parent or child element's description for more details.

Table 13. Child Elements of the **CONNECT** Element

Element Name	Cardinality / Description
INITIAL	0..1. This element is only valid in <b>CONNECT</b> elements contained within <b>FIELD</b> elements.
SOURCE	0..1. Within a <b>FIELD</b> element, the <b>SOURCE</b> is the source of the value displayed in the field control (unless <b>INITIAL</b> is used).
TARGET	0..1. Within a <b>FIELD</b> element, the <b>TARGET</b> is the property to which the value in the field control will be assigned.

## CONTAINER

The **CONTAINER** element groups **FIELD**, **ACTION\_CONTROL** and **IMAGE** elements so that they can be used in a single cell of a **CLUSTER** or **LIST** element.

### Attributes:

The **CONTAINER** element has the following attributes:

Table 14. Attributes of the **CONTAINER** Element

Attribute Name	Required	Default	Description
LABEL	No		A reference to an externalized string that should be used as the associated label for this container.
LABEL_ABBREVIATION	No		A reference to an externalized string containing the associated label abbreviation text for this container. This label abbreviation is placed only on table headers in a <b>LIST</b> .

Table 14. Attributes of the CONTAINER Element (continued)

Attribute Name	Required	Default	Description
WIDTH	No	100	The percentage of the width of the field value cell in the cluster or list that the container should occupy.
ALIGNMENT	No	DEFAULT	Defines the horizontal alignment of the elements within the container. Can be set to LEFT, RIGHT, CENTER, or DEFAULT. The value DEFAULT corresponds to the CSS class <i>default</i> in <i>curam_common.css</i> . Currently the default is to be left aligned.
SEPARATOR	No		A reference to an externalized string to use as the separator between the elements within the container.
STYLE	No		A CSS class to be applied to this container.

#### Child Elements:

The CONTAINER element can contain the following child elements. It must contain at least one element.

Table 15. Child Elements of the CONTAINER Element

Element Name	Cardinality / Description
FIELD	0..n. The FIELD, ACTION_CONTROL, IMAGE and WIDGET elements can be freely intermingled.
IMAGE	0..n. The FIELD, ACTION_CONTROL, IMAGE and WIDGET elements can be freely intermingled.
ACTION_CONTROL	0..n. The FIELD, ACTION_CONTROL, IMAGE and WIDGET elements can be freely intermingled.
WIDGET	0..n. The FIELD, ACTION_CONTROL, IMAGE and WIDGET elements can be freely intermingled.

#### DETAILS\_ROW

The DETAILS\_ROW element is used within a LIST element to enable each row to be expanded to show more details about the row. Child elements of DETAILS\_ROW define the content that is displayed when the row is expanded. Currently only the INLINE\_PAGE element is supported as a child.

When a page containing a list with expanded rows is submitted to self or refreshed after a dialog submit, the rows will be re-expanded after the page loads again. This functionality is based on page parameters to the corresponding INLINE\_PAGE and the following limitations apply:

- The INLINE\_PAGE must take page parameters and they must uniquely identify each row within the list.
- The functionality is supported for pages submitted to self or refreshed after a dialog submit. In all other cases all rows after refresh are reset to default - collapsed.
- If the list contains duplicate items, only the first of them will retain the expanded state after refresh.
- If an edit operation in a dialog changes values that are used in the INLINE\_PAGE parameters, this row will be collapsed after refresh.



- If an expanded row is expandable conditionally and it is no longer expandable after the page is refreshed, its state will be always set to collapsed.

Note that DETAILS\_ROW element is not allowed in a list using the SCROLL\_HEIGHT attribute.

#### Attributes:

The DETAILS\_ROW element has the following attribute.

Table 16. Attributes of the DETAILS\_ROW Element

Attribute Name	Required	Default	Description
MINIMUM_EXPANDED_HEIGHT	Yes	30px	Specifies minimum height in pixels of an expanded row for this list. To be used for in-line pages that are expected to contain nested lists with long actions menus which would not fit to the default expanded row height.

#### Child Elements:

The DETAILS\_ROW element contains the following child elements.

Table 17. Child Elements of the INFORMATIONAL Element

Element Name	Cardinality / Description
INLINE_PAGE	1..1 This defines the page to be shown when the list row is expanded. Currently this is the only supported element, hence it's 1..1 cardinality.
CONDITION	0..1. Affects whether or not the details row is displayed.

## DESCRIPTION

The DESCRIPTION element defines the description associated with a PAGE\_TITLE, CLUSTER or LIST element. A DESCRIPTION is constructed by concatenating a number of connection sources together.

#### Attributes:

The DESCRIPTION element has the following attributes:

Table 18. Attributes of the DESCRIPTION Element

Attribute Name	Required	Description
SEPARATOR	No	A reference to an externalized string to use as the separator between the elements within the container.

#### Child Elements:

The DESCRIPTION element can contain child elements as follows:

Table 19. Child Elements of the DESCRIPTION Element

Element Name	Cardinality / Description
CONNECT	1..n. Only CONNECT elements containing SOURCE elements can be included (one SOURCE per CONNECT). Sources can be server interface properties or, with the NAME attribute set to TEXT, references to strings in a properties file.

## FIELD

The FIELD element specifies a data value to be displayed in a CLUSTER, a value to be retrieved from the user via an input control in a CLUSTER, or a list of data values to be displayed in a LIST column. FIELD elements can also be aggregated within CONTAINER elements so that they fill a single cell of a CLUSTER or LIST element.

Please note that, when the FIELD element is used to display a code table hierarchy either on an edit or ready-only page, the following should apply:

- For an edit page, only one FIELD element is needed to display a code table hierarchy with a domain definition inherited from CODETABLE\_CODE that has the code table name set to the lowest level code table in a hierarchy. The CDEJ infrastructure automatically determines its code table hierarchy and then displays however many dropdowns it has, i.e. if it is a three level hierarchy, then the three levels are displayed.
- For a read-only page, however only the lowest level code table value is displayed on the screen by the same way using a single FIELD element as the edit page. And the CDEJ infrastructure does not support on displaying its full hierarchy.

### Attributes:

The FIELD element has the following attributes:

*Table 20. Attributes of the FIELD element*

Attribute Name	Required	Default	Description
LABEL	No		A reference to an externalized string that needs to be used as the associated label for this field. The LABEL attribute is mandatory when a CONNECT element exists that contains a TARGET.
LABEL_ABBREVIATION	No		A reference to an externalized string that contains the associated label abbreviation text for this field. This label abbreviation is placed only on table headers in a LIST.
DESCRIPTION	No		A reference to an externalized string that is displayed below the label text.
ALT_TEXT	No		A reference to an externalized string that is used as the alternate text for the field. This reference is applicable only when the field has a target connection, that is, it is an input field. If this attribute is added to a mandatory input field, the text Mandatory is appended to the externalized string. If this attribute is not specified, the LABEL is used. Browsers that are supported by the Cúram application display alternate text when the mouse is hovered over the input control.
WIDTH	No		Specifies the width of the field value within its cluster or list cell.

Table 20. Attributes of the FIELD element (continued)

Attribute Name	Required	Default	Description
WIDTH_UNITS	No	PERCENT	The units in which the width is interpreted. This measurement can be PERCENT to indicate the percentage of the space available to the field, or CHARS to indicate the number of visible characters the field needs to accommodate.
HEIGHT	No	1	For input fields that resolve to a text input control, this input specifies the number of visible lines of text that the control displays. For input fields that resolve to a selection list, this value specifies the number of entries that are initially displayed. For example, a scrollable selection list is displayed instead of a drop-down selection list.
ALIGNMENT	No	DEFAULT	Defines the horizontal alignment of the field value. Can be set to LEFT, RIGHT, CENTER, or DEFAULT. The value DEFAULT corresponds to the CSS class <i>default</i> in the <i>curam_common.css</i> . Currently the default is to be left-aligned. In a CLUSTER, only input fields are aligned. In a LIST, all fields are aligned.
USE_DEFAULT	No	true	If set to true (the default) and the field has no SOURCE connection, then if a sensible default value for the field can be determined automatically, it is displayed.  For example, numeric fields display a zero, string fields are empty, and date fields defaults to the current date.
USE_BLANK	No	false	If the field source is a code-table-based property, or a server interface list property, it is displayed in a list. If this attribute is set to true, an extra blank value is added to the top of the list.

Table 20. Attributes of the FIELD element (continued)

Attribute Name	Required	Default	Description
CONTROL	No	DEFAULT	<p>The CONTROL attribute can take one of a number of values:</p> <ul style="list-style-type: none"> <li>• DEFAULT - The field behaves in the standard fashion.</li> <li>• SUMMARY, DYNAMIC, DYNAMIC_FULL_TREE, and FAILURE - These settings apply only to rules fields. For more information, see “Rules Trees” on page 215.</li> <li>• SKIP - Indicates that the field is only present to occupy space in a CLUSTER to balance the layout. No label or value is displayed. However, the label background still is presented.</li> <li>• TRANSFER_LIST - Enables a list on a page to be displayed as a transfer list widget. This mode is only applicable and supported for list controls with multiple selection capability.</li> <li>• CT_HIERARCHY_HORIZONTAL - Displays a list as a horizontal code table hierarchy.</li> <li>• CT_HIERARCHY_VERTICAL - Displays a list as a vertical code table hierarchy. For more information on code table hierarchies, see the <i>Cúram Server Developers Guide</i>.</li> </ul>
CONFIG	No		<p>Identifies configuration details for this FIELD instance. This attribute can be used only with a FIELD whose CONTROL attribute is for a widget that supports configuration. For example, if the CONTROL attribute is DYNAMIC for a FIELD of the RESULT_TEXT domain then the CONFIG attribute needs to match an ID on a config element in the RulesDecisionConfig.xml file. For more information on configuration, see “Dynamic Rules View” on page 216.</p> <p>CT_DISPLAY_LABELS : Displays labels for each code table in a code table hierarchy. . For more information on code table hierarchies, see the CONTROL attribute in “FIELD” on page 72.</p>

Table 20. Attributes of the FIELD element (continued)

Attribute Name	Required	Default	Description
INITIAL_FOCUS	No	false	A FIELD element, whose INITIAL_FOCUS attribute is set to true, gets focus when the page is displayed. In other words, the cursor is placed in that field ready for data entry. If no FIELD requests the initial focus, the cursor is placed in the first input field on the page. It is not allowed to have more than one FIELD with the INITIAL_FOCUS attribute set to true specified on a page.
PROMPT	No	false	This attribute is used to configure a placeholder value in the field that is associated with a Date Selector; if the field is blank. On focus, the placeholder text disappears to allow for data entry.
CONTROL_REF	No		This setting is used to configure Dynamic Conditional Clusters. The purpose of the CONTROL_REF is to set the controlling input. If something is selected, a cluster becomes visible. The CONTROL_REF attribute is set to an identifier that is evaluated by the JavaScript.

#### Child Elements:

The FIELD element can contain the following child elements:

Table 21. Child Elements of the FIELD Element

Element Name	Cardinality / Description
CONNECT	<p>0..3. A field can contain up to three CONNECT elements. The SOURCE connection defines the initial value for the field (this will be the static value shown if there is no target end-point, or the initial value of an input control if there is a target end-point). The TARGET end-point defines the property that will be set from the field value during the action phase. If a TARGET end-point is specified the SOURCE end-point can only be from a server interface property. This is because domain information is required to correctly format the value for display in the input control.</p> <p>If an INITIAL end-point is used and the property is not a list value, it specifies the visible value of the field (which will be read-only). The SOURCE value will be hidden, and the pair of values can only be changed via a pop-up search page. The TARGET end-point will be supplied with the hidden value.</p> <p>If an INITIAL end-point is used and the property is a list value, it specifies the visible values in a drop-down list. The INITIAL element's HIDDEN_PROPERTY specifies the corresponding list of hidden values that will be supplied to the TARGET end-point. In this instance, the SOURCE end-point specifies one of the hidden values in the list that should be used as the initial list selection (the corresponding visible value is displayed).</p>

Table 21. Child Elements of the FIELD Element (continued)

Element Name	Cardinality / Description
LINK	0..1. Only valid for output fields (those with no TARGET connection end-point). The value of the output field will be used as the text for the hyperlink specified by this LINK element.  If the field is based on a domain which requires a pop-up window then the LINK element can be used to supply parameters to the pop-up page. In this case the LINK element must not have a PAGE_ID attribute specified. See "Using the Pop-up Page" on page 251 for further details.
LABEL	0..1. Allows the label for a FIELD to be constructed from a number of sources. If both a LABEL attribute and LABEL child element are specified, the element takes precedence. See "LABEL" on page 84 for more details.
SCRIPT	0..n. A script file associated with this FIELD that contains JavaScript code to be activated in response to the specified event on the field control. See "SCRIPT" on page 102 for more details and limitations on this element usage.

## FOOTER\_ROW

The FOOTER\_ROW element is used to define a single footer row at the end of a list. A list can have multiple footer rows.

A FOOTER\_ROW element may only contain FIELD elements. The number of FIELD elements must match the number of columns in the parent list.

There are two CSS classes associated with footer row fields. A FIELD with a TEXT SOURCE connection is output with the footerheader CSS class. All other SOURCE connections are output with the footervalue CSS class. Both of these classes are defined in curam\_common.css and can thus be customized.

Spanning column widths are supported through the use of skip fields. For instance, if one normal field and two skip fields are used in a FOOTER\_ROW element, this normal field will span three columns. Example code is shown below.

```

<LIST TITLE="List.Title.One" DESCRIPTION="List.Description.One">
  <FIELD LABEL="Field.Title.BankId" WIDTH="40">
    <CONNECT>
      <SOURCE NAME="DISPLAY" PROPERTY="dtls$entitlement"/>
    </CONNECT>
  </FIELD>
  <FIELD LABEL="Field.Title.Name" WIDTH="35">
    <CONNECT>
      <SOURCE NAME="DISPLAY" PROPERTY="dtls$date"/>
    </CONNECT>
  </FIELD>
  <FIELD LABEL="Field.Title.VersionNo" WIDTH="25">
    <CONNECT>
      <SOURCE NAME="DISPLAY" PROPERTY="dtls$total"/>
    </CONNECT>
  </FIELD>

  <FOOTER_ROW>
    <FIELD CONTROL="SKIP"/>
    <FIELD WIDTH="40" LABEL="Field.Title.Footer" >
      <CONNECT>
        <SOURCE NAME="TEXT" PROPERTY="Footer.Text.Entitlement"/>
      </CONNECT>
    </FIELD>
    <FIELD>
      <CONNECT>
        <SOURCE NAME="DISPLAY" PROPERTY="dtls$entitlement"/>
      </CONNECT>
    </FIELD>
  </FOOTER_ROW>
</LIST>

```

Figure 35. Example of a FOOTER\_ROW in a List.

#### Attributes:

The FOOTER\_ROW element has no attributes.

#### Child Elements:

The FOOTER\_ROW element contains the following child elements.

Table 22. Child Elements of the FOOTER\_ROW Element

Element Name	Cardinality / Description
FIELD	1..n Each FOOTER_ROW must contain the same number FIELD elements as there are columns in the parent LIST.

## IMAGE

The IMAGE element inserts an image into a CONTAINER.

#### Attributes:

The IMAGE element has attributes as follows:

Table 23. Attributes of the IMAGE Element

Attribute Name	Required	Default	Description
IMAGE	Yes		A reference to an entry in the Image.properties file.
LABEL	Yes		The entry in the UIM's associated properties file which is used as the alternate (or "alt") text of the image.
STYLE	No		A CSS style to associate with the image.

**Child Elements:**

The IMAGE element has no child elements.

**INCLUDE**

The INCLUDE element indicates that the elements within an external UIM view document should be included at this position in the page.

**Attributes:**

The INCLUDE element has attributes as follows:

*Table 24. Attributes of the INCLUDE Element*

Attribute Name	Required	Default	Description
FILE_NAME	Yes		The file name of the UIM view document to be included. No path to the file should be specified. The file name alone is sufficient to identify the document.

**Child Elements:**

The INCLUDE element has no child elements.

**INITIAL**

This element is only valid within a CONNECT element contained in a FIELD element. Use of this connection type is described in further detail in the following sections:

- For pop-up pages see “Pop-up Pages” on page 247
- For selection lists populated from server interface properties see “Selection Lists” on page 212

**Attributes:**

The INITIAL element has the following attributes:

*Table 25. Attributes of the INITIAL Element*

Attribute Name	Required	Default	Description
NAME	Yes		The name of the SERVER_INTERFACE instance to use as the source of the property value.
PROPERTY	Yes		The source of the data to be displayed in the visible field. This can be a list or a non-list field type.
HIDDEN_PROPERTY	No		The source of the list data that has a one-to-one mapping (based on the list indexes) to the list property specified in the PROPERTY attribute.

**Child Elements:**

The INITIAL element contains no child elements.

**INFORMATIONAL**

The INFORMATIONAL element is used to display informational messages returned from the server. These are different to error messages in that the server call



completes successfully. The messages are created in server side code using the SDEJ Informational Manager API (see the *Cúram Server Developers Guide* for more details). This API allows a developer to assign messages to an output list field(s). This field must then be referenced using child CONNECT elements. The message will be displayed at the top of the page in the same area as error messages and this may not be on the page on which the INFORMATIONAL element was defined. It could be on the following page or on the parent page in the case of modal dialogs. Finally, messages will never be displayed within the context panel of the application, but will instead will always be displayed within the main content area of the page.

**Attributes:**

The INFORMATIONAL element has no attributes.

**Child Elements:**

The INFORMATIONAL element contains the following child elements.

*Table 26. Child Elements of the INFORMATIONAL Element*

Element Name	Cardinality / Description
CONNECT	1..n Each CONNECT element specifies a single SOURCE end-point. This is a field of a bean which contains informational messages.

**INLINE PAGE**

The INLINE\_PAGE element is used to display the contents of one UIM page *in-line* in another. Currently this is only supported within the DETAILS\_ROW element of a LIST to support displaying extra content when a list row is expanded.

**Attribute:**

The INLINE\_PAGE element has the following attributes:

*Table 27. Attributes of the INLINE\_PAGE Element*

Attribute Name	Required	Default	Description
PAGE_ID	Yes		The ID of the UIM page to display. Circular dependencies must not be introduced. If a page is used inline, it is not allowed for it to be mapped to a tab at the same time.
URI_SOURCE_NAME	No		The name of the SERVER_INTERFACE instance to use as the source of the URI. This attribute is paired with URI_SOURCE_PROPERTY. Note that a URI can only be sourced from a server interface. This attribute cannot be used to specify page parameters or properties files as a source for the URI. The server interface reference must be called during the “display-phase” and the parent ACTION_CONTROL must be of type ACTION when this property is used.
URI_SOURCE_PROPERTY	No		The name of the property to use as the source of the URI.

**Child Elements:**

The `INLINE_PAGE` element contains the following child elements.

*Table 28. Child Elements of the `INLINE_PAGE` Element*

Element Name	Cardinality / Description
CONNECT	0..n. Connections on this element define the parameters to be exported to the page targeted by the <code>INLINE_PAGE</code> elements <code>PAGE_ID</code> attribute. The <code>CONNECT</code> should contain both a <code>SOURCE</code> and a <code>TARGET</code> element and the <code>TARGET</code> element should have the <code>NAME</code> attribute set to <code>PAGE</code> and the <code>PROPERTY</code> attribute set to the name of the page parameter.

**Restrictions on usage:**

The UIM page opened in an expanded row is intended for only viewing additional information about the row. It should not be used for editing information about that row. Instead a modal dialog should be launched from the page when an edit is required.

As these pages are for viewing information only, the following rules/restrictions should be noted for these "in-line" pages.

- The "in-line" pages displayed in an expanded row must not be used for editing information.
- The "in-line" pages displayed in an expanded row should not display very complex widgets that require a "full screen". This includes the following domain specific controls and UIM elements:
  - Decision Assist: The Decision Matrix Widget
  - Decision Assist: Typical Picture Editor Widget
  - Decision Assist: Evidence Review Widget
  - Agenda Player
  - Batch Function View
  - The Rules Simulation Editor
  - The Rates Table
  - The Meeting View Widget
  - The `FILE_EDIT` Widget
  - The Calendar
  - Rules Trees

**Note:** There are no validations in place for these restrictions and it is the responsibility of the developer to ensure they don't use unsupported widgets in an expandable list.

**`IS_FALSE`**

A Boolean test to evaluate if the parent `CONDITION` succeeds or fails. This element evaluates to true when the referenced property value is false.

**Attributes:**

The `IS_FALSE` element has the following attributes:

Table 29. Attributes of the IS\_FALSE Element

Attribute Name	Required	Default	Description
NAME	Yes		The name of the SERVER_INTERFACE instance to use as the source of the property value.
PROPERTY	Yes		The name of the property being accessed. It must be a Boolean value.

See “Attributes” for more details on the use of this element to access the values of action-phase server interface properties.

#### Child Elements:

The IS\_FALSE element contains no child elements.

## IS TRUE

A Boolean test to evaluate if the parent CONDITION succeeds or fails. This element evaluates to true when the referenced property value is true.

#### Attributes:

The IS\_TRUE element has the following attributes:

Table 30. Attributes of the IS\_TRUE Element

Attribute Name	Required	Default	Description
NAME	Yes		The name of the SERVER_INTERFACE instance to use as the source of the property value.
PROPERTY	Yes		The name of the property being accessed. It must be a Boolean value.

In the majority of cases the NAME and PROPERTY combination will reference a display-phase server interface property. However when a page submits to itself using an ACTION\_CONTROL with a child LINK element that has the PAGE\_ID set to THIS (e.g., a search page), properties of the action-phase server interface can be referenced. When the page is first displayed the action-phase server interface will not be in scope and the property is treated as if its value is false. When the page is submitted, the action-phase server interface will be in scope and the referenced property will be evaluated as normal.

#### Child Elements:

The IS\_TRUE element contains no child elements.

## JSP SCRIPTLET

The JSP\_SCRIPTLET element defines JSP scriptlet code that should be inserted into the page at that point relative to any other LIST or CLUSTER elements. Any TextHelper beans declared by a SERVER\_INTERFACE element to be in the DISPLAY phase are available to the scriptlet by getting the attribute of the page context with the same name as the NAME attribute of the SERVER\_INTERFACE element. An example is shown in “JSP SCRIPTLET” below.

```

<SERVER_INTERFACE NAME="MyBeanName" CLASS="MyClass"
                  OPERATION="getMyData" />
<JSP_SCRIPTLET>
  <![CDATA[
    curam.omega3.texthelper.TextHelper th =
      pageContext.findAttribute("MyBeanName");
    String myValue = th.getFieldValue("myPropertyName");
    out.print("VALUE: " + myValue);
  ]]>
</JSP_SCRIPTLET>

```

Figure 36. Example JSP SCRIPTLET Accessing a TextHelper

As the code within the JSP\_SCRIPTLET element may contain reserved XML characters<sup>2</sup>, you can either replace these characters with the appropriate XML character entity or enclose the contents of the element in the CDATA (“character data”) block as shown above which will prevent the XML parser from trying to interpret the contents of the block.

A common use of the JSP\_SCRIPTLET element is to write code that will redirect the current page to another page. “JSP SCRIPTLET” on page 81, below, shows an example of this.

```

<PAGE PAGE_ID="Activity_resolveAttendeeHome">
  <JSP_SCRIPTLET>
    <![CDATA[
      curam.omega3.request.RequestHandler rh
        = curam.omega3.request.RequestHandlerFactory
          .getRequestHandler(request);
      String context = request.getContextPath() + "/";
      context += curam.omega3.user.UserPreferencesFactory
        .getUserPreferences(pageContext.getSession())
          .getLocale() + "/";
      String url = context + "UserCalendarPage.do?"
        + "startDate=&calendarViewType=CVT3";
      url += "&" + rh.getSystemParameters();
      response.sendRedirect(response.encodeRedirectURL(url));
    ]]>
  </JSP_SCRIPTLET>
</PAGE>

```

Figure 37. Example JSP SCRIPTLET Redirecting to a Page

This demonstrates the API used to access the system parameters that control an application's ability to return to previous pages. The information about the previous page is stored in the system parameters accessible via the RequestHandler. getSystemParameters() method. By adding the system parameters, any **Cancel** button on the following page will return to the expected page when clicked. The RequestHandlerFactory. getRequestHandler() method is passed the JSP request object and will return the appropriate request handler. The system parameters should be appended to the redirect URL and just require a separating “&” character as they are already formatted in *name = value* pairs.

When using a JSP\_SCRIPTLET to redirect to another page, the JSP\_SCRIPTLET should be the only child element of the PAGE element. When this is the case, no HTML content will be generated for the page: it will not be displayed, so no HTML is required. If other elements are present, then HTML content will be generated. This can include the page header, navigation menus, footer, title, etc. If this HTML

2. The reserved characters in XML are “ ’ ” “ ” ” “ & ” “ < ” and “ > ”. The respective XML character entities are “ &apos; ”, “ &quot; ”, “ &amp; ”, “ &lt; ”, and “ &gt; ”.

content exceeds the size of the buffer on the web container serving the page, then the content will be transmitted to the web browser. Once any content is transmitted in this way, the redirect operation will have no effect. Therefore, ensuring that the page contains a single JSP\_SCRIPTLET element and no other elements will ensure that the redirect operation works as expected.

If you need to access a TextHelper instance from a JSP scriptlet that redirects to another page, then you cannot use the SERVER\_INTERFACE element to declare the TextHelper as shown in “JSP SCRIPTLET” on page 81, as this extra element would cause HTML content to be generated. Instead, you must declare the TextHelper instance within the scriptlet code as shown below.

It should be noted that, when using JSP\_SCRIPTLET, there is limited error handling capability. Thus, code should not make calls to secured server interface methods. Instead, the target page of any JSP\_SCRIPTLET should be secured appropriately.

```
<PAGE PAGE_ID="Activity_resolveApplicationHome">
<JSP_SCRIPTLET>
<![CDATA[
    curam.omega3.request.RequestHandler rh
        = curam.omega3.request.RequestHandlerFactory
            .getRequestHandler(request);
    String context = request.getContextPath() + "/";
    context += curam.omega3.user.UserPreferencesFactory
        .getUserPreferences(pageContext.getSession())
            .getLocale() + "/";
    String activityID = request.getParameter("ID");
    String eventType = request.getParameter("TYPE");
    String url = context;

    curam.interfaces.ActivityPkg.Activity_readDescription_TH
        th = new curam.interfaces.ActivityPkg
            .Activity_readDescription_TH();
    th.setFieldValue(
        th.key$activityDescriptionKey$activityID_idx,
        activityID);
    th.callServer();

    String description = th.getFieldValue(
        th.result$activityDescriptionDetails$description_idx);
    if (eventType.equals("AT1")) {
        url = "Activity_viewUserRecurringActivityPage.do?";
    } else {
        url = "Activity_viewUserStandardActivityPage.do?";
    }
    url += "activityID=" + activityID;
    url += "&description="
        + curam.omega3.request.RequestUtils.escapeURL(
            description);
    url += "&" + rh.getSystemParameters();
    response.sendRedirect(response.encodeRedirectURL(url));
]]>
</JSP_SCRIPTLET>
</PAGE>
```

*Figure 38. Example JSP\_SCRIPTLET Redirecting and Accessing a TextHelper*

When adding parameters to the parameter list, care must be taken if the parameter value may contain non-ASCII characters. Values containing non-ASCII characters must be escaped before they are added to the parameter list to ensure that the characters are preserved correctly. The RequestUtils.escapeURL(String) method

can be used to perform the escaping. An example of the Java code to perform this escaping is shown in the example above. Code following that pattern should be included within your JSP scriptlet.

**Attributes:**

The JSP\_SCRIPTLET element has no attributes.

**Child Elements:**

The JSP\_SCRIPTLET element contains no child elements. The body of the element must only contain the JSP scriptlet code to be inserted into the page.

**LABEL**

The LABEL element can be used as a child element of FIELD to construct a label by concatenating multiple values. An example of the field and label data is shown in "LABEL," below.

```
<CLUSTER TITLE="Cluster.Title">
  <FIELD>
    <LABEL>
      <CONNECT>
        <SOURCE NAME="TEXT" PROPERTY="Label.Text" />
      </CONNECT>
      <CONNECT>
        <SOURCE NAME="DISPLAY" PROPERTY="personName" />
      </CONNECT>
      <CONNECT>
        <SOURCE NAME="TEXT" PROPERTY="Label.Separator" />
      </CONNECT>
      <CONNECT>
        <SOURCE NAME="DISPLAY" PROPERTY="dateOfBirth" />
      </CONNECT>
    </LABEL>

    <CONNECT>
      <TARGET NAME="ACTION" PROPERTY="fieldName"/>
    </CONNECT>
  </FIELD>
</CLUSTER>
```

Figure 39. Example of a Dynamic LABEL

**Attributes:**

The LABEL element has no attributes:

**Child Elements:**

The LABEL element can contain the following child elements.

Table 31. Child Elements of the LABEL Element

Element Name	Cardinality / Description
CONNECT	1..n. A CONNECT element specifying a single SOURCE end-point. Action-phase server interfaces cannot be used in the SOURCE end-point.

**LINK**

The LINK element specifies the page to go to after an action phase. Alternatively, a LINK element can specify any external web page or certain resource. Links can contain CONNECT elements to map values to parameters to be added to the link.

**Attributes:**

The LINK element has the following attributes. Note that the PAGE\_ID, PAGE\_ID\_REF, URL, URI, and URI\_REF attributes are mutually exclusive as well as the pair of attributes URI\_SOURCE\_NAME and URI\_SOURCE\_PROPERTY.

Please note that attributes that have the ability to link to external web pages or resources (i.e mailto: links) will have their link back functionality stripped away. This link back functionality keeps a link to the previous page. An example of where this is needed is with cancel buttons where if they are used, the page will link back to the previous page. In order to keep this, the link will have to be to an internal Curam page. In order to mark a link as being a link to an internal Curam page, the keyword 'curam:' needs to be added before the link text.

*Table 32. Attributes of the LINK Element*

Attribute Name	Required	Default	Description
PAGE_ID	No		<p>The unique identifier of the page to be opened. This is the value of the PAGE_ID attribute of the PAGE element in the required UIM page document.</p> <p>If this attribute is set to the PAGE_ID of the current page, the page will be re-opened with all the input fields reset to their default state.</p> <p>If the link is on an action control with a TYPE set to SUBMIT and this attribute is set to the value THIS, the link will return to the current page after the action phase and the input fields will not be reset to their default state. This is useful for search pages where the search criteria need to be preserved.</p>
PAGE_ID_REF	No		A PAGE_ID can alternatively be specified by reference to an entry in the CuramLinks.properties file. This allows many links to refer to the same target page yet all can be updated by changing the entry in the CuramLinks.properties file.
URL	No		It is recommended to use the new URI attribute which is described below. The URL attribute is maintained for backward compatibility.
URI	No		Rather than link to another page in the application, the URI attribute allows the creation of a link to any URI whatsoever. This can be used to link to pages or other resources completely outside of the application. Parameters must be supplied by CONNECT elements within the LINK to ensure correct encoding.

Table 32. Attributes of the LINK Element (continued)

Attribute Name	Required	Default	Description
URI_REF	No		A URI (or URL) can alternatively be specified by reference to an entry in the CuramLinks.properties file. This allows many links to refer to the same target yet all can be updated by changing the entry in the CuramLinks.properties file. The file can be placed in any component in the application.
URI_SOURCE_NAME	No		The name of the SERVER_INTERFACE instance to use as the source of the URI. This attribute is paired with URI_SOURCE_PROPERTY. Note that a URI can only be sourced from a server interface. This attribute cannot be used to specify page parameters or properties files as a source for the URI. The server interface reference must be called during the “display-phase” and the parent ACTION_CONTROL must be of type ACTION when this property is used.
URI_SOURCE_PROPERTY	No		The name of the property to use as the source of the URI.
OPEN_NEW	No	false	When set to true, this flag indicates that the linked page should be opened in a new window. When set to false (the default) the linked page will be opened in the current window. This setting is only supported for links to external sites.
SAVE_LINK	No	true	This attribute indicates that the page containing the link should be returned to if an action control on the target page is configured to return to the previous page. An action control without a LINK child element will return the user to the previous page. If there is a sequence of pages and any one of them needs to go back to a “starting” page, then each page in the sequence should set this attribute to false so that subsequent pages do not return to their immediate previous page in the chain.
SET_HIERARCHY_RETURN_PAGE	No	false	This attribute is no longer used but has been retained in the UIM schema to avoid upgrade impact.
USE_HIERARCHY_RETURN_PAGE	No	false	This attribute is no longer used but has been retained in the UIM schema to avoid upgrade impact.



Table 32. Attributes of the LINK Element (continued)

Attribute Name	Required	Default	Description
HOME_PAGE	No		<p>If this attribute is set to true, the link will take a user directly to their home page. During development the home page can be configured by setting the "application code" field of the Cúram "users" table. This value of this field corresponds to an entry on the APPLICATION_CODE code-table. At runtime, the Cúram Administration application allows the home page to be set when creating or editing a user.</p> <p>Note, that in the development environment Java EE security is not enabled. Therefore, since a user name is not available the home page link cannot be displayed.</p>
OPEN_MODAL	No	"false"	<p>If this attribute is set to true, the link will open the referenced page in a new window. The new window is modal, meaning that while it is open the parent window cannot be accessed. When a user navigates from the original page in the modal dialog, either by submitting a form or clicking a link, the modal dialog is closed, and the parent page that spawned it is sent to the new location.</p>
DISMISS_MODAL	No	"true"	<p>If this attribute is set to false, the link will open the referenced page in the same pop-up window, modal or normal depending on what the browser supports.</p>
WINDOW_OPTIONS	No	"width=800, height=450"	<p>The size of each modal dialog is configurable using this parameter. The value of the attribute is a comma separated list of name value pairs. The currently supported options are width and height, both of which take an integer value, which is translated directly to a pixel value. Any other parameters will cause an exception to be thrown. This attribute should only be set when OPEN_MODAL is set to true on the same LINK tag.</p>

#### Child Elements:

The LINK element can contain the following child elements:

Table 33. Child Elements of the LINK Element

Element Name	Cardinality / Description
CONNECT	0..n. Connections on a link define the parameters to be exported to the page targeted by the link. The CONNECT should contain both a SOURCE and a TARGET element and the TARGET element should have the NAME attribute set to PAGE and the PROPERTY attribute set to the name of the page parameter. Any type of SOURCE element can be used except the TEXT. Also, in the scenario where the LINK is inside an ACTION_CONTROL with TYPE = SUBMIT, the SOURCE must have an ACTION phase bean, a page parameter or a CONSTANT. The reason being the URL is generated in the action class and the DISPLAY bean is not accessible at the stage.
CONDITION	0..1. Affects whether or not the link is displayed.

### Modal Dialogs:

A Modal Dialog is similar to a Pop-up Page, in that it opens a dialog box to display a page on top of the main application content. However, modal dialog is different in a number of ways.

- When a modal dialog is open, its parent page cannot be accessed. The parent page is grayed-out and ignores any user action.
- Changing the page in the Modal Dialog, either by submitting a form or by clicking a hyperlink, causes it to close, and the parent page to be changed to the changed page, with the following exceptions
  - If the page linked to has the same id as the current modal page (e.g. a 'save & new' button/link), then the page will be refreshed within the same modal window
  - If the link clicked has the attribute DISMISS\_MODAL set to false, the page linked to will opened within the same modal window
  - If the link clicked has the attribute OPEN\_MODAL set to true, it will open in a new modal window
- The usage of Modal Dialogs is different to that of Pop-up pages. It is considerably less complex, consisting of using either one or two optional attributes on the LINK tag.

### Using Modal Dialogs

A LINK tag is made to open in a Modal Dialog, rather than the default action of opening a new page in the same window, by setting the OPEN\_MODAL attribute to true.

```
<LINK PAGE_ID="MultiSelectWidgetResult" OPEN_MODAL="true" />
```

Note in the example the use of the OPEN\_MODAL attribute on the LINK tag.

Setting OPEN\_MODAL on a LINK that is inside an ACTION\_CONTROL of type SUBMIT has no effect. Setting OPEN\_MODAL =true on a link implies also having DISMISS\_MODAL =false on that link, and setting DISMISS\_MODAL =true on it is ignored. Setting DISMISS\_MODAL =false implies OPEN\_MODAL =false, so there is no need to set it.

## Configuring Modal Dialogs

Modal Dialogs can be individually configured by setting the `WINDOW_OPTIONS` attribute on a `LINK` tag which has the `OPEN_MODAL` attribute set to `true`. Multiple options can be set via this attribute, which is formatted as a comma separated list of name value pairs. The currently supported parameters are

- `width` - sets the width of the Modal Dialog, measured in pixels. This parameter takes an integer value.
- `height` - sets the height of the Modal Dialog, measured in pixels. This parameter takes an integer value.

```
<LINK PAGE_ID="MultiSelectWidgetResult" OPEN_MODAL="true"
      WINDOW_OPTIONS="width=600,height=500" />
```

Note in the example above the use of the `WINDOW_OPTIONS` attribute. The values specified for `width` and `height` are simple integers and do not have any alphabetic characters appended. A default width of 600 pixels is used if no `width` parameter is specified. If no `height` parameter is specified the height will be automatically calculated to accommodate the page contents. If an unsupported parameter is placed in the `WINDOW_OPTIONS`, a build time exception will be thrown.

If the `WINDOW_OPTIONS` attribute is also specified on the `PAGE` element of the page a `LINK` points to, it will take precedence over the value specified on the `LINK` itself.

The minimum required height for modal dialogs can be configured using the property `modal.dialogs.minimum.height` that is located in the `ApplicationConfiguration.properties` file.

## Controlling Modal Dialogs from custom JavaScript

Modal Dialogs can be controlled by custom JavaScript using the provided `curam.util.UimDialog` API. For details see the full API documentation in HTML format, accessible by opening `<cdej-dir>\doc\JavaScript\index.html` in a Web browser.

## Loading custom non-UIM pages in a Modal Dialog

Custom non-UIM pages must hook into a specific set of API functions in order to work correctly in a Modal Dialog. These functions are provided by the `curam.util.Dialog` API. The details are available in the full API documentation: `<cdej-dir>\doc\JavaScript\index.html`.

## LIST

The `LIST` element defines the layout of a control used to display lists of data. Each field or action control becomes a column and data values are then tabulated.

### List attributes:

The `LIST` element has the following attributes:

*Table 34. Attributes of the LIST Element*

Attribute Name	Required	Default	Description
TITLE	No		A reference to an externalized string containing the title string for this list. See also note below.

Table 34. Attributes of the LIST Element (continued)

Attribute Name	Required	Default	Description
STYLE	No		The class name of the CSS style to associate with this list for formatting.
DESCRIPTION	No		A reference to an externalized string that provides more details about the list than the title alone. This will be displayed below the title on the page.
SORTABLE	No	true	Lists can be sorted by clicking on the appropriate headers. This is set by default to be enabled without the use of the attribute. This attribute allows this feature to be controlled with false disabling the feature and true enabling it.
SUMMARY	No		A reference to an externalized string containing the summary of this list. The SUMMARY attribute describes the purpose and/or structure of a list.
SCROLL_HEIGHT	No		Specifies in pixels the desired fixed height of a scrollable list. A vertical scrollbar is provided once the list exceeds the scroll height. The scrollbar is only applied to the list body and the list's column headers remain fixed. Scroll height is independent of the list contents and therefore an empty list will still be set to the height specified.

Table 34. Attributes of the LIST Element (continued)

Attribute Name	Required	Default	Description
BEHAVIOR	No		<p>Optional attribute which controls the display and behavior of the toggle button used to expand or collapse the list.</p> <p>Three value options are available for this attribute:</p> <ul style="list-style-type: none"> <li>• NONE which prevents the toggle button from being displayed in the list header.</li> <li>• EXPANDED : the toggle button is displayed and the list is initially expanded.</li> <li>• COLLAPSED : the toggle button is displayed and the list is initially collapsed.</li> </ul> <p>When the BEHAVIOR is not set for a list, its default value of EXPANDED is implied.</p> <p>Note that this attribute is only applicable when the property ENABLE_COLLAPSIBLE_CLUSTERS is not set or is set to true in curam_config.xml. For details see “General Configuration” on page 35.</p>
PAGINATED	No	true	Enables the ability to page through lists displayed in Cúram pages. Any LIST longer than the configured minimum size will display only the first "page" of data and the pagination controls will be displayed below the list.
DEFAULT_PAGE_SIZE	No	Based on the global configured value, usually 15.	Specifies the page size the list will get by default. The page size can be then changed at runtime by the user.
PAGINATION_THRESHOLD	No	Based on the global configured value, usually same as DEFAULT_PAGE_SIZE.	Specifies the minimum list size at which pagination will be enabled. For shorter lists there will be no pagination, even if otherwise pagination is switched on.

**Note:** Lists on search pages now display the number of items found as a result of the search. The number of items will be displayed beside the list title.

The text used to display the number of items can be customized by setting the following property in the CDEJResources.properties file, for example:

record.number.message=Items found:

The actual number of items will be displayed after the text.

This feature only applies to search pages and must be enabled by adding the following to the curam-config.xml file:

```
<LIST_ROW_COUNT>true</LIST_ROW_COUNT>
```

#### Child Elements:

The LIST element can contain the following child elements. It must contain at least one ACTION\_CONTROL, FIELD, or CONTAINER element. SOURCE connections can be made to list or non-list properties. Within a table all list properties must belong to the same list structure defined in the server interface model. This ensures that they are all the same length. The number of rows in the list will be equal to the number of elements in the list properties. The value of a non-list property is simply repeated on each row.

Table 35. Child Elements of the LIST Element

Element Name	Cardinality / Description
TITLE	0..1. The TITLE element will be displayed above the LIST.
DESCRIPTION	0..1 The "DESCRIPTION" on page 71 element has the same behavior as the DESCRIPTION attribute but allows the description to be built up from a number of sources. If both are specified, this element takes precedence over the corresponding attribute.
ACTION_SET	0..1. The action set can contain ACTION_CONTROL elements of any type. The action controls will be displayed above and/or below the entire list.
FIELD	0..n. The FIELD, CONTAINER, and ACTION_CONTROL elements can be freely intermingled. Only output fields can be used (i.e., fields with no target connection.)
CONTAINER	0..n. The FIELD, CONTAINER, and ACTION_CONTROL elements can be freely intermingled. Within the container, only output fields can be used (i.e., fields with no target connection.)
CONDITION	0..1. Affects whether or not the list is displayed.
FOOTER_ROW	0..n. This should be defined after all other child elements.
LIST_CONNECT	0..n. This should be defined after all other child elements. The only supported child elements are SOURCE and TARGET. The SOURCE connection must be a display phase bean.

#### Editable Lists:

This section describes editable lists.

Up until now UIM only supported read only lists, where FIELD elements within a list could only have SOURCE connections. UIM now supports FIELD elements within a list that have SOURCE and TARGET connections, otherwise known as editable lists. FIELD elements that have only a TARGET connection with **no** SOURCE connection are not supported. The reason for this is that only Clusters that have input fields should be used for creating business data within the application.

There are essentially two distinct types of editable lists:

1. Editable Lists controlled by checkbox

If the **first** field within a list has both connections and it has SVR\_BOOLEAN as it's underlying domain, the first column in the list will be displayed as a check box. When a user selects the check box on a particular row, the other editable columns within that row can be edited (their value updated).

If a user does not select a check box, then the other editable columns within that row are disabled and cannot be edited. The key point, is that within a Check Box Controlled Editable List, all the editable columns are controlled by the first column - the check box column.

## 2. Editable Lists

If the first field within a list has both connections and it does **not** have SVR\_BOOLEAN as it's underlying domain then it will be treated as a normal editable list, where all of the editable columns are decoupled from one another. Even if there is a check box column within the list (not the first column), it cannot control whether the other editable lists are editable or not.

A mixture of read only fields and editable fields are permitted within a list but suffice to say that the read only columns cannot be updated.

Within editable lists it is possible to submit hidden values (per list row) to the server that are not visible within the list. The LIST\_CONNECT element is supported within a LIST element in order to facilitate this. For more information, refer to "Child Elements" on page 92. For example in the context of a person object, if there was an editable list on a page that displayed details about the person, there may be the need to submit the persons ID (unique identifier) to the server as a hidden field without displaying it to the user. In this case a single LIST\_CONNECT element could be configured within the list to pass the unique id for each person (each row represents a single person).

Only the following data types are supported on fields within editable lists:

- CURAM\_BOOLEAN,
- THREE\_FIELD\_DATE,
- SVR\_DOUBLE,
- SVR\_FLOAT,
- SVR\_INT8,
- SVR\_INT16,
- SVR\_INT32,
- SVR\_INT64,
- SVR\_CHAR, and
- SVR\_STRING.

## MENU

The MENU element is used to define six types of menus in a Cúram client application. The menu types are:

- **STATIC** : The menu is made up of ACTION\_CONTROL elements that will appear on the page menu. The ACTION\_CONTROL elements must have the TYPE of ACTION.
- **NAVIGATION** : The menu is made up of ACTION\_CONTROL elements that will be appended to the "Navigation" menu. The ACTION\_CONTROL elements must have the TYPE of ACTION.
- **DYNAMIC** : The menu is driven by XML data constructed on the server application.

- **INTEGRATED\_CASE** : The menu is driven by XML data constructed on the server application. This menu is specific to the Cúram-style Integrated Case user interface and is rendered as a set of tabs.
- **IN\_PAGE\_NAVIGATION** : The menu is made up of **ACTION\_CONTROL** elements that will appear on the in-page-navigation menu at the top of the main content area.
- **WIZARD\_PROGRESS\_BAR** : This is another specific type of menu rendered as a button bar on the top of the content area in a modal dialog for displaying a sequence of related pages in the wizard manner. The menu is driven by a resource stored in the server application.

#### Attributes:

The **MENU** element has the following attribute:

*Table 36. Attributes of the MENU Element*

Attribute Name	Required	Default	Description
MODE	No	STATIC	<p>The type of menu to create. The mode can be <b>STATIC</b> (the default), <b>NAVIGATION</b>, <b>DYNAMIC</b>, <b>INTEGRATED_CASE</b>, <b>IN_PAGE_NAVIGATION</b> or <b>WIZARD_PROGRESS_BAR</b>.</p> <p>Static, navigation and in-page-navigation menus contain one or more <b>ACTION_CONTROL</b> elements that represent links to other pages. The static menu normally appears just above the main content area of the page. Navigation menu items will be appended to the navigation menu, normally on the left of the page. In-page-navigation menu items appear at the top of the main content area and the wizard progress bar appears at the top of the modal dialog content area.</p> <p>Dynamic menus of both types (<b>DYNAMIC</b> and <b>INTEGRATED_CASE</b>) are created from data retrieved from the server and contain a single <b>CONNECT</b> element specifying a <b>SOURCE</b> end-point to a server interface property.</p>

#### Child Elements:

The **MENU** element can contain the following child elements. Note that the **ACTION\_CONTROL** and **CONNECT** elements are mutually exclusive.

*Table 37. Child Elements of the MENU Element*

Element Name	Cardinality / Description
<b>ACTION_CONTROL</b>	1..n. Only action controls with a <b>TYPE</b> of <b>ACTION</b> can be used.
<b>CONNECT</b>	1. A <b>CONNECT</b> element specifying a single <b>SOURCE</b> end-point.

#### **DYNAMIC and INTEGRATED\_CASE type menus:**

The data for both **DYNAMIC** and **INTEGRATED\_CASE** menu's are driven by the same XML format. An example of the menu data sent by the application server is shown



below.

```
<DYNAMIC_MENU>
  <LINK PAGE_ID="CaseHome"
    DESC="2:field1:curam.omega3.myMessages:info_menu1:()"
    TYPE="case" >
    <PARAMETER NAME="caseID" VALUE="1234" />
  </LINK>
  <LINK PAGE_ID="ProductHome"
    DESC="2:field1:curam.omega3.myMessages:info_menu2:()"
    TYPE="product" >
    <PARAMETER NAME="productID" VALUE="5678" />
    <PARAMETER NAME="caseID" VALUE="1234" />
  </LINK>
</DYNAMIC_MENU>
```

Figure 40. Example of Dynamic MENU Data

All the menu links are contained within the DYNAMIC\_MENU root element. Each entry on the menu is specified by a LINK element. The LINK element has the following attributes:

- PAGE\_ID : Specifies the target page for the link.
- DESC : Specifies the server message catalog entry to be looked up and used as the text for the link. The Cúram SDEJ provides an API to create the string representation of a message catalog entry shown in the example above. Consult the Cúram Server Developers Guide for details on using message catalogs.
- TYPE : specifies a value that is looked up in appropriate menu configuration file (described below) to identify the icon that should be associated with the link.

Each LINK element can contain a number of PARAMETER elements that specify additional parameters that will be added to the link from the menu. The PARAMETER element has the following attributes:

- NAME : The parameter name.
- VALUE : The parameter value.

The configuration files for the DYNAMIC and INTEGRATED\_CASE menu's are DynamicMenuConfig.xml and ICDynamicMenuConfig.xml respectively. The following are examples each configuration file.

```
<?xml version="1.0" encoding="UTF-8"?>
<DYNAMIC_MENU_CONFIG>
  <SEPARATOR IMAGE="Images/separator.gif"
    TEXT="Dyn.Menu.Separator"/>
  <LINK TYPE="case" IMAGE="Images/case.gif"
    TEXT="Dyn.View.Case"/>
  <LINK TYPE="product" IMAGE="Images/product-delivery.gif"
    TEXT="Dyn.View.Product"/>
</DYNAMIC_MENU_CONFIG>
```

Figure 41. Example of a DYNAMIC Menu Configuration File

```
<?xml version="1.0" encoding="UTF-8"?>
<INTEGRATED_CASE_MENU_CONFIG>
  <LINK TYPE="case" IMAGE="Images/case.gif"
    TEXT="Dyn.View.Case"/>
  <LINK TYPE="product" IMAGE="Images/product-delivery.gif"
    TEXT="Dyn.View.Product"/>
</DYNAMIC_MENU_CONFIG>
```

Figure 42. Example of an INTEGRATED\_CASE Menu Configuration File

The differences to note are the root elements, DYNAMIC\_MENU\_CONFIG and INTEGRATED\_CASE\_MENU\_CONFIG, and the SEPARATOR element which is not used in an INTEGRATED\_CASE because of its very specific look and feel.

The SEPARATOR element describes an image or a piece of text used to separate the menu items and has the following attributes:

- IMAGE : Specifies an image to use as the separator.
- TEXT : Specifies an entry in the CDEJResources.properties file. This attribute is mandatory. If an image is specified this will be used as the alternate text for the image, if not, then the text will be displayed.

The LINK element has the following attributes.

- TYPE : This must match the TYPE attribute of the LINK element returned from the server application.
- IMAGE : Specifies an image to use in the link. This attribute is mandatory.
- TEXT : Specifies an entry in the CDEJResources.properties file. This attribute is mandatory. It will be used as the alternate text for the image.

#### The IN\_PAGE\_NAVIGATION type menu:

The in-page navigation menu, see User Interface Element 9 of “Application user interface overview” on page 4, allows for the addition of a set of links which will be displayed as tabs embedded within a UIM page. Each UIM page in the set must define the same MENU element. The currently selected UIM page, aka tab, is identified by the STYLE="in-page-current-link" attribute. This will differ on each of the UIM pages in the set and should be set on the ACTION\_CONTROL that matches the UIM page the MENU is contained in.

```
<PAGE PAGE_ID="InPageNav">
  <PAGE_TITLE>
    <CONNECT>
      <SOURCE NAME="TEXT" PROPERTY="Title.Text"/>
    </CONNECT>
  </PAGE_TITLE>
  <MENU MODE="IN_PAGE_NAVIGATION">
    <ACTION_CONTROL LABEL="Label.page1">
      <LINK PAGE_ID="Page1" SAVE_LINK="false"/>
    </ACTION_CONTROL>
    <ACTION_CONTROL
      LABEL="Page2.Label"
      STYLE="in-page-current-link" >
      <LINK PAGE_ID="Page2" SAVE_LINK="false" />
    </ACTION_CONTROL>
  </MENU>
  .....
</PAGE>
```

Figure 43. Example of the IN\_PAGE\_NAVIGATION menu in UIM

#### WIZARD\_PROGRESS\_BAR menu:

The wizard progress menu bar is inserted on a page by including a MENU element which has a MODE attribute set to WIZARD\_PROGRESS\_BAR. It binds a number of pages, allowing for the sequential navigation through them. For instance, in a modal dialog which contains a wizard progress menu bar, pages can be navigated through by clicking the previous or next button. At the same time, the wizard progress menu bar presented on the top of it will indicate its progress.

#### The UIM wizard pages:

There are some specifics regarding the UIM pages used with the WIZARD\_PROGRESS\_BAR menu:

- The wizard pages should open in the modal dialog. The wizard progress bar functionality should not be used in standard non-modal UIM pages.
- Each page in the wizard flow is implemented as standard UIM with a wizard progress bar widget placed at the top of each page.
- The pages should have action controls for advancing through the wizard (back and forward buttons as required by the scenario). The LINK elements of these action controls should have DISMISS\_MODAL attribute set to false (except for the controls supposed to close the wizard). Additionally, the SAVE\_LINK attribute should also be set to false.

```
<PAGE PAGE_ID="Sample_PageOne">
  <MENU MODE="WIZARD_PROGRESS_BAR">
    <CONNECT>
      <SOURCE
        NAME="DISPLAY" PROPERTY="resourceID" />
      </CONNECT>
    </MENU>
    <PAGE_TITLE>
      <CONNECT>
        <SOURCE NAME="TEXT"
          PROPERTY="PageTitle" />
        </CONNECT>
      </PAGE_TITLE>
      <SERVER_INTERFACE
        CLASS="WizardSample"
        NAME="DISPLAY" OPERATION="getResourceID"
        PHASE="DISPLAY" />
      <ACTION_SET ALIGNMENT="CENTER" TOP="false">
        <ACTION_CONTROL
          LABEL="ActionControl.Label.Cancel"/>
        <ACTION_CONTROL
          LABEL="ActionControl.Label.Next">
          <LINK PAGE_ID="Sample_PageTwo"
            SAVE_LINK="false"
            DISMISS_MODAL="false"/>
        </ACTION_CONTROL>
      </ACTION_SET>
      .....
    </PAGE>
```

Figure 44. An example of wizard-type menu UIM

In the example above the connection in the MENU provides the identifier of the server-side resource describing this wizard (see below).

#### **Wizard menu configuration:**

The text required by the wizard progress bar items come from a property resource whose identifier must be provided to the wizard progress bar menu.

```

Number.Wizard.Pages=2
Sample_pageOne.Wizard.Item.Text=Child
Sample_pageOne.Wizard.Page.Title=Step 1: Child Details
Sample_pageOne.Wizard.Page.Desc=Capture some details
Wizard.PageID.1=Sample_pageOne

Sample_pageTwo.Wizard.Item.Text=Parent
Sample_pageTwo.Wizard.Page.Title=Step 2: Parent Details
Sample_pageTwo.Wizard.Page.Desc=Capture some details 1
Wizard.PageID.2=Sample_pageTwo

```

Figure 45. Example of the required properties in the resource store property file

Table 38. Properties in the wizard defining resource

Property Name	Description
Number.Wizard.Pages	The value of this property defines the number of items to be rendered for the wizard progress bar. The value must be a numeric whole number greater than zero.
<PageID>.Wizard.Item.Text	Defines the text to be displayed within the wizard progress bar item for each page of the wizard. There must be one of these properties defined for each page in the wizard. The property is uniquely identified for each wizard page by the <PageID> prefix which represents the actual identifier of that UIM page in the wizard flow.
<PageID>.Wizard.Page.Title	Defines the title to be displayed within the wizard progress bar for the current page of the wizard. There must be one of these properties defined for each page in the wizard. The property is uniquely identified for each wizard page by the <PageID> prefix which represents the actual identifier of that UIM page in the wizard flow.
<PageID>.Wizard.Page.Desc	Defines the description to be displayed within the wizard progress bar for the current page of the wizard. There must be one of these properties defined for each page in the wizard. The property is uniquely identified for each wizard page by the <PageID> prefix which represents the actual identifier of that UIM page in the wizard flow.
Wizard.PageID.<PageNum>	Defines the position of the page within the wizard flow. The widget uses this information to style the bar items correctly. There must be one of these properties defined for each page in the wizard. This property is uniquely identified for each wizard page by the <PageNum> suffix which represents the position of each page within the list of wizard menu pages.

The order of the properties declaration in the resource is important as the associated menu widget will draw the wizard items for the progress bar in that order. The page title and description are added by the widget for the current page of the wizard.

## PAGE

The PAGE element is the root element of a UIM document that describes the data to be included in a generated JSP page.

### Attributes:

The PAGE element has the following attributes:

*Table 39. Attributes of the PAGE Element*

Attribute Name	Required	Default	Description
PAGE_ID	Yes		An identifier for the page used when referencing the page from LINK elements. This identifier must be unique within a project. The file name of the document must be the same as the value of this attribute and have the extension .uim.
POPUP_PAGE	No	false	Indicates that this page is a pop-up that will be opened from a parent page. Pop-up pages do not include the side-bar, header and footer of standard pages. The value can be set to true or false. The attribute must only be used for pages configured according to "Pop-up Pages" on page 247 (i.e., search pop-up pages).
SCRIPT_FILE	No		The name of the script file containing the JavaScript functions that are specified in the ACTION attribute of any SCRIPT elements on the page. If no SCRIPT_FILE attribute is set on a particular SCRIPT element within a FIELD or ACTION_CONTROL the PAGE script file is used by default. The script file should be added in a component. If another script file has the same name in another component, the version in the highest priority component will be used. Each SCRIPT can specify its own script file if required, or share this common script file.
APPEND_COLON	No		Set to true to automatically append colons to FIELD and CONTAINER labels within CLUSTER elements. This overrides the value of the APPEND_COLON element in the curam-config.xml file for that individual page (see "APPEND_COLON" on page 36).
WINDOW_OPTIONS	No	"width=700, height=auto; calculated"	The size of the page when displayed in a modal dialog is configurable using this parameter. The value of the attribute is a comma separated list of name value pairs. The currently supported options are width and height, both of which take an integer value, which is translated directly to a pixel value. Only a width needs to be specified however as the height will be dynamically calculated. Any other parameters will cause an exception to be thrown.

Table 39. Attributes of the PAGE Element (continued)

Attribute Name	Required	Default	Description
TYPE	No	DEFAULT	Used to define specific types of UIM pages. Two types are supported, DETAILS and SPLIT_WINDOW.  SPLIT_WINDOW enables the use of frames within the page. If the attribute is not present or is set to DEFAULT then frames are not used. See “Agenda Player” on page 254 for an example of use.  DETAILS defines a UIM page that will be used as a context panel page. For more information see “Context panel UIM” on page 152.
HIDE_CONDITIONAL_LINKS	No	TRUE	Set to true to hide conditional links that evaluate to false. Set to false to show a disabled conditional link that evaluate to false. This overrides the value of the HIDE_CONDITIONAL_LINKS element in the curam-config.xml file for that individual page (see “APPEND_COLON” on page 36).

#### Child Elements:

The PAGE element can contain child elements as follows:

Table 40. Child Elements of the PAGE Element

Element Name	Cardinality / Description
INCLUDE	0..1. This element can be used before any other child element of a PAGE element.
PAGE_TITLE	0..1. This does not apply to context panel UIM pages. In this case, the PAGE_TITLE element is mandatory. See “Context panel UIM” on page 152 for more information.
DESCRIPTION	0..1
SHORTCUT_TITLE	0..1
SERVER_INTERFACE	0..n. Multiple SERVER_INTERFACE elements are supported, however it is recommended that only one SERVER_INTERFACE with the PHASE attribute set to ACTION is defined per PAGE element. See “SERVER INTERFACE” on page 104 for more information.
INFORMATIONAL	0..1
MENU	0..2. The page can contain one optional static and one optional dynamic menu as well as append extra items to the navigation menu.
ACTION_SET	0..1. In this context, the action set defines the set of action controls that will appear around the page's main content area.
PAGE_PARAMETER	0..n

Table 40. Child Elements of the PAGE Element (continued)

Element Name	Cardinality / Description
CONNECT	0..n. In this context, the connections can copy values directly from the properties of source server interfaces to properties of the target server interfaces. Each CONNECT element should contain both a SOURCE and a TARGET element.
JSP_SCRIPTLET	0..n. JSP_SCRIPTLET, CLUSTER and LIST can be intermingled freely and the order in UIM will be preserved in the generated page.
CLUSTER	0..n. JSP_SCRIPTLET, CLUSTER and LIST can be intermingled freely and the order in UIM will be preserved in the generated page.
LIST	0..n. JSP_SCRIPTLET, CLUSTER and LIST can be intermingled freely and the order in UIM will be preserved in the generated page.
SCRIPT	0..n. A script associated with the PAGE that will be activated in response to the specified event. See "SCRIPT" on page 102 for more details.

Where a page is configured to contain a large number of scrollable list and cluster elements (approximately 15), it may cause JSP compile issues in Weblogic. This is due to a Weblogic system limitation in how big a page can be rendered at run time. To overcome this restriction, arrange the display of the required scrollable lists and clusters over a number of pages.

## PAGE\_PARAMETER

The PAGE\_PARAMETER element declares a parameter to the current page. Once a parameter is declared, it can be used as the source of a connection by setting the connection source bean NAME attribute to PAGE.

### Attributes:

The PAGE\_PARAMETER element has the following attributes:

Table 41. Attributes of the PAGE\_PARAMETER Element

Attribute Name	Required	Default	Description
NAME	Yes		The name of the parameter to use in SOURCE connection end-points.

### Child Elements:

The PAGE\_PARAMETER element contains no child elements.

## PAGE\_TITLE

The PAGE\_TITLE element defines the title that appears at the top of a page's main content area. A title is constructed by concatenating a number of connection sources together. These can include localized strings and data from server interfaces.

**Note:** The PAGE\_TITLE element defines the text for the tab title bar where the UIM page is used as a context panel page. See "Context panel UIM" on page 152 for more information.

### Attributes:

The PAGE\_TITLE element has the following attributes:

*Table 42. Attributes of the PAGE\_TITLE Element*

Attribute Name	Required	Default	Description
DESCRIPTION	No		A reference to a localized string that provides a more detailed description of the page than the title alone. This will be displayed with the title in the page's main content area.
STYLE	No		The name of the CSS class to use when displaying the title on the page.
ICON	No		A reference to an entry in the Image.properties file specifying the image file to use beside the title in the main content area.

#### **Child Elements:**

The PAGE\_TITLE element can contain child elements as follows:

*Table 43. Child Elements of the PAGE\_TITLE Element*

Element Name	Cardinality / Description
CONNECT	1..n. Only CONNECT elements containing SOURCE elements can be included (one SOURCE per CONNECT). Sources can be server interface properties or, with the NAME attribute set to TEXT, references to strings from a properties file.
DESCRIPTION	0..1 The "DESCRIPTION" on page 71 element has the same behavior as the DESCRIPTION attribute but allows the description to be built up from a number of sources. If both are specified, this element takes precedence over the corresponding attribute.

## **SCRIPT**

The SCRIPT element defines an exit point to allow the invocation of a script (JavaScript) in response to an event. Scripts are supported for pages, read-write fields and action controls. These elements are not applicable and not supported for fields within a LIST or read-only fields.

#### **Attributes:**

The SCRIPT element has the following attributes:



Table 44. Attributes of the *SCRIPT* Element

Attribute Name	Required	Default	Description
EVENT	Yes		<p>The JavaScript name of the event as defined in the W3C HTML recommendations.</p> <p>JavaScript events are valid within the PAGE, FIELD or ACTION_CONTROL elements, with the exception of FIELD elements within a LIST or read-only FIELD elements.</p> <p>Note that the ONCLICK event will be ignored for ACTION_CONTROL with a TYPE of CLIPBOARD (for further information see "ACTION CONTROL" on page 56.).</p> <p>In addition, please note that by default when a link is clicked in the Cúram application the link is processed by Cúram specific code. If you are adding some scripting to a link and do not want this default processing to occur, the event should be stopped using the JavaScript APIs available.</p>
ACTION	Yes		<p>The JavaScript to be invoked if the event occurs. This must be a function call including parameters, if any. For example; someFunction() or someFunction(someParam) where someParam may be a global variable defined in script file.</p>
SCRIPT_FILE	No		<p>The name of the script file containing the JavaScript functions that are specified in the ACTION attribute of the SCRIPT element. If no SCRIPT_FILE attribute is set on a particular SCRIPT element within a FIELD or ACTION_CONTROL the PAGE script file is used by default. The script file should be added in a component. If another script file has the same name in another component, the version in the highest priority component will be used. If not specified, the SCRIPT will expect to find the functions in the page-level script file specified with the PAGE element's SCRIPT_FILE attribute.</p>
EXPRESSION	No		<p>The name of the a JavaScript function identifier (excluding the parenthesis) that will be used to evaluate whether a dynamic conditional cluster will be displayed or not. The name should ideally reflect the encapsulated logic within the function.</p>

**Child Elements:**

The SCRIPT element contains no child elements.

## SERVER INTERFACE

The SERVER\_INTERFACE element defines a server interface to which other elements of the page can connect.

### Attributes:

The SERVER\_INTERFACE element has the following attributes:

Table 45. Attributes of the SERVER\_INTERFACE Element

Attribute Name	Required	Default	Description
NAME	Yes		A unique name for this instance of the server interface on this page.
CLASS	Yes		The name of the server interface class.
OPERATION	Yes		The name of the server interface operation on the class.
PHASE	No	DISPLAY	<p>The phase of the page in which the server interface is called. This can be DISPLAY (the default) or ACTION. Server interfaces set to the DISPLAY phase are called as the page is displayed (i.e., the execution of the JSP page).</p> <p>Server interfaces set to the ACTION phase are only called in response to the activation of an ACTION_CONTROL with a TYPE of SUBMIT. It is recommended that only one SERVER_INTERFACE is set to the ACTION phase per PAGE.</p>
ACTION_ID_PROPERTY	No		<p>Specifies a name of the server access bean property that will be populated with ACTION_ID of the action control used to make the server call. The value of this attribute must be a valid property name of the corresponding server access bean. The use of shorthand notation is allowed (for example specify theProperty instead of the fully qualified dtls\$theProperty).</p> <p>This attribute is only valid on server interfaces with PHASE = ACTION and must be specified on all server interfaces within the page or not specified on any of them.</p> <p>If multiple server interfaces specify ACTION_ID_PROPERTY with different domains the value of ACTION_ID on all action controls within the page must be suitable for all of the domains. Failing to comply with this rule will lead to error at runtime when the corresponding action control is activated.</p> <p>If this attribute is specified then the ACTION_ID attribute of ACTION_CONTROL element must also be specified.</p>

**Note:** It is technically possible to specify multiple SERVER\_INTERFACE elements set to the ACTION phase. However, this is not recommended. Each SERVER\_INTERFACE is essentially a separate transaction and when an invocation fails, no further invocations of other server interfaces are made and completed transactions are not rolled back.

For example, three SERVER\_INTERFACE elements are defined, each set to the ACTION phase. When the page is executed, the first server interface invocation succeeds and the second fails. In this scenario, the third server interface is never invoked and the action of the first will not be rolled back.

**Child Elements:**

The SERVER\_INTERFACE element contains no child elements.

**SOURCE**

The SOURCE element defines the source end-point of a data connection. The source can be the value of a server interface property, the value of a parameter to the page (which must be declared via the PAGE\_PARAMETER element), or the value of an externalized string.

**Attributes:**

The SOURCE element has the following attributes:

*Table 46. Attributes of the SOURCE Element*

Attribute Name	Required	Default	Description
NAME	Yes		The name of the SERVER_INTERFACE instance to use as the source of the property value, or PAGE, if the source is the value of a page parameter, or TEXT (or CONSTANT) if the source is the value of an externalized text string. TEXT or CONSTANT can only be used when TARGET has a server interface defined in the ACTION phase.
PROPERTY	Yes		The name of the server interface property, the name of the input page parameter, or the string reference to the externalized string whose value is required.

**Child Elements:**

The SOURCE element contains no child elements.

**TAB\_NAME**

The TAB\_NAME element defines the text used for the tab in the tab bar, where the UIM page is used as a context panel UIM page. The text is constructed by concatenating a number of connection sources together. These can include localized strings and data from server interfaces.

This element only applies where the TYPE attribute of the PAGE element is set to DETAILS. See “Context panel UIM” on page 152 for more information.

**Child Elements:**

The TAB\_NAME element can contain child elements as follows:

Table 47. Child Elements of the TAB\_NAME Element

Element Name	Cardinality / Description
CONNECT	1..n. Only CONNECT elements containing SOURCE elements can be included (one SOURCE per CONNECT). Sources can be server interface properties or, with the NAME attribute set to TEXT, references to strings from a properties file.
DESCRIPTION	0..1 The "DESCRIPTION" on page 71 element has the same behavior as the DESCRIPTION attribute but allows the description to be built up from a number of sources. If both are specified, this element takes precedence over the corresponding attribute.

## TARGET

The TARGET element defines the target end-point of a data connection. The target can be the value of a server interface property or the value of a parameter to be exported from the page.

### Attributes:

The TARGET element has the following attributes:

Table 48. Attributes of the TARGET Element

Attribute Name	Required	Default	Description
NAME	Yes		The name of the SERVER_INTERFACE instance to use as the target of the property value, or PAGE, if the target is the value of a page parameter.
PROPERTY	Yes		The name of the server interface property, or the name of the output page parameter whose value is to be set.

### Child Elements:

The TARGET element contains no child elements.

## TITLE

The TITLE element defines the title that appears at the top of a CLUSTER or LIST element. A TITLE is constructed by concatenating a number of connection sources together. These can include localized strings and data from server interfaces.

### Attributes:

The TITLE element has the following attributes:

Table 49. Attributes of the TITLE Element

Attribute Name	Required	Description
SEPARATOR	No	A reference to an externalized string to use as the separator between the elements within the container.

### Child Elements:

The TITLE element can contain child elements as follows:

Table 50. Child Elements of the TITLE Element

Element Name	Cardinality / Description
CONNECT	1..n. Only CONNECT elements containing SOURCE elements can be included (one SOURCE per CONNECT). Sources can be server interface properties or, with the NAME attribute set to TEXT, references to strings in a properties file.

## VIEW

The VIEW element is the root element of a UIM document that defines elements to be included in a UIM page document. A view cannot include other views using the INCLUDE element.

### Attributes:

The VIEW element has no attributes.

### Child Elements:

The VIEW element can contain child elements as follows:

Table 51. Child Elements of the VIEW Element

Element Name	Cardinality / Description
PAGE_TITLE	See the PAGE element.
SHORTCUT_TITLE	See the PAGE element.
SERVER_INTERFACE	See the PAGE element.
MENU	See the PAGE element.
ACTION_SET	See the PAGE element.
PAGE_PARAMETER	See the PAGE element.
CONNECT	See the PAGE element.
JSP_SCRIPTLET	See the PAGE element.
CLUSTER	See the PAGE element.
LIST	See the PAGE element.
SCRIPT	See the PAGE element.

## UIM Reference for Widgets

### Introduction

Widgets are used when the handling of data in the client application is too complicated to do with the automatic domain definition recognition of the FIELD element. Widgets allow several different sources of data to be connected to a control that can then supply data to several different targets.

There are a number of predefined types of WIDGET element. Each type of WIDGET can contain one or more WIDGET\_PARAMETER elements. The configuration of these WIDGET\_PARAMETER elements depends on the type of the widget. These are described in the sections below.

Most widget types can only be defined within CLUSTER elements (exceptions to this are described below). There may also be restrictions on how many widgets of a particular type can be included in a single UIM document.

## WIDGET

The WIDGET element is used to define the type of widget to include and it holds the WIDGET\_PARAMETER elements that configure the widget.

### Attributes:

The WIDGET element has the following attributes:

Table 52. Attributes of the WIDGET Element

Attribute Name	Required	Default	Description
TYPE	Yes		The type of WIDGET. This can be one of the following: <ul style="list-style-type: none"><li>• EVIDENCE_COMPARE</li><li>• FILE_EDIT</li><li>• FILE_UPLOAD</li><li>• MULTISELECT</li><li>• SINGLESELECT</li><li>• RULES_SIMULATION_EDITOR</li><li>• FILE_DOWNLOAD</li><li>• IEG_PLAYER</li></ul>
LABEL	No		A reference to an externalized string that should be used as the associated label string for this widget.
WIDTH	No		The width of the control specified in the appropriate units.
WIDTH_UNITS	No	PERCENT	The units in which the width is interpreted. This can be PERCENT to indicate the percentage of the space available to the widget, or CHARS to indicate the number of visible characters wide the widget will be.
HEIGHT	No	1	A HEIGHT value that may be used by the widget.
ALIGNMENT	No	DEFAULT	Defines the horizontal alignment of the widget. Can be set to LEFT, RIGHT, CENTER, or DEFAULT. The value DEFAULT corresponds to the CSS class <i>default</i> in <i>curam_common.css</i> . Currently the default is to be left aligned.
HAS_CONFIRM_PAGE	No	false	Attribute to be used only on widget of type of MULTISELECT. Used to specify that the widget selection data is to be submitted to the confirmation page. Can be true or false. See "Confirmation Pages" on page 122.

### Child Elements:

The WIDGET element can contain the following child element:

Table 53. Child Elements of the WIDGET Element

Element Name	Cardinality / Description
WIDGET_PARAMETER	1..n. The parameters depend on the type of widget.

## WIDGET\_PARAMETER

The WIDGET\_PARAMETER element is used to define the properties of an individual widget. In particular, the WIDGET\_PARAMETER elements allow connections to be made between named properties of the widget and various source and target data end-points.

### Attributes:

The WIDGET\_PARAMETER element has the following attribute:

Table 54. Attributes of the WIDGET\_PARAMETER Element

Attribute Name	Required	Default	Description
NAME	Yes		The name of the property on the WIDGET that this element configures.

### Child Elements:

The WIDGET\_PARAMETER element can contain the following child element:

Table 55. Child Elements of the WIDGET\_PARAMETER Element

Element Name	Cardinality / Description
CONNECT	<p>A WIDGET_PARAMETER can be connected in one of two ways depending on the specification for the particular WIDGET. The first way is similar to that of FIELD elements:</p> <p>1..n. The parameter can contain multiple CONNECT elements. Usually (the FILE_DOWNLOAD WIDGET is an exception to this) a WIDGET_PARAMETER contains up to three CONNECT elements, SOURCE, TARGET, and INITIAL connection end-points. The valid types of source or target depend on the individual parameter.</p> <p>The second way to connect a parameter is similar to the CONNECT elements in a LINK element.</p> <p>1..n. CONNECT elements that each connect a SOURCE end-point to a TARGET end-point.</p>

## The EVIDENCE\_COMPARE Widget

The EVIDENCE\_COMPARE widget displays the differences between two sets of evidence. These differences are high-lighted using the following colors: evidence items that have changed are shown in red; new items are shown in green; deleted items are shown in gray.

This widget should be the sole element in a CLUSTER. Its TYPE should be set to EVIDENCE\_COMPARE and its WIDGET\_PARAMETER elements should be set as follows:

Table 56. Parameters to the EVIDENCE\_COMPARE Widget

Parameter Name	Required	Description and Connections
OLD_EVIDENCE	Yes	<p>This parameter must include a single CONNECT element that must specify a SOURCE end-point.</p> <p>The SOURCE end-point should specify a property of the EVIDENCE_TEXT domain that contains the original evidence.</p>

Table 56. Parameters to the EVIDENCE\_COMPARE Widget (continued)

Parameter Name	Required	Description and Connections
NEW_EVIDENCE	Yes	<p>This parameter must include a single CONNECT element that must specify a SOURCE end-point.</p> <p>The SOURCE end-point should specify a property of the EVIDENCE_TEXT domain that contains the new evidence.</p>

## The FILE\_EDIT Widget

The FILE\_EDIT widget allows a user to edit a Microsoft Word document on their local computer and then save it to the IBM Cúram database. A document can be created automatically from a template where the template details can be set before the document is presented to the user for editing.

The FILE\_EDIT widget uses either a Java applet to manage the interaction between the user's browser and Word (for the browsers which support Java) or the Native Messaging API for Chrome.

In either case only the source and target documents and the template details are required. If key details, or other data, are required by the server interfaces that handle the document, these should be provided by page parameters and page-level connections.

NOTE: the Chrome Native Messaging API solution requires a separate installation/configuration which is detailed in the appropriate documentation. See “User Machine Configuration for the Native Messaging version” on page 115

Once the page with the FILE\_EDIT widget loads, it immediately launches the File Edit Control Panel in the modal dialog. This panel displays the informational messages about the editing session initialization and other background events as well as error messages if there are any. It does also allow for some minimal interaction with the application server.

The Control panel modal dialog can be closed up to the point that the Microsoft Word application initializes correctly and the document opens. Thereafter, the close option is not available because closing the Word application will end the process.

Once the document loads and is ready for editing, it is automatically saved locally and displays along with the corresponding notification in the Word status bar and also the Windows task bar (if so configured, see the “FILE\_EDIT Widget Configuration” on page 112). The user can now edit the document and save it as they wish.

Each document Save operation within the Word application triggers the notification message in the application status bar and from the Windows task bar to notify the user that their changes are saved locally but not to the database. In order to save the interim versions of their document back to the database the user has the possibility to go back to the browser where there is the Commit changes button in the File Edit Control Panel. The button is initially disabled. It will be enabled once the document is saved in the Word application. Once the user presses this button, the current document version is passed back to the server and saved to the



database. The user is notified of the result of this interim save in the panel and the Commit changes button is disabled again until the next Save operation in Word.

Because of the specific invocation of the server interfaces by the FILE\_EDIT widget, it is not permitted to use any property of the ACTION phase server interface in a SOURCE connection of the submit button's LINK element.

After the user finishes editing the document, they finish the editing session by closing either the document being edited (if there are multiple documents open) or the Word application itself. At this stage the application in the browser displays the final save confirmation dialog asking if the user wants to save their final changes to the server or discard them.

NOTE: The dialog is only displayed if it has been configured, see "FILE\_EDIT Widget Configuration" on page 112.

Please note, that if there were interim saves as above described, the database will contain the latest committed copy of the document even if the user chooses Cancel at this stage. However it is also possible to discard all the changes altogether if there were no interim changes and the user decides not to save them.

Once the final save(or cancel) is performed, the application transfers the user to the page that it has been configured to go to as specified by the ACTION\_CONTROL of TYPE="SUBMIT" in the UIM page containing the FILE\_EDIT widget. If there is no page specified, this "landing" page is assumed to be the last visited page.

There are circumstances where this "landing" page is not available. In this case the application performs a search to identify which page should be opened first based on configuration. Once a page is identified, it is used as the landing page, potentially changing the tab if necessary.

The FILE\_EDIT widget can be used as follows: the WIDGET element should have the TYPE attribute set to FILE\_EDIT. Two WIDGET\_PARAMETER elements are required:

*Table 57. Parameters to the FILE\_EDIT Widget*

Parameter Name	Required	Description and Connections
DOCUMENT	Yes	<p>Defines the source document (usually a template) and the target to which to write the saved document. The parameter must contain a CONNECT element with a SOURCE set from a DISPLAY phase sever interface and a TARGET set from an ACTION phase sever interface. Both fields should be Word documents.</p> <p>The data-type for both the source and target document must be SVR_BLOB.</p>

Table 57. Parameters to the FILE\_EDIT Widget (continued)

Parameter Name	Required	Description and Connections
DETAILS	Yes	<p>The template details that should be set in the document before presenting it to the user for editing. The parameter must contain a CONNECT element with a SOURCE set from a DISPLAY phase sever interface. The details are in XML format, described below.</p> <p>The data-type for the template details must be SVR_BLOB.</p>

The template details must be provided in a simple XML format. An example of the format is shown below:

```
<?xml version="1.0" encoding="UTF-8"?>
<FIELDS>
  <FIELD NAME="personName" VALUE="John Smith"/>
  <FIELD NAME="AddressLine1" VALUE="1 Main Street"/>
  <FIELD NAME="AddressLine2" VALUE="Newtown"/>
  <FIELD NAME="AddressLine3" VALUE="Erehwon"/>
</FIELDS>
```

Figure 46. Sample Template Details

It is recommended that your XML uses UTF-8 encoding to handle multi-byte characters. To preserve the correct encoding it is important that any code that manipulates the XML honors the encoding of the document. If the encoding is not honored, this can lead to characters being displayed incorrectly when opened in Microsoft Word.

Each FIELD element identifies the name of a field in the document template and the value to which it should be set.

While editing the document in Word, the user can not navigate to another browser page (which the modal File Edit Control Panel and absence of the closing button there would prevent) or close the browser. If the user attempts to close the originating browser window in the middle of the editing session, the browser warning is displayed notifying the user of the consequences.

If the user chooses to remain on the page, they can proceed with the editing or end the session by closing Word application/the document being edited. If, however, they choose to leave the page, the editing session will be terminated, and the document or Word application (if it was the only document open) closes along with the browser; the user changes are not saved in this case, however any saved interim changes before this termination happens are persisted in the database.

#### **FILE\_EDIT Widget Configuration:**

There are some configuration settings which allow for the bigger flexibility as regards the widget usage or the widget solution itself. They are summarized in the table below.

Table 58. FILE\_EDIT Widget Configuration settings summary

Setting Name	Location (.properties file)	Required	Default value	Description
fileedit.chrome.messagingApplicationConfiguration	ApplicationConfiguration	Yes	false	<p>Allows for using the Native Messaging API for Chrome browser (starting from Chrome 29 which introduces this technology). In order to use the solution the user's machine should have the Native Messaging solution parts installed and configured as described in the appropriate documentation. See "User Machine Configuration for the Native Messaging version" on page 115</p> <p>If this is set to false, which is the default value, the applet based solution will be used for any browser including Chrome which should work as long as Java is supported by the Chrome version used.</p> <p>Note that there could be further restrictions imposed by Chrome in order to enable and use the Java plug-in which they intend to drop soon; these restrictions are beyond IBM control and the user should take the necessary measures to have the supported JRE and browser plug-in installed and properly enabled as described in the "User Machine Configuration for the Applet version" on page 114.</p>
fileedit.save.autoconfirm	CDEJResources	No	-	<p>Can be set to either true or false if added and replaces the final save confirmation dialog with the predefined action for either saving the latest changes automatically or discarding them if set to true or false correspondingly. The confirmation dialog is not displayed in this situation.</p>

Table 58. FILE\_EDIT Widget Configuration settings summary (continued)

Setting Name	Location (.properties file)	Required	Default value	Description
fileedit.taskbar.messages	CDEJResources	No	-	Can be set to either true or false values; prevents from the Word status messages being duplicated by the Window task bar notification messages. If set to false, no task bar notification will be displayed, while setting it to true or not having that property in CDEJResources.properties at all would cause the task bar notification messages to be displayed.  Please keep in mind that suppressing the additional task bar notification could affect the accessibility of the FILE_EDIT widget.
fileedit.log.on	CDEJResources	Yes	false	Can be set to either true or false values; when set to true, it causes the log (service) messages to be displayed in the File Edit Control panel dialog in addition to the regular status messages.  These log messages do not have value to the end user and therefore are not translated (display in English). Turning on the logging should not normally be needed but might be useful when reporting or tracing the problems with the widget.

#### User Machine Configuration for the Applet version:

The applet version of the FILE\_EDIT widget is used for the browsers which support the Java plug-in. Google announced dropping the Java plug-in support for Chrome browser. While the applet based solution will work in this until the plug-in is working (if properly allowed to run and the application is configured accordingly, see “FILE\_EDIT Widget Configuration” on page 112), this is expected to be just a temporary situation and therefore the Native Messaging Bridge version of the FILE\_EDIT widget is generally recommended to be used in Chrome, see “User Machine Configuration for the Native Messaging version” on page 115.

On first use of a new version of the integration applet the user will be presented with a pop up dialog window to confirm if the code from publisher “International Business Machines Corporation” should be allowed to run. The checkbox “Always trust the content from this publisher” should be selected and dialog confirmed, which will ensure the widget executes successfully and the prompt is not

displayed again on subsequent uses. New versions of the widget will be downloaded to the user's machine automatically when the Cúram application is upgraded to a new version.

When a user attempts to edit a Word document, execution of the integration applet may be blocked depending on security settings of the Java browser plugin on that particular machine. This causes the editing session to fail. If you experience these kind of issues, please check the following:

- Microsoft Word (supported version) should be installed on the user's machine.
- Word installation should be working as expected on the user's machine when started manually.
- The Web browser Popup blocker feature on the user's machine should be disabled.
- For supported browsers other than Internet Explorer if you are getting a message about the missing Java plugin even though it is installed on the machine, verify the following option is enabled: Control Panel -> Java -> Advanced -> Default Java for browsers-> Mozilla family
- Generally if you are getting message about the missing Java plugin even though it is installed on the machine, check if a slide-down message is displayed in the small popup window that opens when you attempt to edit a Word document. If so, then confirm that you want to always run code from this publisher and reload the application in the browser.

Note to users of Windows 7 or higher: Word integration is currently only supported for non-Administrator users. You may experience issues if the user is logged into Windows as Administrator or if Internet Explorer is started in administration mode.

Please also note that Chrome browser requires the opposite: it should be launched with Administrator privileges for the FILE\_EDIT applet to initialize successfully. This is only required when running Word integration in Chrome for the first time.

If you are using this feature in an environment supporting the TLS v1.2 protocol you will need to utilize an operating system, browser, and JDK environment with compatible support for the client, in conjunction with the application being hosted on a compliant server (e.g. WebSphere configured for SP800-131a). The specific steps for configuring the client environment are dependent on the operating system, browser, and JDK you are using, but all must support TLS v1.2. Assuming a TLS v1.2-configured server environment and all the required software that supports TLS v1.2 is installed on the client, you must configure the browser to use the appropriate JDK and to utilize the TLS v1.2 protocol.

Additional security dialog pops up on the first run of the applet asking user's permission for the website to access and control the Java application published by the "International Business Machines Corporation". The check box "Do not show this again for this app and web site" should be selected and the permission confirmed by clicking the "Allow" button in the dialog.

#### **User Machine Configuration for the Native Messaging version:**

When running the Word Integration in Chrome, a different underlying technology is used (if configured, see "FILE\_EDIT Widget Configuration" on page 112), therefore the user should not be presented by any additional dialogs.

However the Native Messaging technology used requires additional installation on the users machine which should normally be handled by the system administrator.

If these installations are missing the user will be notified in the File Edit Control Panel and could return to the application from there. If the required additions are installed but the Word application is missing on the machine, the user will also be notified.

Otherwise using the FILE\_EDIT widget in Chrome should not be different.

### The FILE\_UPLOAD Widget

The FILE\_UPLOAD widget is a type of widget through which users can specify a file on a local computer to be uploaded to the server. Usually, the widget is displayed as a text field with a **Browse** button beside it. The user can click the button to open a file dialog box and select a file for upload.

**Button appearance:** The button is created by the browser. Therefore, the actual appearance of the button can vary depending on the browser that is being used. The normal widget attributes WIDTH and WIDTH\_UNITS do not apply to the FILE\_UPLOAD widget. Some browsers do not permit the width of the file name entry box to be set for security reasons. For example, if the width is set to zero width, the file name entry box could be hidden while it was still active.

Also, because the FILE\_UPLOAD widget uses browser-specified controls, the text on the button is displayed in whatever locale the browser is set to, regardless of the locale that is configured in the application.

**File Size Validation:** There are settings to limit the maximum size of a file that is allowed to be uploaded. The validations for these settings are carried out on the server side after the file is fully uploaded to a temporary directory. Therefore, it should be kept in mind that large files could be uploaded consuming a large amount of disk space. We recommend checking the file upload folder at intervals to ensure disk space usage meets requirements.

There are three application-level configuration settings for the FILE\_UPLOAD widget. These control how the web-server handles the incoming files. Default settings are already present, but the default values can be overridden by adding configuration settings to the ApplicationConfiguration.properties file. The settings follow the same *name = value* format of all the other entries there. The settings are as follows:

#### uploadMaximumSize

This is the maximum size of a file that can be uploaded to the server. The number is specified in bytes. If the number is negative, there is no limit to the file size. By default, the value is -1 (no limit).

#### uploadThresholdSize

This is maximum number of bytes of the file's content that the web-server will hold in memory while the file is being uploaded. Once the number of bytes uploaded exceeds this limit, the web-server will begin to store the file on disk to save memory. By default, the value is 1024.

#### uploadRepositoryPath

This is the path to the folder on the disk in which the files will be stored as they are uploaded if they exceed the threshold size. By default, the value is the JVM defined temp folder, so this folder must be present on your system. If it is not on your system, you can create it or explicitly set the uploadRepositoryPath to a folder of your choice.

The WIDGET element should have the TYPE attribute set to FILE\_UPLOAD. The widget supports the following WIDGET\_PARAMETER elements:

Table 59. Parameters to the FILE\_UPLOAD Widget

Parameter Name	Required	Description and Connections
CONTENT	Yes	<p>This parameter indicates the target connection for the actual content of the uploaded file.</p> <p>A single CONNECT element with a TARGET that connects to a property of an ACTION phase server interface is required.</p>
FILE_NAME	No	<p>This parameter represents the name of the file to be uploaded. The parameter can be set to provide a default name for the file to be uploaded, and can also supply the name of the file chosen by the user.</p> <p>If present, the parameter can include CONNECT elements for either or both end-points: a SOURCE end-point for the initial name of the file, and a TARGET end-point for the file that was actually chosen. The SOURCE end-point can specify a property of a DISPLAY phase server interface. The TARGET end-point can specify a property of an ACTION phase server interface.</p> <p><i>Note: Many browsers do not allow a default value for the name of a file to be uploaded. In this case, setting a SOURCE connection will have no effect.</i></p>
CONTENT_TYPE	No	<p>This parameter indicates the target connection for the content type of the uploaded file. The content type describes the format of the uploaded data. For example, a simple text file would have a content type of “text/plain” and a Microsoft Word document would have a content type of “application/msword”.</p> <p>A single CONNECT element with a TARGET that connects to a property of an ACTION phase server interface is required.</p>
ACCEPTABLE_CONTENT_TYPES	No	<p>A HTML page only allows certain types of content to be uploaded by default (the actual default types are dependent on the browser). This parameter can specify the types of content that the page will accept. The value of the parameter should be a comma-separated list of content types. If there is more than one FILE_UPLOAD widget on a page, the acceptable content types of all widgets are pooled together and define what is acceptable for that page (this is a limitation of the HTML specification.)</p> <p>A single CONNECT element with a SOURCE that connects to a TEXT property is allowed.</p>

### File Upload Widget Considerations:

File Upload Considerations in Chrome.

In Chrome, if the file upload widget is used adjacent to another field, once selected, the longer file name once selected might overlap with the label of that other field. To avoid this issue, do not have a file upload adjacent to another field, or allow for enough space in between the fields.

## The FILE\_DOWNLOAD Widget

A WIDGET with the TYPE set to FILE\_DOWNLOAD results in the generation of a hyperlink on the page. Clicking on the hyperlink invokes a special FileDownload servlet included in the Cúram CDEJ that returns the contents of a file from the database. The FileDownload servlet is configured with the server interface to call to get the file contents and the parameters to pass to identify that file. The configuration is performed in the curam-config.xml file. A single server interface can be configured for each page of the application that includes a file download widget. An example configuration is shown in “File Downloads” on page 56.

An ACTION\_CONTROL with the TYPE set to FILE\_DOWNLOAD can also be used to generate a hyperlink to download a file. You should use the ACTION\_CONTROL element when the hyperlink text is a fixed value retrieved from the page's corresponding properties file. The FILE\_DOWNLOAD WIDGET allows the hyperlink text to be a dynamic value retrieved from a server interface property.

The FILE\_DOWNLOAD widget can also be utilized within the Actions menu of the Context Panel. The menu item TYPE must be set to FILE\_DOWNLOAD. The menu item PAGE-ID must match the PAGE\_ID attribute of the FILE\_DOWNLOAD widget configuration. The file identifier must be available as a page parameter in the respective.tab file for the menu. This page parameter must match the PAGE\_PARAM attribute of the FILE\_DOWNLOAD widget configuration.

The WIDGET element should have the TYPE attribute set to FILE\_DOWNLOAD. The widget supports the following WIDGET\_PARAMETER elements:

*Table 60. Parameters to the FILE\_DOWNLOAD Widget*

Parameter Name	Required	Description and Connections
LINK_TEXT	Yes	<p>This parameter indicates the source connection for sourcing content of the link text which will appear on the screen.</p> <p>A single CONNECT element with a SOURCE that connects to a property of a DISPLAY phase server interface is required. If you want to use a fixed text value, you should use an ACTION_CONTROL with the TYPE set to FILE_DOWNLOAD instead of a WIDGET.</p>



Table 60. Parameters to the FILE\_DOWNLOAD Widget (continued)

Parameter Name	Required	Description and Connections
PARAMS	No	<p>This optional parameter supplies the FileDownload servlet with the necessary parameters.</p> <p>The parameter can include CONNECT elements with a SOURCE end-point for the page parameter supplying a value for the FileDownload servlet, and a TARGET end-point for specifying the servlet parameter to supply the value to. The SOURCE end-point should refer to a parameter on the page declared by a corresponding PAGE_PARAMETER element. The TARGET end-point can specify a parameter whose name corresponds to a configured FileDownload servlet parameter name. Thus both end-points should have a NAME attribute set to PAGE.</p>

## The MULTISELECT Widget

The MULTISELECT widget allows you to specify that the first column in a LIST should contain a check-box on each row and to allow several rows to be selected. A “Select All” feature can be enabled which displays a check-box in the column header. See “ENABLE\_SELECT\_ALL\_CHECKBOX” on page 39 for further details.

Each check box can represents multiple entities in the row. For each check box that is selected, the fields on that row will be compiled into a “ | ” delimited string and each row will be tab delimited and passed as a page parameter when a specific type of page link is activated.

The UIM document in “The MULTISELECT Widget” is an example of a page with multiple rows with check boxes. When the form is submitted, a single string, containing multiple fields for each selected row, is passed to the *in\$tabbedString* field on the target page. Following the UIM is a detailed description of each relevant part of the UIM that implement this functionality.

```

        <PAGE PAGE_ID="MultiSelectWidgetTest"
        xsi:noNamespaceSchemaLocation="CuramUIMSchema"
        xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">

<SERVER_INTERFACE NAME="DISPLAY" CLASS="MyBean"
        OPERATION="Display" PHASE="DISPLAY"/>
<SERVER_INTERFACE NAME="ACTION" CLASS="MyBean"
        OPERATION="Submit" PHASE="ACTION"/>

<LIST TITLE="List.Title">
    <ACTION_SET BOTTOM="false">
        <ACTION_CONTROL TYPE="SUBMIT">
            <LINK_PAGE_ID="MultiSelectWidgetResult">
                <CONNECT>
                    <SOURCE NAME="ACTION"
                        PROPERTY="in$tabbedString"/>
                    <TARGET NAME="PAGE"
                        PROPERTY="referenceNumTabString"/>
                </CONNECT>
            </LINK>
        </ACTION_CONTROL>
    </ACTION_SET>
    <CONTAINER LABEL="List.Multiselect.Header" WIDTH="5"
        ALIGNMENT="CENTER">
        <WIDGET TYPE="MULTISELECT"
            HAS_CONFIRM_PAGE="true">
            <WIDGET_PARAMETER NAME="MULTI_SELECT_SOURCE">
                <CONNECT>
                    <SOURCE PROPERTY="personID" NAME="DISPLAY"/>
                </CONNECT>
                <CONNECT>
                    <SOURCE PROPERTY="caseID" NAME="DISPLAY"/>
                </CONNECT>
            </WIDGET_PARAMETER>
            <WIDGET_PARAMETER NAME="MULTI_SELECT_TARGET">
                <CONNECT>
                    <TARGET PROPERTY="in$tabbedString" NAME="ACTION"/>
                </CONNECT>
            </WIDGET_PARAMETER>
            <WIDGET_PARAMETER NAME="MULTI_SELECT_INITIAL">
                <CONNECT>
                    <SOURCE NAME="DISPLAY" PROPERTY="out$tabString"/>
                </CONNECT>
            </WIDGET_PARAMETER>
        </WIDGET>
    </CONTAINER>
    <FIELD LABEL="Field.Title.ReferenceNumber" WIDTH="35">
        <CONNECT>
            <SOURCE NAME="DISPLAY" PROPERTY="personID"/>
        </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Title.Forename" WIDTH="30">
        <CONNECT>
            <SOURCE NAME="DISPLAY" PROPERTY="firstName"/>
        </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Title.Surname" WIDTH="30">
        <CONNECT>
            <SOURCE NAME="DISPLAY" PROPERTY="surname"/>
        </CONNECT>
    </FIELD>
</LIST>
</PAGE>

```

Figure 47. MULTISELECT Example

The main points to note in the above UIM example are:

- The WIDGET of TYPE equal to MULTISELECT is a child node of a CONTAINER element. The container's label will be used as the column header unless the select all check box is enabled in curam-config.xml. See "ENABLE\_SELECT\_ALL\_CHECKBOX" on page 39 for further details.
- Up to three WIDGET\_PARAMETER elements are allowed within the WIDGET element. MULTI\_SELECT\_SOURCE and MULTI\_SELECT\_TARGET are mandatory and MULTI\_SELECT\_INITIAL is optional.
- The MULTI\_SELECT\_SOURCE can have multiple CONNECT elements, each with one SOURCE element. Each SOURCE is added to the " | " delimited string. If only one SOURCE element is specified the string will not contain any " | " delimiters. Then each select row will be delimited by a tab character.
- The MULTI\_SELECT\_TARGET element must contain only one CONNECT element with only one TARGET element. This TARGET element specifies the field on the action phase bean that the " | " and tab-delimited string will be assigned to when the page is submitted.
- The MULTI\_SELECT\_INITIAL contains only one CONNECT element with a single SOURCE element. This contains a " | " and tab-delimited string which specifies the rows that are selected when the page is loaded.
- In the LIST element the ACTION\_SET has one ACTION\_CONTROL element.
- Optional HAS\_CONFIRM\_PAGE attribute is used to indicate that the page with MULTISELECT widget submits to a confirmation page, where user selection is re-displayed for confirmation. See "Confirmation Pages" on page 122

Below is an example of the delimited string passed as a parameter to the specified page.

101|case121    102|case122    103|case123

NOTE: The MULTISELECT widget does not support the list pagination feature and all it's items will be displayed within one scrollable list. See "PAGINATION" on page 40 and "LIST" on page 89 for more details on pagination support.

*Table 61. Parameters to the MULTISELECT Widget*

Parameter Name	Required	Description and Connections
MULTI_SELECT_SOURCE	Yes	<p>This parameter can include multiple CONNECT elements that must specify a SOURCE end-point.</p> <p>The SOURCE end-point must be a list property containing the key data for the row.</p>
MULTI_SELECT_TARGET	Yes	<p>This parameter must include one CONNECT element that must specify a TARGET end-point.</p> <p>The TARGET end-point must be a string property containing the key data for selected rows.</p>

Table 61. Parameters to the MULTISELECT Widget (continued)

Parameter Name	Required	Description and Connections
MULTI_SELECT_INITIAL	No	<p>This parameter must include one CONNECT element that must specify a SOURCE end-point.</p> <p>The SOURCE end-point must be a string property containing the key data for the rows that are initially check when page is loaded.</p>

### Confirmation Pages:

MULTISELECT widget has a specific mechanism allowing for confirming user selection on a separate page. This confirmation page is supposed to re-display values selected by an user on the MULTISELECT widget offering a choice to review these values and confirm them or re-visit the previous page to refine the selection.

Confirming user selection can become a problem where there is a lot of selected values from a big MULTISELECT widget to be passed to the confirmation page. There are request length limitations in place, so in order to pass bigger amounts of data possible in this case different request mechanism (request forwarding) has to be used.

MULTISELECT widget with the selection to be confirmed is specified by HAS\_CONFIRM\_PAGE optional attribute on the WIDGET element. The attribute is to be set to true. It is only valid for a widget of TYPE of MULTISELECT.

Some things to keep in mind with confirmation pages:

- As request forwarding is used to carry the data in this case, the URL for the confirmation page will not be displayed with the forwarding page URL shown instead.
- Even though the mentioned attribute is set on a MULTISELECT widget, the setting applies to the whole page (as there is only one form per page). So, in case where multiple submit buttons exist on a page with MULTISELECT widget to be confirmed, a confirmation step should be assumed for all of these buttons (i.e., there is no way to have a submit with confirmation and another without confirmation on that page).
- The confirmation is to be the immediate step carried out on submitting the form with user selection; no resolve page should be used in the middle.
- It is recommended to have a read-only page for user selection confirmation, allowing user to cancel and return to the previous page if the selection is to be refined.

### The SINGLESELECT Widget

The SINGLESELECT widget allows you to specify that the first column in a LIST should contain a radio button on each row. This widget functions in same way as the MULTISELECT widget, except you are limited to selecting a single item via radio buttons instead of check boxes. See “The MULTISELECT Widget” on page 119 for further details.

NOTE: The SINGLESELECT widget does not support the list pagination feature and all its items will be displayed within one scrollable list. See “PAGINATION” on page 40 and “LIST” on page 89 for more details on pagination support.

*Table 62. Parameters to the SINGLESELECT Widget*

Parameter Name	Required	Description and Connections
SELECT_SOURCE	Yes	This parameter must include multiple CONNECT elements that must specify a SOURCE end-point.  The SOURCE end-point must be a list property containing the key data for the rows to be displayed.
SELECT_TARGET	Yes	This parameter must include one CONNECT element that must specify a TARGET end-point.  The TARGET end-point must be a string property containing the key data for selected row.
SELECT_INITIAL	No	This parameter must include one CONNECT element that must specify a SOURCE end-point.  The SOURCE end-point must be a string property containing the key data for the row that is initially checked when page is loaded.

### **The RULES\_SIMULATION\_EDITOR Widget**

The RULES\_SIMULATION\_EDITOR widget is used to edit or create data used when simulating the execution of a rule-set. The widget generates clusters of fields that correspond to the fields of Rules Data Objects (RDO). A normal cluster is used to display the fields of a basic RDO and a multi-column cluster is used for a list RDO. A standard list is not used, as a list RDO with many fields would result in a list that had too many columns to be displayed on the screen.

The user can enter or modify values on the page corresponding to the RDO fields and, for list RDO s displayed in a multi-column cluster, press a button to create additional columns for field values.

The WIDGET element should have the TYPE attribute set to RULES\_SIMULATION\_EDITOR. The parameters to the widget are as follows:

Table 63. Parameters to the RULES\_SIMULATION\_EDITOR Widget

Parameter Name	Required	Description and Connections
VALUES	Yes	<p>The simulation data values. A previous set of values can be displayed and edited or a new set of values can be created.</p> <p>The parameter should contain a CONNECT element with a SOURCE set to a DISPLAY phase bean field containing the values and a TARGET set to an ACTION phase bean field that will receive the edited values. If the SOURCE has no values set, the editor will create them.</p>
META_DATA	Yes	<p>The simulation meta-data. The meta-data contains details about the structure of the RDO s necessary to generated the input fields.</p> <p>The parameter should contain a CONNECT element with a SOURCE set to a DISPLAY phase bean field containing the meta-data.</p>
ADD_BUTTON_CAPTION	Yes	<p>The caption to use on the button displayed at the bottom of each multi-column cluster and used to add a new column of extra data to a list RDO. If an image is also specified, this caption is used as the "alt" text of the image.</p> <p>The parameter should contain a CONNECT element with a SOURCE that gets a localized string from a TEXT source.</p>
ADD_BUTTON_IMAGE	No	<p>The path to the image file to use if an image button is to be used in place of a standard button. The path is relative to the WebContent folder.</p> <p>The parameter should contain a CONNECT element with a SOURCE that gets a localized string from a TEXT source.</p>

The widget should be placed in a CLUSTER element. The clusters for the RDO s will be rendered within that cluster. The SHOW\_LABELS attribute should be set to false. The LABEL\_WIDTH attribute of the CLUSTER element will be inherited by the clusters that are generated by the widget, so it can be used to control the layout. An ACTION\_CONTROL element in the cluster or on the page should be added to save and process the simulation data created by the widget in the usual manner.

When a widget is not supplied with any simulation data values, it will display empty fields. For list RDO s, a single empty column of fields will be displayed; values can be entered and more columns added as needed. If values are supplied,

they will be displayed. In a multi-column cluster, pressing the defined “add” button will add a single empty column to the right of any existing columns. All other empty columns will be removed at this time, so deleting the values in one or more columns has the effect of removing those columns from the multi-column cluster.

### **The IEG\_PLAYER Widget**

Consult the *Cúram Intelligent Evidence Gathering (IEG)* guide for details.

## **Dynamic UIM Cross Reference**

Dynamic UIM as its name implies, is UIM that is cached in the resource store - rather than static UIM (described in earlier sections) which resides on the file system - so that the server and client do not have to be rebuilt in order for a page to be displayed in an application. All string values in dynamic UIM documents must be externalized in properties files, which must also be cached in the resource store.

When creating a dynamic UIM document, only the PAGE element is a valid root element. All the UIM features (elements and attributes) referenced in “UIM Reference for Pages and Views” on page 54 are supported for dynamic UIM, except for those which are listed in “Unsupported Features in Dynamic UIM” on page 304.

Refer to “Maintaining Dynamic UIM Pages” on page 300 on details about how to maintain dynamic UIM pages in the Resource Store.

## **Dynamic UIM System Initialization**

There are two ways in which the Dynamic UIM system can be initialized; when the application is started, or the first time that there is a request for a Dynamic UIM page in the running application. By default the Dynamic UIM system is initialized when the application is started. In order to override the default initialization of the Dynamic UIM system - so that it is initialized when a Dynamic UIM page is first requested - a configuration setting can be added to the `ApplicationConfiguration.properties` file. This setting follows the same *name = value* format of all the other entries there. It should be set as follows:

### **dynamicUIMInitModelOnStart**

This value should be set to false in order to override the default setting.

If a developer intends to access dynamic UIM pages in the application, then the default initialization of the dynamic UIM system must be used. Otherwise, if the developer is not using dynamic UIM pages and finds their Tomcat start-up time is too slow, the default initialization of the dynamic UIM should be overridden, as described above.

---

## **Application Configuration**

An application in the Cúram user interface is a collection of user interface elements, based on UIM pages, that are combined to create specific content for a particular user or role. Develop Cúram web client applications by configuring application configuration files.

An application comprises of an application banner and one or more application sections. Each section, contains an optional section shortcut panel and one or more tabs. A tab represents a business object or logical grouping of information. In the

following figure, the features of an application user interface are numbered and are cross-referenced by subsequent topics in the section. Subsequent topics outline how to develop an application by using the relevant XML configuration files.




Figure 48. Application User Interface Overview

#### Related concepts:

“Cúram applications” on page 7

When a user logs into the Cúram application they are presented with a view that is specific to their role, which an application. An application in the Cúram user interface is a collection of user interface elements, mainly based on UIM pages, combined to create specific content for a particular user or role.

“Application user interface overview” on page 4

The application user interface contains elements that are implemented through user interface metadata. Other topics in the section describe how each of the user interface elements can be configured in an application.

#### Related reference:

“UIM Reference” on page 52

Learn about the Cúram User Interface Meta-data (UIM) format used to specify the contents of the Cúram web application client pages.

## Configuration files

Configure applications, sections, tabs and related elements in XML-based configuration files.



The configuration files are in the <server-dir>\components\<component-name>\clientapps directory. See “Application Configuration Files” on page 34 for more information about the clientapps directory, and best practices for working with application configuration files.

Each configuration file has a specific extension and an associated schema file detailing the supported attributes. The following table provides a summary of the file extensions and related schema files.

*Table 64. Configuration Files*

File Extension	Schema File	Description
.app	application-view.xsd	Configuration file to define an application, including the application banner, referenced sections and application search.
.sec	section.xsd	Configuration file to define the referenced tabs and section shortcut panel in a section.
.ssp	section-shortcut-panel.xsd	Configuration file to define the contents of a section shortcut panel.
.tab	tab.xsd	Configuration file to define a tab, including the context panel and referenced navigation and actions menu.
.nav	navigation.xsd	Configuration file to define the content of a tab navigation bar.
.mnu	menubar.xsd	Configuration file to define the content of a tab actions menu.

The schema files are all located in the <sdej-dir>\lib directory and can be used during development for validation in any XML editor.

The configuration files for applications, sections and tabs are processed as part of the **database** target and stored on the database for use at runtime. A standalone target, **inserttabconfiguration**, is also available for processing the configuration files only. This command is useful during development because it is more efficient than the full database target. For more information on these targets please consult the *Cúram Server Developers Guide*.

The **inserttabconfiguration** validates all the configuration files, ensuring that they conform to the XML schema, in addition to ensuring that all mandatory elements and attributes are specified. All files are processed before the build fails, listing all validation errors.

## Web client properties

Configure the title that is displayed in the browser tab in the CDEJResources.properties file. The CDEJResources.properties file contains values for properties that are used throughout the web client.

The core file is located in %CURAM\_DIR%\CuramCDEJ\doc\defaultproperties\curam\omega3\i18n. %CURAM\_DIR% is the Cúram installation directory, which by default is C:\IBM\Curam\Development.

This properties file can be localized as per Locales. Images defined in this file can also be customized per locale.

## Customizing the CDEJResources.properties file

To customize the CDEJResources.properties file, use the procedure that is outlined in the following task.

### Procedure

1. Create a custom copy in the custom component, for example, webclient\components\custom.
2. Include only the properties that are being overridden.

## Configuring the browser title

To customize the browser title, configure the properties that are outlined in the following task.

### Procedure

Add the properties from the following list to the custom CDEJResources.Properties file:

#### **browser.tab.title**

Defines the application name that is used in the browser tab title.

#### **browser.tab.title.separator**

Defines the text that is used to separate the page title and application name strings.

#### **browser.tab.title.application.name.first**

Controls whether the browser tab title displays the application name before the current page title.

## Applications

An application is a particular view of the Cúram client defined for a specific user or role. The application definition file details the application banner and a reference to the sections that are part of the application.

An application banner provides the user with the context of the application they are currently accessing. The banner contains the following elements:

- The name of the application. Refer to User Interface Element 1.1 in “Application Configuration” on page 125 to see an example of an application name configured in the User Interface.
- The role of the user that this application is intended for.
- A welcome message for the user. Refer to User Interface Element 1.2 in “Application Configuration” on page 125 to see an example of a welcome message configured in the User Interface.
- An application menu, which includes links to the User Preferences dialog, application help, the about box, and to logout of the application. Refer to User Interface Element 1.3 in “Application Configuration” on page 125 to see an example of an application menu configured in the User Interface.
- A configurable application logo, which defaults to the IBM logo, placed at the far right of the application banner. It can be customized or removed.
- A quick search facility for the application. Refer to User Interface Element 1.4 in “Application Configuration” on page 125 to see an example of an application search configured in the User Interface.

The application search is an optional addition to the application banner which provides a quick search facility. The application search supports:

- A text entry field where the user can enter their search criteria.
- An optional search type combo box, which lists the types of object which can be searched on.
- A search button to trigger the actual search.
- An optional link to more search options.

Refer to User Interface Element 1.4 in “Application Configuration” on page 125 to see an example of a fully configured application search in the User Interface. This example has both the optional search type combo box, and optional link with more search options enabled

## Application definition

An application is defined by creating an XML file with the extension .app in the clientapps directory.

The root XML element in the .app file is the application element and the attributes allowed on this element are defined in the following table. The application banner is configured by using these attributes.

Table 65. Attributes of the application Element

Attribute	Description
id	<p><i>Mandatory.</i></p> <p>The unique identifier for the application, which must match the name of the file. This id matches to an APPLICATION_CODE entry and is used to determine the application to display for a particular user.</p> <p>See “Associate an application with a user” on page 138 for more information.</p>
title	<p><i>Optional.</i></p> <p>The text for the title that will be displayed as part of the application banner. The attribute must reference an entry in the associated properties file.</p>
sub-title	<p><i>Optional.</i></p> <p>The text for the subtitle that will be displayed as part of the application banner. The attribute must reference an entry in the associated properties file.</p>
user-message	<p><i>Optional.</i></p> <p>The text for the welcome message that will be displayed as part of the application banner. The attribute must reference an entry in the associated properties file.</p> <p>The text can contain a placeholder, %user-full-name, which will be replaced with the users full name. The full name is determined based on the FirstName and Surname fields on the Users database table.</p>
hide-tab-container	<p><i>Optional.</i></p> <p>When set to true, this indicates that there is only one section in the application and the section tab should not be displayed. The default is false.</p>

Table 65. Attributes of the application Element (continued)

Attribute	Description
header-type	<p><i>Optional.</i></p> <p>This indicates that an additional header is to be used and what type of content will be provided. The values supported are static and dynamic.</p> <p>See “Application optional header” on page 136 for more information.</p>
header-source	<p><i>Optional.</i></p> <p>A reference to the source that will be used as an additional header. The value of this depends on the value of header-type. For static content, the attribute should reference a filename of a file in the resource store. For dynamic content, the attribute should reference a custom widget.</p> <p>See “Application optional header” on page 136 for more information.</p>
logo	<p><i>Optional.</i></p> <p>A reference to the path of an image, e.g. CDEJ/themes/v6/images/large-application-logo.png or an image name, e.g. large-application-logo.png, where the named image is stored in the application resource store. This is used to configure a custom application logo displayed at the far right of the application banner. The custom application logo will only be displayed when the attribute logo-required is set to true, otherwise this setting is ignored.</p> <p>Note: Only images with the same height as the default IBM logo (26 pixels in the internal application and 61 pixels in the external application) are supported.</p>
logo-alt-text	<p><i>Optional.</i></p> <p>The alternative text for the custom application logo specified by the attribute logo. It is only used when the custom application logo is displayed on the application banner. Otherwise, the setting for this attribute is ignored.</p>
logo-required	<p><i>Optional.</i></p> <p>When not set, a default IBM logo is displayed on the application banner. When set to true, in conjunction with the logo attribute, the referenced custom application logo is displayed. When set to false, the application logo is not displayed on the application banner.</p>

The application element supports the child elements detailed in “Application definition” on page 129.

Table 66. Supported Child Elements of the application Element

Element	Description
section-ref	<p>1..n.</p> <p>The application must contain a minimum of one section-ref element. Each section-ref element references a section to be included in the application. See “Application section-ref element” on page 134 for more information.</p>
application-menu	<p>Optional.</p> <p>Allows for the optional addition of links to the application banner. The links supported include the user preferences editor, application logout and help. See “Application application-menu element” for more information.</p>
application-search	<p>Optional.</p> <p>Allows for the optional addition of a quick search facility on the application banner. See “Application application-search element” on page 132 for more information.</p>
timeout-warning	<p>Optional.</p> <p>Allows for the optional addition of a session timeout modal dialog. See “Application timeout-warning element” on page 134 for more information.</p>

#### Application application-menu element:

The application menu forms part of the application banner, and allows for the optional addition of up to three links; specifically a link to the application help, a link to log out of the application and a link to open the user preferences dialog.

Each link is defined as a child element of application-menu element and the supported elements are detailed in the following table.

Table 67. Supported child elements of the application-menu element

Element	Description
preferences	<p>Optional.</p> <p>Defines a link to the user preferences dialog. This dialog allows a user to configure customizations for the application view.</p> <p>The title of the preferences link is defined using the supported title attribute. The value of the title attribute should be a reference to an entry in the associated properties file.</p>
help	<p>Optional.</p> <p>Defines a link to the general help for the Cúram application.</p> <p>The title of the help link is defined using the supported title attribute. The value of the title attribute should be a reference to an entry in the associated properties file.</p>

Table 67. Supported child elements of the application-menu element (continued)

Element	Description
logout	<p><i>Optional.</i></p> <p>Defines a link to allow a user to end their session and logout of the application.</p> <p>The title of the logout link is defined using the supported title attribute. The value of the title attribute should be a reference to an entry in the associated properties file.</p>

### Application application-search element:

To define the application search, use the application-search element.

Refer to user interface element 1.4 in “Application Configuration” on page 125 to see an example of a fully configured application search in the user interface.

In its simplest form, the application-search element requires two attributes, which are used when there is only one type of search and no combo box is to be displayed:

Table 68. Attributes of the application-search element

Attribute	Description
default-search-page	<p><i>Optional.</i></p> <p>A reference to the UIM page that will be displayed when the search button is clicked.</p> <p>When this attribute is used, it is assumed there is only one type of search and no search type combo box is displayed.</p>
initial-text	<p><i>Optional.</i></p> <p>The text to be displayed in the text entry field as a prompt. This text should describe what type of information can be provided for the search, e.g. Enter a participant reference number.</p> <p>The attribute must reference an entry in the associated properties file.</p>

The application-search element supports two child elements that are used for more complex style searches, as shown in the following table.

Table 69. Supported child elements of the application-search element

Element	Description
search-pages	<p><i>Optional.</i></p> <p>Defines multiple types of search. See “search-pages” on page 133 for more information.</p>
further-options-link	<p><i>Optional.</i></p> <p>Defines a link to a more advanced search page. See “further-options-link” on page 134 for more information.</p>

## search-pages

The search-pages element is used when multiple search types are required, e.g. Person, Case, or types of search, e.g. Person Surname, Person Reference Number. Each search type is listed in a combo box and a different prompt is displayed in the text entry field depending on the selected entry in the combo box.

The search-pages element supports the child elements detailed in the following table.

*Table 70. Supported child elements of the search-pages element*

Element	Description
search-page	<i>1..n.</i>  Defines a single search type. The attributes of the search-page element are defined in Table 71.

**Note:** Where the search-pages element is used to define multiple types of search, the initial-text and default-search-page must not be specified.

*Table 71. Attributes of the search-page element*

Attribute	Description
type	<i>Mandatory.</i>  The unique identifier for the type of search. It will be passed as a parameter (searchType) to the UIM page invoked when the application search is performed.
description	<i>Mandatory.</i>  The text to be displayed for the search option in the combo box. The attribute must reference an entry in the associated properties file.
page-id	<i>Mandatory.</i>  A reference to a UIM page that will be displayed when the search button is clicked.
initial-text	<i>Mandatory.</i>  The text to be displayed as a prompt in the text entry field when that business object is selected in the combo box. The attribute must reference an entry in the associated properties file.
default	<i>Optional.</i>  A boolean indicating if this entry is the default entry to be selected in the combo box. One, and only one, entry should have the default specified as true.

**Note:** Blank values are not allowed in the search type combo box, so if the user requires a generic search (i.e. across all business objects), they must provide configuration data for this. For example, a business object of "All" linked to a page that will carry out the search across all the business objects that have been defined.

Search pages are linked using a reference to the UIM page to be opened when the search button is clicked. The UIM pages defined for a search can expect a number of parameters to be passed to them and used as part of the search:

- **searchText**  
The search text that has been entered in the text entry field.
- **searchType**  
The selected search type. This is only applicable where multiple search types have been defined.

For more information on creation of UIM pages see “UIM Reference” on page 52

#### **further-options-link**

In addition to multiple search types, the application search also supports a link to a more advanced search page. This is specified using the `further-options-link` element, which requires the following attributes:

*Table 72. Attributes of the further-options element*

Attribute	Description
description	<i>Mandatory.</i>  The text of the link. The attribute must reference an entry in the associated properties file.
page-id	<i>Mandatory.</i>  A reference to a UIM page that will be displayed when the link is clicked. This UIM page should require no page parameters.

#### **Application section-ref element:**

An application must reference a minimum of one section, and up to a maximum of five sections, by using the `section-ref` element.

See “Sections” on page 138 for more information.

*Table 73. Attributes of the section-ref element*

Attribute	Description
id	<i>Mandatory.</i>  The id of a section configuration file (.sec).

#### **Application timeout-warning element:**

Define the session timeout warning by using the `timeout-warning` element.

In its simplest form, the `timeout-warning` element does not require any mandatory attributes. If attributes are omitted default values will be used.

A browser session is timed from when data was most recently sent to or received from the server. In some cases, a user might enter much data into the application without realizing that the current session has timed out. When the user does initiate a server call, for example to submit the entered data, the browser prompts the user to reauthenticate to the application. Therefore, the user loses all the data



that the user had entered into the application. To prevent users from losing data when their session times out, you can configure a session timeout warning.

Table 74. Attributes of the timeout-warning element

Attribute	Description
title	<i>Optional.</i>  Configures the title on the session timeout warning dialog.  A reference to a property within the associated properties file. This value is used to display the title on the timeout warning dialog.
user-message	<i>Optional.</i>  Configures the main user message on the session timeout warning dialog.  A reference to a property within the associated properties file. This value is used to display the main user message within the timeout warning dialog.
quit-button	<i>Optional.</i>  Configures the text on the quit button of the session timeout warning dialog.  A reference to a property within the associated properties file. This value is used to display the text on the quit button within the timeout warning dialog.
continue-button	<i>Optional.</i>  Configures the text on the continue button of the session timeout warning dialog.  A reference to a property within the associated properties file. This value is used to display the text on the continue button within the timeout warning dialog.
width	<i>Optional.</i>  Configures the width of the session timeout warning dialog.  A reference to the width of the timeout warning dialog, in pixels.
height	<i>Optional.</i>  Configures the height of the session timeout warning dialog.  A reference to the height of the timeout warning dialog, in pixels.
timeout	<i>Optional.</i>  Configures the period of time in seconds that the user has to take action within the timeout warning dialog.  A reference to the period of time in seconds that the user has to take action within the dialog before the session expires. The countdown timer displayed within the modal will start at this value and countdown to 0:0 until the session times out.

## Application optional header

You can specify a custom header in addition to, or instead of, the application banner. Define the optional header by using the `header-type` and `header-source` attributes on the `application` element. Define the optional header as either a static HTML fragment or as a custom widget.

Where the header is required instead of the application banner, the optional attributes of the `applications` element, as listed in “Application definition” on page 129, should be omitted.

The `header-type` attribute is restricted to the values `static` or `dynamic`. Setting a static value indicates that a HTML fragment is to be placed within the header. In this instance, the `header-source` attribute should reference a file that is stored in the resource store. This file must be stored with a content type of `text/xml`.

If the `header-type` attribute is set to `dynamic`, the `header-source` attribute should reference the custom widget to be used to display the content. This reference will be the same as that specified with the relevant `styles-config.xml`. For more information on creating and referencing custom widgets please consult the *Cúram Custom Widget Development Guide*.

Whether a custom widget or HTML fragment is used it must always start with a `<div>` element.

## Application example

An example shows an application that is stored in a file called `SimpleApp.app`.

```

<?xml version="1.0" encoding="UTF-8"?>
<ac:application
  id="SimpleApp"
  logo="SimpleApp.logo"
  title="SimpleApp.title"
  subtitle="SimpleApp.subtitle"
  user-message="SimpleApp.UserMessage">

  <ac:application-menu>
    <ac:preferences title="preferences.title"/>
    <ac:help title="help.title"/>
    <ac:logout title="logout.title"/>
  </ac:application-menu>

  <ac:application-search>
    <ac:search-pages>
      <ac:search-page type="SAS01"
        description="Search.Person.LastName.Description"
        page-id="Person_searchResolver"
        initial-text="Search.Person.LastName.InitialText"
        default="true"/>
      <ac:search-page type="SAS02"
        description="Search.Person.Gender.Description"
        page-id="Person_listByGender"
        initial-text="Search.Person.Gender.InitialText" />
    </ac:search-pages>
    <ac:further-options-link
      description="Search.Further.Options.Link.Description"
      page-id="Person_search" />
    </ac:application-search>

  <ac:section-ref id="SimpleHomeSection"/>
  <ac:section-ref id="SimpleWorkspaceSection"/>

</ac:application>

```

*Figure 49. Simple.app*

**Note:** In the above example a namespace, ac has been declared and all elements are prefixed with the namespace. This is recommended practice. Consult “Application Configuration Files” on page 34 for more information.

The SimpleApp.app should have a corresponding SimpleApp.properties file, which details the localizable content. For example:

```

SimpleApp.logo=CDEJ/themes/v6/images/application-logo.png
SimpleApp.title=Cúram
SimpleApp.subtitle=Simple Application
SimpleApp.UserMessage=Welcome, %user-full-name

preferences.title=User Preference
help.title=Help
logout.title=Logout
Search.Person.LastName.Description=Surname
Search.Person.LastName.InitialText=Enter surname to search for
Search.Person.Gender.Description=Gender
Search.Person.Gender.InitialText=Enter gender to search for
Search.Further.Options.Link.Description=Advanced Search

```

In the above example, the Cúram logo image is referencing the default logo image shipped with the Cúram Client Development Environment (CDEJ). A custom logo can be added to the Images folder in the component and referenced directly as Images/my-custom-logo.png.

**Note:** In the properties file for the SimpleApp.app example, the `ú` in `Cúram` is added using the Unicode escape sequence. An alternative approach is to add the `ú` directly and ensure the file is saved in the UTF-8 format. Both approaches are supported for the application configuration files.

## Associate an application with a user

Map a user to the application and the home page that will be displayed when the user initially logs on. The home page is the initial page, which is displayed in its associated tab.

To map a user to an application and to a home page, configure the following mapping:

- APPLICATIONCODE field on the Users database table

maps to

- an entry in the APPLICATION\_CODE codetable

maps to

- the id attribute of an application

When a user logs in, the value of the APPLICATIONCODE field in the Users database table is used to determine both the application and home page to display.

The value field of the code table entry must match the name of the application (.app) file to use and the description field of the code table entry indicates the name of the UIM page to be displayed as the home page. The following example shows a subset of a code table definition:

```
<codetable java_identifier="APPLICATION_CODE"
           name="APPLICATION_CODE">
  <code default="false" java_identifier="SIMPLE_HOME"
        status="ENABLED" value="SimpleApp">
    <locale language="en" sort_order="0">
      <description>SimpleHome</description>
      <annotation></annotation>
    </locale>
  </code>
</codetable>
```

Figure 50. CT\_APPLICATIONCODE.ctx

**Note:** For more information on code tables see the *Cúram Server Developers Guide*.

In this example, a code table entry SimpleApp has been defined, with a description of SimpleHome. The code SimpleApp, matches the id of the SimpleApp.app example. The description, SimpleHome, indicates the UIM page to be displayed as the home page. This page must be associated with the relevant application. For more details on how to associate pages with an application, see “Opening tabs and sections” on page 165.

## Sections

An application can contain one or more application sections, where a section is a collection of tabs and an optional section shortcut panel. A section shortcut panel supports quick links to open tabs and dialogs within a section.




Figure 51. Application User Interface Overview

Refer to user interface element 2 in the previous figure to see sections configured in the user interface. The section that is open is a lighter shade of color than the other sections.

It is recommended that a maximum of five sections be used, each representing a different set of activities that can be performed by a user. The following list outlines the five recommended types of sections:

**Home** The Home section is intended to contain only one tab, with a single page that acts as a home page for the user. The home page should provide a summary of significant information and quick links to common activities.

### Workspace

The Workspace section is where the majority of tasks relating to the user role will be performed.

**Inbox** The Inbox section represents the area of the application where the user can access the work currently allocated to them.

### Calendar

The Calendar section contains a calendar of the users activities and schedules.

### Reports

The Reports section contains a number of reports relevant for the particular user.

## Section definition

A section is defined by creating an XML file with the extension .sec in the clientapps directory.

The root XML element in the .sec file is the section element and the attributes allowed on this element are defined in the following table.

Table 75. Attributes of the section Element

Attribute	Description
id	<i>Mandatory.</i>  The unique identifier for the section, which must match the name of the file. This is used when referenced from an application (.app) configuration file.
title	<i>Mandatory.</i>  The text for the title that will be displayed on the section tab. The attribute must reference an entry in the associated properties file.
hide-tab-container	<i>Optional.</i>  When set to true, this indicates that there is only one tab in the section and the tab bar should not be displayed. The default is false.
default-page-id	<i>Optional.</i>  A reference to a UIM page that should be opened by default when the section is opened. The UIM page referenced must be directly associated with a tab. For more information on associating pages with tabs, consult “Tabs” on page 145.  This attribute ensures that an anchored default tab is always open when the section is opened. An anchored tab does not contain an option to close it.

**Note:** The default-page-id attribute must not be used on the "Home" or first section of an application. The user's home page, and its associated tab are opened automatically when a user logs into an application. See “Associate an application with a user” on page 138 for more information.

The section element supports the child elements detailed in the following table.

Table 76. Supported Child Elements of the section Element

Element	Description
tab	<i>1..n.</i>  A reference to a tab to be included in this section. See “Section tab element” on page 141 for more information.
shortcut-panel-ref	<i>Optional.</i>  A reference to the section shortcut panel to be included in this section. See “Section shortcut-panel-ref element” on page 141 for more information.

### Section tab element:

A section is a collection of tabs. To associate a tab with a section, use the tab element. A section must define at least one tab element and tabs must only ever be referenced by one section in any application. Therefore tabs can be reused in different sections, as long as the section is included in a separate application.

The attributes of the tab element are detailed in the following table.

Table 77. Attributes of the tab element

Attribute	Description
id	<i>Mandatory.</i>  The id of a tab configuration file (.tab). See "Section tab element" for more information.

### Section shortcut-panel-ref element:

Use the shortcut-panel-ref element to define the section shortcut panel to add to a section.

Specify only one shortcut-panel-ref per section. See "Section shortcut panel" on page 142 for more information.

The attributes of the shortcut-panel-ref element are detailed in the following table.

Table 78. Attributes of the shortcut-panel-ref element

Attribute	Description
id	<i>Mandatory.</i>  The id of a section shortcut panel (.sec). See "Section shortcut panel" on page 142 for more information.

### Section example

An example shows a section that is stored in a file called SimpleWorkspaceSection.sec.

```
<?xml version="1.0" encoding="UTF-8"?>
<sc:section
  id="SimpleWorkspaceSection"
  title="SimpleWorkspaceSection.title">

  <sc:shortcut-panel-ref id="SimpleShortcutPanel"/>

  <sc:tab id="Person" />
  <sc:tab id="Employer" />
  <sc:tab id="Case" />
  ...
</sc:section>
```

Figure 52. SimpleWorkspaceSection.sec

The SimpleWorkspaceSection.sec should have a corresponding SimpleWorkspaceSection.properties file, which details the localizable content. For

example:

```
SimpleWorkspaceSection.title=Workspace
```

## Section shortcut panel

Each section can optionally contain a section shortcut panel which provides quick links to open content and perform actions within the section. The menu items in the shortcut panel can be divided into categories.

Refer to User Interface Element 7 of “Application Configuration” on page 125 to see an example of a configured section shortcut panel.

When a section is first opened, the section shortcut panel is collapsed by default. The double arrow beside the title of the shortcut panel can be used to expand, and subsequently collapse, the panel.

Menu items in a shortcut panel which open modal dialogs are identified by an ellipses (...), which indicates that further actions are required. Refer to User Interface Element 7.1.1 of “Application Configuration” on page 125 to see an example of a configured menu item in an expanded category of a shortcut panel.

### Section shortcut panel definition

A section shortcut panel is defined by creating an XML file with the extension `.ssp` in the `clientapps` directory.

The root XML element in the `.ssp` file is the `section-shortcut-panel` element and the attributes allowed on this element are defined in the following table.

Table 79. Attributes of the section-shortcut-panel Element

Attribute	Description
id	<i>Mandatory.</i>  The unique identifier for the section shortcut panel, which must match the name of the file. This is used when referenced from a section ( <code>.sec</code> ) configuration file.
title	<i>Mandatory.</i>  The text for the title that will be displayed for the sections shortcut panel, both when it is expanded and when it is collapsed. The attribute must reference an entry in the associated properties file.

The `section-shortcut-panel` element supports the child elements detailed in the following table.

Table 80. Supported Child Elements of the section-shortcut-panel Element

Element	Description
nodes	<i>Mandatory.</i>  Groups together multiple child node elements. See “Section shortcut panel node element” on page 143 for more information.



## Section shortcut panel node element:

Use the node element to represent menu items and categories that are used within the shortcut panel.

There are three supported types of node element and the type attribute is used to define this:

- **group**

A group node in a shortcut panel represents a category and is used to categorize a number of menu items as described in “Section shortcut panel” on page 142. “Registration” are defined using node Each category is defined using node elements of type group. This type of node supports child node elements of type leaf and separator.

- **leaf**

A leaf in a shortcut panel is a menu item within a category, which can open a page in an existing or new tab, or open a modal dialog<sup>3</sup>. Where a menu item opens a modal dialog, an ellipsis is appended to the text displayed to indicate more information is required.

- **separator**

A separator can be used to add extra space between menu items within a node of type group (i.e. a category).

The attributes supported by the node element are detailed in the following table.

Table 81. Attributes of the node element

Attribute	Description
id	<i>Mandatory.</i>  The identifier for the node. This must be unique within the .ssp file.
type	<i>Mandatory.</i>  The type of node, where three types are supported: <ul style="list-style-type: none"><li>• group</li><li>• leaf</li><li>• separator</li></ul>
title	<i>Mandatory.</i>  The text for the title of the node. The attribute must reference an entry in the associated properties file.  Note: This is not required where the type is specified as separator.
page-id	<i>Optional.</i>  A reference to the UIM page to be displayed when the menu item is selected. This is only applicable for node elements with a type of leaf.

---

3. A modal dialog is a UIM page opened in a new window, where the parent window cannot be accessed while it is open. Consult “Modal Dialogs” on page 88 for more information.

Table 81. Attributes of the node element (continued)

Attribute	Description
open-as	<p><i>Optional.</i></p> <p>Where set, this attribute indicates the UIM page to be displayed when the menu item is selected should be opened as a modal dialog. The only value supported is <i>modal</i>.</p> <p>This is only applicable for node elements with a type of leaf.</p>
append-ellipsis	<p><i>Optional.</i></p> <p>A boolean attribute which indicates if the ellipsis automatically appended to the menu item which opens in a modal dialog should be disabled. The default is true. The attribute is applicable only where the type attribute is leaf and the open-as attribute has been set.</p> <p>Note: Setting this attribute to true where the open-as attribute has not been set will not add the ellipsis to the menu item.</p>

## Section shortcut panel example

An example shows a section shortcut panel that is stored in a file called SimpleShortcutPanel.ssp.

```
<?xml version="1.0" encoding="UTF-8"?>
<sc:section-shortcut-panel
  id="SimpleShortcutPanel"
  title="SimpleShortcutPanel.Title">

  <sc:nodes>
    <sc:node id="Searches" type="group"
      title="Searches.Title">
      <sc:node id="PersonSearch" type="leaf"
        page-id="Person_search"
        title="PersonSearch.Title" />
      ...
    </sc:node>
    <sc:node id="QuickLinks" type="group"
      title="QuickLinks.Title">
      ...
    </sc:node>
    <sc:node id="Registration" type="group"
      title="Registration.Title">
      <sc:node id="RegisterEmployer" type="leaf"
        page-id="Employer_register"
        title="RegisterEmployer.Title"
        open-as="modal" />
      ...
      <sc:node type="separator" id="separator" />
      ...
    </sc:node>
  </sc:nodes>
</section-shortcut-panel>
```

Figure 53. SimpleShortcutPanel.ssp

The SimpleShortcutPanel.ssp should have a corresponding SimpleShortcutPanel.properties file, which details the localizable content. For example:

SimpleShortcutPanel.Title=Shortcuts Panel  
 Searches.Title=Searches  
 PersonSearch.Title=Person Search  
 QuickLinks.Title=Quick Links  
 Registration.Title=Registration  
 RegisterEmployer.Title=Register an Employer

## Tabs

A tab typically represents a business object, for example, a Case or a Participant, though it can also be used to represent a logical grouping of information.

The following figure shows an annotated example of a configured tab in an application.




Figure 54. Application User Interface Overview

The following list describes the annotated tab elements that are in the previous figure:

### Tab Title Bar (4)

The title bar contains text to identify the current tab.

### Tab Actions Menu (5)

The actions menu provides actions associated with the business object

represent by the tab. The actions can be a mix of menu items and other menus, each of which links to a page that will be displayed in the tab content area or a modal dialog.

#### **Tab Context Panel (6)**

The context panel is typically used to present summary information about the business object. The summary information is available for every page that is displayed in the content area. The context panel can be collapsed and expanded to provide more space for the tab content area.

#### **Tab Content Area**

A tab comprises of one or more pages of information. The pages are displayed in the content area and can be navigated using the navigation bar.

#### **Navigation Bar (8)**

The navigation bar contains a number of navigation tabs, each of which link to a page or set of pages that are part of the tab. The navigation bar can be used to separate the business object information into logical groupings of pages.

#### **Page Group Navigation Bar (16)**

Where a tab links to a set of pages, the pages are displayed as a page group navigation bar, with the first one selected by default.

#### **Page Content (15)**

Selecting a navigation tab or page group entry will display the corresponding UIM page content within the content area.

#### **Smart panel (20)**

A smart panel is an optional panel, displaying a UIM page, that is added to the right of the content area in a tab. It can be collapsed and expanded, and is collapsed by default. In addition, the size of the smart panel can be increased and decreased when it is expanded.

A tab supports the ability to dynamically enable or disable, and hide or show, entries in the tab actions menu, the tab navigation bar and the page group navigation bar. The dynamic content is updated based on configured refresh events. A refresh event updates the specified part of the tab based on the submission of a modal dialog page or when a specific UIM page is loaded in the content area.

#### **Related reference:**

“Tab tab-refresh element” on page 150

The tab-refresh element allows the tab actions menu, tab navigation and context panel to be refreshed based on different events.

#### **Tab definition**

A tab is defined by creating an XML file with the extension .tab in the clientapps directory.

The root XML element in the .tab file is the tab-config element and the following table shows the required attributes.

Table 82. Attributes of the tab-config Element

Attribute	Description
id	<p><i>Mandatory.</i></p> <p>The identifier for the tab, which must match the name of the file.</p> <p>The id attribute is used to reference the tab configuration from section configuration files (.sec). See “Section tab element” on page 141 for more information.</p>

The tab-config element supports the child elements that are shown in the following table. See the child topics for more information.

Table 83. Supported Child Elements of the tab-config Element

Element	Description
page-param	<p><i>0..n.</i></p> <p>Defines a parameter required when opening a tab.</p>
menu	<p><i>Optional.</i></p> <p>A reference to the actions menu configuration.</p>
context	<p><i>Mandatory.</i></p> <p>A reference to the UIM page to be used as the tab context panel, or alternatively details of the tab name and title.</p>
navigation	<p><i>Mandatory.</i></p> <p>A reference to the tab navigation configuration, or alternatively the name of the UIM page that will be opened in this tab.</p>
smart-panel	<p><i>Optional.</i></p> <p>A reference to the UIM page to be used for the smart panel.</p>
tab-refresh	<p><i>Optional.</i></p> <p>Defines what part of a tab should refresh under what circumstances.</p>

#### Tab page-param element:

The page-param element allows for multiple page parameters to be defined for a tab. Each page parameter that is defined maps to the name of a name-value pair. The name-value pair is passed to all UIM pages that are opened from both the tab actions menu and the navigation bar.

Page parameters are also used to identify unique instances of a tab. For example, a tab is defined for a Person object. Two instances of this tab can be opened, one for James Smith and one for Linda Smith. The instances are uniquely identified by the page parameter, id, which has been defined for the tab. The id parameter maps to the unique id for the person and will be different for both James Smith and Linda Smith.

Table 84. Attributes of the page-param Element

Attribute	Description
name	<i>Mandatory.</i>  A unique identifier for the page parameter.

**Related reference:**

“Opening tabs and sections” on page 165

You can open new sections and tabs by using several methods.

**Tab menu element:**

The menu element contains a reference to the tab action menu configuration which is maintained in a separate .mnu configuration file.

The following table shows the attributes of the menu element.

Table 85. Attributes of the menu element

Attribute	Description
id	<i>Mandatory.</i>  A reference to the id of a tab action menu configuration file (.mnu).

**Related reference:**

“Tab actions menu” on page 153

The tab actions menu is a drop-down menu in the tab title bar. Each menu item corresponds to a tab-specific action.

**Tab context element:**

The context element defines a context panel by referencing a UIM page which forms the content of the context panel.

The context element is mandatory. If no context panel is to be defined, then a tab name and tab title must be specified.

The tab title bar and tab name can be populated with data using either the context panel UIM page or using the tab-name and tab-title attributes in the .tab file. Where the context panel UIM page is used only to add content to the tab name and tab title, the height attribute should be set to zero.

Table 86. Attributes of the context element

Attribute	Description
page-id	<i>Optional.</i>  A reference to the UIM page that will be used for the content of the context panel. If this is not specified, the tab-name and tab-title attributes <i>must</i> be specified.
tab-name	<i>Optional.</i>  The text that will be displayed in the tab bar. The attribute must reference an entry in the associated properties file.

Table 86. Attributes of the context element (continued)

Attribute	Description
tab-title	Optional.  The text that will be displayed in the tab title bar. The attribute must reference an entry in the associated properties file.
height	Optional.  The pixel height of the context panel. This is only relevant if a page-id attribute has been specified to define a context panel.  The default value if not specified is 150 pixels.

**Related reference:**

“Context panel UIM” on page 152

A context panel is a specific type of UIM page identified by the PAGE element that contains an attribute of TYPE="DETAILS".

**Tab navigation element:**

The navigation element defines what pages are opened within a tab.

A single page can be defined using the page-id attribute, or multiple pages can be defined using a reference to the tab navigation configuration file (.nav).

**Note:** The navigation element is mandatory and one of either page-id or id must be specified.

Table 87. Attributes of the navigation element

Attribute	Description
page-id	Optional.  A reference to the UIM page that will be opened in the tab. When a link to this UIM page is selected, it will automatically trigger the page to be opened in a new tab.
id	Optional.  A reference to a tab navigation configuration file (.nav).

**Related reference:**

“Tab navigation” on page 160

The various UIM pages are grouped as part of a tab that can be navigated to within a tab. Tab navigation includes the Content Area Navigation Bar and the Page Group Navigation Bar components.

**Tab smart-panel element:**

The content of the smart panel is defined by a UIM page, referenced by the page-id attribute.

Similar to the context panel, the UIM elements that can be used are limited. Refer to User Interface Element 20 of “Tabs” on page 145 for an example of a smart panel configured in an application.

Table 88. Attributes of the smart-panel element

Attribute	Description
page-id	<i>Mandatory.</i>  A reference to the UIM page that will be displayed in the smart panel of the tab.
title	<i>Mandatory.</i>  The text for the title that will be displayed for the smart panel, both when it is expanded and when it is collapsed. The attribute must reference an entry in the associated properties file
width	<i>Optional.</i>  The initial width of the smart panel when it is expanded. The default value if this attribute is not set is 250 pixels.
collapsed	<i>Optional.</i>  Boolean indicating if the smart panel should be expanded or collapsed by default. The default value if this attribute is not set is true.

**Related reference:**

“Context panel UIM” on page 152

A context panel is a specific type of UIM page identified by the PAGE element that contains an attribute of TYPE="DETAILS".

**Tab tab-refresh element:**

The tab-refresh element allows the tab actions menu, tab navigation and context panel to be refreshed based on different events.

By default, only the content area of a tab is refreshed when a modal dialog is submitted. When a modal dialog is either closed or canceled without an action being performed, the content area is not refreshed.

The tab actions menu, tab navigation and context panel can all be refreshed based on two events. The first event is when a specific UIM page is loaded in the content area, and the second event is when a UIM page is submitted from a modal or the content area. The following list describes how each element of a tab is refreshed:

**Tab Actions Menu**

Refreshing the tab actions menu results in updating the entries in the menu that can be dynamically disabled or hidden. See the related link for more information about dynamic support.

**Tab Navigation**

Refreshing the tab navigation results in updating the entries in the tab navigation bar and page group navigation bar that can be dynamically disabled or hidden. See the related link for more information about dynamic support.

**Context Panel**

Refreshing the context panel reloads the UIM page that is displayed in the context panel.

**Content Area**

Refreshing the content area reloads the UIM page that is displayed in the



content area. This refresh option is available for use only where a modal dialog has been opened from the list drop-down panel of a nested expandable list.

By default only the parent of a list drop-down panel is updated when the modal dialog is submitted. Where the list drop-down panel exists in a nested expandable list, this will result in the parent list reloading and not the entire content area.

The two different type of refresh events can be configured by using the child elements that are detailed in the following table.

*Table 89. Supported child elements of the tab-refresh element*

Element	Description
onload	<i>1..n.</i> Defines a refresh event, where when the specified page is loaded in the content area, the defined parts of the tab are updated.
onsubmit	<i>1..n.</i> Defines a refresh event, where when the specified page is submitted from a modal or in the content area, the defined parts of the tab are updated.

### **onsubmit/onload**

The onsubmit and onload elements both require the same set of attributes, as described in the following table.

*Table 90. Attributes of the onload/onsubmit Elements*

Attribute	Description
page-id	<i>Mandatory.</i> A reference to the UIM page to associate with the refresh event.
context	<i>Optional.</i> Boolean indicating if the context panel should be update when the specified page is loaded or submitted.
menu-bar	<i>Optional.</i> Boolean indicating if the tab actions menu should be updated when the specified page is loaded or submitted. See the related link for more information about dynamic support.
navigation	<i>Optional.</i> Boolean indicating if the tab navigation should be updated when the specified page is loaded or submitted. See the related link for more information about dynamic support.

Table 90. Attributes of the onload/onsubmit Elements (continued)

Attribute	Description
main-content	<p><i>Optional.</i></p> <p>Boolean indicating if the main content area should be updated when the specified page is loaded or submitted.</p> <p>This type of refresh event must only be used for modal dialogs that are opened from a list dropdown panel in a nested expandable list.</p>

**Related reference:**

“Tab actions menu dynamic support” on page 158

The tab actions menu supports the ability to dynamically enable or disable entries, and hide or show entries. This feature is supported using a combination of the dynamic attribute of the menu-item element, the loader-registry element and a Java loader implementation.

## Context panel UIM

A context panel is a specific type of UIM page identified by the PAGE element that contains an attribute of TYPE="DETAILS".

This type of UIM page can only use a subset of existing UIM elements, as indicated in the following list:

- SERVER\_INTERFACE can only be used with a DISPLAY phase
- ACTION\_CONTROL can only be used with an ACTION type
- The following elements are not supported:
  - MENU
  - SHORTCUT\_TITLE
  - JSP\_SCRIPTLET
  - DESCRIPTION
  - INFORMATIONAL
  - SCRIPT
  - INCLUDE
  - VIEW

**Note:** These same limitations apply to the smart panel UIM pages, but are not enforced.

A mandatory TAB\_NAME element is required for context panel UIM pages, which allows for dynamic information to be added to the tab name. Additionally, a mandatory PAGE\_TITLE element is required to add information to the tab title bar.

**Related reference:**

“TAB\_NAME” on page 105

“PAGE TITLE” on page 101

## Tab example configuration file

An example is provided of a tab configuration file.

The following example shows a tab configuration file named SimpleTab.tab.

```

<?xml version="1.0" encoding="UTF-8"?>
<tc:tab-config
  id="SimpleTab">

  <tc:page-param name="concernroleid"/>

  <tc:menu id="SimpleMenu"/>

  <tc:context page-id="SimpleDetailsPanel"
    tab-name="simple.tab.name" />

  <tc:navigation id="SimpleNavigation"/>

  <tc:smart-panel page-id="SimpleSmartPanel"
    title="smart.panel.title"
    collapsed="true"
    width="300" />

  <tc:tab-refresh>
    <tc:onload page-id="SimpleHome" navigation="true"/>
    <tc:onsubmit page-id="ModifySomething"
      context="true" menu-bar="true"/>
  </tc:tab-refresh>

</tc:tab-config>

```

*Figure 55. SimpleTab.tab*

The SimpleTab.tab file should have a corresponding SimpleTab.properties file, which details the localizable content, for example:

```

simple.tab.name=Simple Tab
smart.panel.title=Smart Panel

```

## Tab actions menu

The tab actions menu is a drop-down menu in the tab title bar. Each menu item corresponds to a tab-specific action.

The menu items support opening UIM pages in the content area of a tab, or alternatively opening a modal dialog to perform some action - these are identified by an ellipses (...). Additionally, it is possible to download a file directly from a menu item.

The tab actions menu also supports the ability to dynamically hide and show items, and enable and disable items in the menu. Refer to User Interface Element 5 of “Tabs” on page 145 for an example of a tab actions menu configured in an application. The menu items that are dynamically hidden are disabled in the menu.

### Tab actions menu definition

Define a tab actions menu by creating an XML file with the extension .mnu in the clientapps directory.

The root XML element in the .mnu file is the menu-bar element and the attributes allowed on this element are defined in the following table.

Table 91. Attributes of the menu-bar element

Attribute	Description
id	<p><i>Mandatory.</i></p> <p>The unique identifier for the menu, which must match the name of the file. The identifier is used when a menu is included in a tab configuration by using the menu element.</p>

A menu definition can be reused and referenced by multiple tab configurations. The menu itself comprises of menu items and submenus, which are used to group menu items. The child elements outlined in the following table are used to define the structure of the menu. See the child topics for more information.

Table 92. Supported child elements of the menu-bar element

Element	Description
menu-item	<p><i>0..n.</i></p> <p>Defines a single entry in the menu, which links to a UIM page that can be opened in a modal dialog or in the content area of a tab.</p>
submenu	<p><i>0..n.</i></p> <p>Defines a grouping of menu items, which form a sub menu.</p>
menu-separator	<p><i>0..n.</i></p> <p>Defines a separator line between entries in the menu.</p>
loader-registry	<p><i>Optional.</i></p> <p>Defines the server interfaces that can be called to dynamically change the state of the menu-items.</p>

#### Tab actions menu menu-item element:

An action entry in the tab actions menu is defined by the menu-item element.

The attributes of the menu-item element are defined in the following table.

A menu-item can do the following actions:

- Open a UIM page in the content area of a tab.
- Open a UIM page in a modal dialog.
- Download a file.

Menu items which open modal dialogs are identified by an ellipsis (...), which indicates that further actions are required.

Table 93. Attributes of the menu-item element

Attribute	Description
id	<p><i>Mandatory.</i></p> <p>The unique identifier for the menu-item, which must be unique within the configuration file.</p>

Table 93. Attributes of the menu-item element (continued)

Attribute	Description
page-id	<i>Mandatory.</i>  A reference to the UIM page to open when the menu-item is selected.
title	<i>Mandatory.</i>  The text that will be displayed for the menu-item. The attribute must reference an entry in the associated properties file.
open-as	<i>Optional.</i>  Where set, this attribute indicates that the UIM page to be displayed should be opened as a modal dialog. The only value supported is <i>modal</i> .
append-ellipsis	<i>Optional.</i>  A boolean attribute which indicates if the ellipsis automatically appended to menu-items which open in a modal dialog should be displayed. The default is true. The attribute is applicable only where the open-as attribute has been set.  Note: Setting this attribute to true where the open-as attribute has not been set will not add the ellipsis to the menu-item.
window-options	<i>Optional.</i>  Defines the height and width of a modal dialog opened from the menu-item. This is only applicable where the open-as attribute is set to modal.  The format for the attribute is: width=<pixel value>,height=<pixel value>  For example: window-options="width=500,height=300"  The height portion of the window-options is optional and if not specified, the height of the dialog will be automatically calculated.
dynamic	<i>Optional.</i>  Boolean indicating that the menu-item can be dynamically disabled or hidden. For more information see the related link.
visible	<i>Optional.</i>  Boolean indicating if the menu-item is hidden or visible. The default is true.
type	<i>Optional.</i>  Defines a menu-item that downloads a file when selected. The only value supported is FILE_DOWNLOAD. For more information see the related link.
description	<i>Optional.</i>  Defines text which forms a description for the menu-item. This is used for administration purposes only. The attribute must reference an entry in the associated properties file.

**Related reference:**

“Tab actions menu dynamic support” on page 158

The tab actions menu supports the ability to dynamically enable or disable entries, and hide or show entries. This feature is supported using a combination of the dynamic attribute of the menu-item element, the loader-registry element and a Java loader implementation.

“File download menu item” on page 158

A menu-item can reference a FILE\_DOWNLOAD configuration by using the type="FILE\_DOWNLOAD" attribute.

**Tab actions menu submenu element:**

A submenu is a group of menu items and is defined by using the submenu element.

The attributes of the submenu element are defined in the following table.

*Table 94. Attributes of the submenu element*

Attribute	Description
id	<i>Mandatory.</i>  The unique identifier for the submenu, which must be unique within the configuration file.
title	<i>Mandatory.</i>  The text that will be displayed for the submenu. The attribute must reference an entry in the associated properties file.
description	<i>Optional.</i>  Defines text which forms a description for the submenu. This is used for administration purposes only. The attribute must reference an entry in the associated properties file.

The submenu element allows for further submenus to be defined, in addition to including menu items and menu separators. Use the supported child attributes that are defined in the following table:

*Table 95. Supported child elements of the submenu element*

Element	Description
menu-item	<i>0..n.</i>  Defines a single entry in the submenu, which links to a UIM page that can be opened in a modal dialog or in the content area of a tab.
submenu	<i>0..n.</i>  Defines a further sub grouping of menu items.
menu-separator	<i>0..n.</i>  Defines a separator between entries in the submenu.

**Tab actions menu menu-separator element:**

A tab actions menu, including associated submenus, can include a line separator to divide the entries in the menu.

Define a line separator by using a menu-separator element. The attributes of the menu-separator are outlined in the following table.

*Table 96. Attributes of the menu-separator element*

Attribute	Description
id	<i>Mandatory.</i> The unique identifier for the menu-separator.

#### **Tab actions menu loader-registry element:**

The loader-registry element defines a list of loader implementations that is used to dynamically enable or disable, and to hide or show the menu items in the tab actions menu.

The following table shows the supported child elements of the loader-registry element.

*Table 97. Supported child elements of the loader-registry element*

Element	Description
loader	<i>1..n.</i> Defines one or more loader implementations that will be used to dynamically set the visibility and enabled state of the menu items.

#### **Related reference:**

“Tab actions menu dynamic support” on page 158

The tab actions menu supports the ability to dynamically enable or disable entries, and hide or show entries. This feature is supported using a combination of the dynamic attribute of the menu-item element, the loader-registry element and a Java loader implementation.

#### **Tab actions menu loader element:**

The loader element defines a single loader implementation that will dynamically set the state of the menu items in a tab actions menu.

The following table shows the attributes of the loader element.

*Table 98. Attributes of the loader Element*

Attribute	Description
class	<i>Mandatory.</i> The fully qualified class name of an implementation of the <code>curam.util.tab.impl.DynamicMenuStateLoader</code> interface.

#### **Related reference:**

“Tab actions menu dynamic support” on page 158

The tab actions menu supports the ability to dynamically enable or disable entries, and hide or show entries. This feature is supported using a combination of the dynamic attribute of the menu-item element, the loader-registry element and a Java loader implementation.

## Tab actions menu dynamic support

The tab actions menu supports the ability to dynamically enable or disable entries, and hide or show entries. This feature is supported using a combination of the dynamic attribute of the menu-item element, the loader-registry element and a Java loader implementation.

The Java loader implementation registered in the navigation configuration will be called when the tab is first loaded and based on the refresh options configured for a tab. The refresh options are configured in the tab configuration file (.tab).

A menu item can be specified as dynamic in the menu configuration file (.mnu) by adding dynamic="true" to the relevant menu-item element.

Where the dynamic attribute is set, a loader-registry is then required and should define the fully qualified classname which implements the `curam.util.tab.impl.DynamicMenuStateLoader` interface.

The `DynamicMenuStateLoader` interface requires one method, `loadMenuState`, to be implemented. The `loadMenuState` method is passed the following parameters:

- a list of menu item identifiers
- a set of name-value page parameters pairs

The loader implementation must decide which menu items to disable or hide. The method returns an object that represents the state of a given menu bar. A state must be set for all identifiers in the list. For more information on this interface, consult the Java Documentation.

**Note:** The list of menu item identifiers passed to the `loadMenuState` method are only those that have been identified as dynamic by the dynamic attribute on the menu-item element.

### Related reference:

“Tab tab-refresh element” on page 150

The tab-refresh element allows the tab actions menu, tab navigation and context panel to be refreshed based on different events.

## File download menu item

A menu-item can reference a `FILE_DOWNLOAD` configuration by using the `type="FILE_DOWNLOAD"` attribute.

The following sample code shows an example of using the `FILE_DOWNLOAD` element in the `curam-config.xml` file:

```
<mc: menu-item id="filedownloadItem" title="some.text.title"
  type="FILE_DOWNLOAD" page-id="FileDownload"/>
```

The `page-id` attribute must match the `page-id` attribute specified for the `FILE_DOWNLOAD` element.

When configuring the `FILE_DOWNLOAD` element in `curam-config.xml`, only the parameters defined for the tab can be used as values for the `PAGE_PARAM` attribute of the `INPUT` element.

The following example shows a fragment of the `FILE_DOWNLOAD` configuration from the `curam-config.xml` file. In this example, the `fileID` page parameter must be specified as a `page-param` element in the tab configuration file (.tab).



Note also that the PAGE\_ID attribute value of FileDownload matches the page-id attribute in the example above.

```
<FILE_DOWNLOAD CLASS="some.pkg.readFile"
    PAGE_ID="FileDownload">
  <INPUT PAGE_PARAM="fileID"
    PROPERTY="key$fileID"/>
  <FILE_NAME PROPERTY="result$name"/>
  <FILE_DATA PROPERTY="result$contents"/>
  <CONTENT_TYPE PROPERTY="result$contentType"/>
</FILE_DOWNLOAD>
```

Figure 56. FILE\_DOWNLOAD Configuration from curam-config.xml

#### Related reference:

“File Downloads” on page 56

### Tab actions menu example configuration file

An example is provided of a tab actions menu configuration file.

The following example shows an example tab actions menu configuration file named SimpleMenu.mnu.

```
<?xml version="1.0" encoding="UTF-8"?>
<mc:menu-bar
  id="SimpleMenu"

  <mc:loader-registry>
    <mc:loader class="some.pkg.SimpleMenuStateLoader"/>
  </mc:loader-registry>

  <mc:submenu id="Person">

    <mc:menu-item id="dynamicLink"
      title="dynamicLink.title"
      page-id="SomeDynamicContent"
      dynamic="true"/>

    <mc:menu-separator id="separator1"/>

    <mc:menu-item id="simpleLink"
      title="simpleLink.title"
      page-id="SimplePage"/>

  </mc:submenu>

  <mc:menu-item id="OpenModal"
    title="openmodal.title"
    page-id="DoSomethingInModal"
    open-as="modal"
    window-options="width=600"/>

</mc:menu-bar>
```

Figure 57. SimpleMenu.mnu

The SimpleMenu.mnu should have a corresponding SimpleMenu.properties file, which details the localizable content, for example:

```
dynamicLink.title=Some Dynamic Link
simpleLink.title=A Simple Link
openmodal.title=Open a Modal
```

## Tab navigation

The various UIM pages are grouped as part of a tab that can be navigated to within a tab. Tab navigation includes the Content Area Navigation Bar and the Page Group Navigation Bar components.

The following list describes the tab navigation components:

### Navigation Bar

The navigation bar contains a number of tabs, each of which can map to a single UIM page or alternatively a set of UIM pages. The tabs in the navigation bar are referred to as navigation tabs. Refer to User Interface Element 8 of “Tabs” on page 145 for an example of a navigation bar configured in an application.

### Page Group Navigation Bar

Where a navigation tab maps to a set of UIM pages, these UIM pages are displayed as a page group navigation bar. Each link in the page group navigation bar is referred to as a navigation page. Refer to User Interface Element 16 of “Tabs” on page 145 for an example of a page group navigation bar configured in an application.

Selecting a navigation tab or navigation page will result in displaying the relevant UIM page in the content area of the tab. For navigation tabs that have a page group navigation bar, the first navigation page in the page group navigation bar is selected when the navigation tab is selected.

If a user selects a subsequent navigation page and then changes to a different navigation tab, the selected navigation page is remembered when the user returns to the original navigation tab and the page is reloaded.

The tab navigation configuration defines when new tabs are opened and determines what UIM page is associated with what tab.

## Tab navigation definition

Tab navigation is defined by creating an XML file with the extension .nav in the clientapps directory.

The root XML element in the .nav file is the navigation element and the attributes allowed on the element are defined in the following table.

Table 99. Attributes of the navigation element

Attribute	Description
id	<i>Mandatory.</i>  The unique identifier for the navigation configuration, which must match the name of the file. The identifier is used when a navigation configuration is included in a tab configuration, using the navigation element.

The child elements outlined in the following table are used to define the structure of the navigation. For more information, see the child topics.

Table 100. Supported child elements of the navigation element

Element	Description
nodes	<i>Mandatory.</i>  Groups navigation pages and navigation tabs together.
loader-registry	<i>Optional.</i>  Defines the server interfaces that can be called to dynamically change the state of the navigation tabs and navigation pages.

#### Tab navigation nodes element:

The nodes element groups together the elements that represent navigation tabs and navigation pages.

The elements are outlined in the following table.

Table 101. Supported child elements of the nodes element

Element	Description
navigation-page	<i>1..n.</i>  Defines a navigation tab that has no page group navigation bar.
navigation-group	<i>1..n.</i>  Defines a navigation tab which contains a page group navigation bar. This element groups together navigation-page elements that form the page group navigation bar.

#### Tab navigation navigation-group element:

The navigation-group element defines a navigation tab that contains a page group navigation bar.

The attributes of the element are outlined in the following table.

Table 102. Attributes of the navigation-group element

Attribute	Description
id	<i>Mandatory.</i>  The unique identifier for the navigation-group, which must be unique within the configuration file.
title	<i>Mandatory.</i>  The text that will be displayed for the navigation tab in the navigation bar. The attribute must reference an entry in the associated properties file.
dynamic	<i>Optional.</i>  Boolean indicating that the navigation tab can be dynamically disabled or hidden.

Table 102. Attributes of the navigation-group element (continued)

Attribute	Description
visible	<i>Optional.</i>  Boolean indicating if the navigation tab is hidden or visible. The default is true.
description	<i>Optional.</i>  Defines text which forms a description for the navigation tab. This is used for administration purposes only. The attribute must reference an entry in the associated properties file.

The navigation-group element groups together navigation-page elements to form the page group navigation bar. The first navigation-page element defined indicates the UIM page to display the first time a navigation tab is selected.

Subsequent selections of the navigation tab, for a given instance of a tab, will remember the previously selected navigation page.

Table 103. Supported child elements of the navigation-group element

Element	Description
navigation-page	<i>1..n.</i>  Defines the set of navigation pages that are grouped together to form the page group navigation bar.

#### Related reference:

“Tab navigation dynamic support” on page 164

The tab navigation bar and page group navigation bar support the ability to dynamically enable or disable, and hide or show, navigation tabs and navigation pages.

#### Tab navigation navigation-page element:

A navigation-page element can represent both a navigation tab and navigation page.

If the navigation-page element is defined as a child element of the nodes element, it represent a navigation tab which is part of the navigation bar. If the navigation-page element is defined as a child element of the navigation-group element, it represent a navigation page which is part of the page group navigation bar.

The attributes of the navigation-page element are outlined in the following table.

Table 104. Attributes of the navigation-page element

Attribute	Description
id	<i>Mandatory.</i>  The unique identifier for the navigation-page, which must be unique within the configuration file.
page-id	<i>Mandatory.</i>  A reference to the UIM page to open when the navigation tab or navigation page is selected.

Table 104. Attributes of the navigation-page element (continued)

Attribute	Description
title	<i>Mandatory.</i>  The text that will be displayed for the navigation tab or navigation page. The attribute must reference an entry in the associated properties file.
dynamic	<i>Optional.</i>  Boolean indicating that the navigation tab or navigation page can be dynamically disabled or hidden.
visible	<i>Optional.</i>  Boolean indicating if the navigation tab or navigation page is hidden or visible. The default is true.
description	<i>Optional.</i>  Defines text which forms a description for the navigation tab or navigation page. This is used for administration purposes only. The attribute must reference an entry in the associated properties file.

**Related reference:**

“Tab navigation dynamic support” on page 164

The tab navigation bar and page group navigation bar support the ability to dynamically enable or disable, and hide or show, navigation tabs and navigation pages.

**Tab navigation loader-registry element:**

The loader-registry element defines a list of loader implementations that are used to dynamically enable or disable, and hide or show both the navigation pages and navigation tabs.

The following table shows the supported child elements of the loader-registry element.

Table 105. Supported child elements of the loader-registry element

Element	Description
loader	<i>1..n.</i>  Defines one or more loader implementations that will be used to dynamically set the visibility and enabled state of the navigation pages and navigation tabs.

**Related reference:**

“Tab navigation dynamic support” on page 164

The tab navigation bar and page group navigation bar support the ability to dynamically enable or disable, and hide or show, navigation tabs and navigation pages.

**Tab navigation loader element:**

The loader element defines a single loader implementation that will dynamically set the state of the navigation pages and navigation tabs.

The following table shows the attributes of the loader element.

*Table 106. Attributes of the loader element*

Attribute	Description
class	<i>Mandatory.</i>  The fully qualified class name of an implementation of the <code>curam.util.tab.impl.DynamicNavStateLoader</code> interface.

**Related reference:**

“Tab navigation dynamic support”

The tab navigation bar and page group navigation bar support the ability to dynamically enable or disable, and hide or show, navigation tabs and navigation pages.

**Tab navigation dynamic support**

The tab navigation bar and page group navigation bar support the ability to dynamically enable or disable, and hide or show, navigation tabs and navigation pages.

Dynamic support is implemented through a combination of the dynamic attribute of the navigation-page and navigation-group elements, the loader-registry element and a Java loader implementation.

The Java loader implementation registered in the menu configuration will be called when the tab is first loaded and based on the refresh options configured for a tab. The refresh options are configured in the tab configuration file (.tab).

A navigation tab and navigation page can be specified as dynamic in the navigation configuration file (.nav) by adding `dynamic="true"` to the relevant navigation-page or navigation-group elements.

Where a dynamic attribute is set, a loader-registry is then required and should define the fully qualified classname which implements the `curam.util.tab.impl.DynamicNavStateLoader` interface.

The `DynamicNavStateLoader` interface requires one method, `loadNavState`, to be implemented. The `loadMenuState` method is passed the following parameters:

- A list of navigation-group and navigation-page identifiers
- A set of name-value page parameters pairs

The loader implementation must decide which items to disable or hide. The method returns an object that represents the state of the navigation tabs and navigation pages. A state must be set for all identifiers in the list. For more information on this interface, consult the Java Documentation.

**Note:** The list of navigation identifiers passed to the `loadNavState` method are only those that have been identified as dynamic by the dynamic attribute on the navigation-page or navigation-group elements.

In addition, a navigation-page and navigation-group element cannot use the same identifier. The identifiers must be unique for all elements within the file.

**Related reference:**

“Tab tab-refresh element” on page 150

The tab-refresh element allows the tab actions menu, tab navigation and context

panel to be refreshed based on different events.

## Tab navigation example configuration file

An example tab navigation configuration file is provided.

The following example shows an example tab navigation configuration file named SimpleNavigation.nav.

```
<?xml version="1.0" encoding="UTF-8"?>
<nc:navigation
  id="SimpleNavigation"

  <nc:loader-registry>
    <nc:loader class="some.pkg.SimpleNavStateLoader"/>
  </nc:loader-registry>

  <nc:nodes>
    <nc:navigation-page id="Home"
      page-id="Home"
      title="Home.Title"/>

    <nc:navigation-group id="Background"
      title="Background.Title">
      <nc:navigation-page id="Addresses"
        page-id="ParticipantAddressList"
        title="Addresses.Title"/>
      <nc:navigation-page id="PhoneNumbers"
        page-id="ParticipantPhoneNumbers"
        title="Phone.Title"/>
    </nc:navigation-group>

    <nc:navigation-page id="Identity"
      title="Identity.Title"
      page-id="ParticipantIdentity"
      dynamic="true"/>
  </nc:nodes>
</nc:navigation>
```

Figure 58. SimpleNavigation.nav

The SimpleNavigation.nav should have a corresponding SimpleNavigation.properties file, which details the localizable content. For example:

```
Home.Title=Home
Background.Title=Background
Addresses.Title=Addresses
Phone.Title=Phone Numbers
Identity.Title=Identity
```

## Opening tabs and sections

You can open new sections and tabs by using several methods.

- A section can be opened directly by clicking the relevant section tab control.
- A tab can be opened directly by clicking the relevant tab control.
- Any link in the application has the potential to open a new tab.
- A section can be opened when a new tab is opened that is associated with any section except the current section.

Opening a section or tab by clicking the relevant tab control is straightforward. To open a tab that is already open, but not in focus, the tab control is selected and focus is given to the tab.

Opening a section by clicking the relevant section tab control will give focus to that section. Any tabs already open in that section will then be accessible.

When a section is opened (directly) for the first time, it may contain no tabs or may result in the automatic opening of a default tab, depending on the section configuration.

Opening a section or tab as a result of selecting a link is more complicated. When a link is selected, before the relevant UIM page is opened, the Cúram client will automatically determine if it should be opened in a new tab and if that tab should be opened in a new section. This is determined based a number of factors that will be detailed in the following sections.

### **Using links to open tabs and sections**

One of the actions that can trigger opening a new tab or new section is selecting a link to a UIM page. There are many different ways in the Cúram application to open a UIM page and many different contexts in which a UIM can be displayed.

A UIM page can be displayed in the following areas of an application:

- A content area
- A tab context panel
- A tab smart panel
- A modal dialog
- A list dropdown panel

A UIM page in any of these contexts can define links to another UIM page. There are different types of links:

- Page level actions menu (content area only)
- Modal button bar (modal dialog only)
- Buttons
- Hyperlinked text
- List actions menu

In addition to links on a UIM page, a UIM page can be opened via the following actions:

- Selecting an entry in the tab actions menu
- Selecting a link in the section shortcut panel
- Selecting a navigation bar tab
- Selecting a page group navigation bar entry

For more information on all the different types of action controls that can be defined in a UIM page, see the related link. For the purposes of this section, selecting a link will apply to any action that can open a new UIM page.

#### **Related reference:**

“UIM Reference” on page 52

Learn about the Cúram User Interface Meta-data (UIM) format used to specify the contents of the Cúram web application client pages.



## Page to tab and tab to section associations

A page is associated with a tab based on the navigation configuration for the tab. A tab is associated with a section through the section configuration file.

### Page to tab associations

The navigation for a tab is configured using the navigation element in the tab configuration file (.tab) and also, if defined, the navigation configuration file (.nav).

Where no tab navigation is defined for a tab, the navigation element defines a single UIM page (via the page-id attribute) that will result in opening the tab. A link to this page will open it in the relevant tab.

Where tab navigation is defined, any UIM page listed using a page-id attribute in the navigation configuration file (.nav) is considered to be associated with the tab. This means that a link to any of these referenced UIM pages will result in opening the relevant tab.

*The page to tab association must be unique. This means that a page can be referenced only once by the navigation configuration for a tab. As a result, a navigation configuration cannot be re-used across multiple tabs.*

There are a number of exceptions to this rule, but they are limited:

- The same UIM page can be referenced by more than one navigation configuration file (.nav), where the page is only ever linked-to from within the context of the tab.

This means that any links to the UIM page are always within the same tab. For example, a Notes UIM page is referenced by both the Person and Employer tabs. The only link to the Notes UIM page is from the page group navigation bar. The Notes UIM page is never referenced from a shortcut panel or linked by a UIM page that is not displayed within the context of the Employer or Person tabs.

- The same UIM page can be referenced by more than one navigation configuration for a tab, where the tabs are included in different application configurations (.app).
- A navigation configuration file (.nav) can be reused by two tabs, where the tabs are included in two different application configurations (.app).

**Resolve Pages:** Because of the way in which the Cúram client application handles resolve pages and opening new tabs, it is recommended not to use resolve pages in a navigation configuration. A resolve page is a specific type of UIM page that contains only a JSP\_SCRIPTLET element.

When a link to a resolve page is selected, the Cúram client recognises that it is a resolve page and executes the content of the JSP\_SCRIPTLET. The resulting UIM page that the JSP\_SCRIPTLET redirects to is then used to determine what tab the page should be opened in.

### Tab to section associations

A tab is associated with a section by listing it through the tab element in the section configuration file (.sec).

When a new tab is opened as a result of selecting a link, the tab is opened in the associated section and focus is given to that section and tab.

**Related reference:**

“Tab navigation” on page 160

The various UIM pages are grouped as part of a tab that can be navigated to within a tab. Tab navigation includes the Content Area Navigation Bar and the Page Group Navigation Bar components.

“JSP SCRIPTLET” on page 81

**Tab and section page parameters**

The client determines if a new tab is opened based on the page to tab to section association. In addition, existing open tabs, and values of the parameters that are passed to a tab, are also considered.

Two instances of the same tab can be opened, where each instance is identified by the page parameters that have been provided. For example, James Smith and Linda Smith are uniquely identified by their concern role ID. The concern role ID is defined as a page parameter for the Person tab.

When a link to James Smith is selected, a new tab is opened showing the details for James Smith. A subsequent link to Linda Smith is selected and a new instance of the same tab configuration is opened, displaying Linda Smiths details.

When a link is selected, the Cúram client application automatically determines what tab, and section, it is associated with. It then compares this information, along with the page parameters to determine what action to take.

The rules for opening tabs are detailed in the following table.

**Note:** The parameters passed when a link is selected must match the names of the page parameters defined in the tab configuration file.

Where not all required page parameters are provided, the behavior of those tabs within the application is not guaranteed. Any extra parameters provided will be ignored and not passed to the tab.

*Table 107. Tab Opening Rules*

Page to Tab Association	Page Parameter Values	Action
Page maps to current tab	Match	Page opens in current tab
Page maps to current tab	Differ	Page opens in new instance of tab
Page maps to existing open tab	Differ	Page opens in a new instance of existing tab
Page maps to existing open tab	Match	Page opens in existing tab
Page maps to new, unopened tab	N/A	Page opens in new tab

**Limitations:** There are a number of limitations and notes to be aware of when designing UIM pages to open in new tabs.

- Links in a modal dialog obey dialog rules first and only obey the rules for opening a tab when the dialog is closing.
- A link defined to open a modal dialog ignores the tab rules.
- Links in a tab navigation bar and page group navigation bar will always open within the context of the current tab.

- A submit link within the content area cannot open a new tab, even if the UIM page is configured to be associated with a different tab.
- If a UIM page is configured to be associated with a tab then the same page cannot be used as `INLINE_PAGE` in expandable lists.

### Tab ordering

A default tab ordering is configured in the application that applies when you open a new tab. You can change the default tab ordering.

The default behavior when opening a new tab in the application is that the tab opens at the end of the tab list. This behavior can be changed to open new tabs next to the tab where the request was made. This is known as tab ordering.

The Application property `curam.environment.enable.sequential.tabs` controls tab ordering. The default value for the tab ordering is set to false.

---

## Working with the Cúram user interface

Use this information to develop user interface elements with the Cúram Client Development Environment for Java. User interface elements that can be created with the Cúram Client Development Environment for Java include shortcut panels, tabs, modal dialogs, tab navigation, and lists.

The topics show how to create a simple client application, and then expand the application with more complex features.

### Related concepts:

“Cúram web client reference,” on page 1

Provides a reference for the Cúram web client application. The Cúram web client has an HTML user interface that is generated by a middle-tier web application. It conforms to the Java EE architecture and is driven by JavaServer pages and servlet technology that is based on the Apache Struts framework. This HTML user interface uses standard browser and Web 2.0 technologies, including JavaScript and cascading style sheets.

## Prerequisites for configuring the user interface

Before you start configuring the Cúram user interface, ensure that you have an understanding of the necessary development environments.

You must have an understanding of development using both the Cúram Client Development Environment for Java (CDEJ) and the Cúram Server Development Environment for Java (SDEJ).

In addition, it is useful to have a basic understanding of Java Platform, Enterprise Edition (Java EE) development environments, Extensible Markup Language (XML), and web technologies such as Hypertext Transfer Protocol (HTTP), JavaServer Pages (JSP), Cascading Style Sheets (CSS), and JavaScript.

It is assumed that the necessary steps to install the Cúram application and the related third-party tools have been completed.

## Creating a simple application

The topics in the following section describe how to create a simple application that has a single section and a single page of content.

The simple application contains the following items:

- Application name
- Application subtitle
- Welcome message
- Application menu
- Section
- Tab

After the Cúram application and the related third-party tools have been installed, two main projects are used for development, the EJBServer project and the webclient project. To create a simple application, you must create and modify files in the following directories:

- webclient\components\component-name\
- EJBServer\components\component-name\clientapps
- EJBServer\components\component-name\codetable
- EJBServer\components\component-name\Data\_Manager
- EJBServer\project\config

In each of the previous examples, *component-name* is the name of the custom component that is used to store customer-specific content to the Cúram application.

## Defining an application

Define a simple application that will contain a single section. An application is a particular view of the Cúram client that is defined for a specific user or role.

Define an application by using an XML configuration file with the extension .app. The .app files, are in the EJBServer\components\component-name\clientapps directory, where *component-name* is a custom component.

```
<?xml version="1.0" encoding="ISO-8859-1"?>
  id="SimpleApp"
  logo="SimpleApp.logo"
  title="SimpleApp.title"
  subtitle="SimpleApp.subtitle"
  user-message="SimpleApp.UserMessage">

  <ac:application-menu>
    <ac:preferences title="preferences.title"/>
    <ac:help title="help.title"/>
    <ac:logout title="logout.title"/>
  </ac:application-menu>

  <ac:section-ref id="SimpleAppHomeSection"/>
</ac:application>
```

Figure 59. SimpleApp app

The SimpleApp.app XML configuration file requires a corresponding SimpleApp.properties file that details the localizable content for the application, as shown in the following example:

```
SimpleApp.logo=CDEJ/themes/v6/images/application-logo.png
SimpleApp.title=C\u00F0Faram
SimpleApp.subtitle=Simple Application
SimpleApp.UserMessage=Welcome, %user-full-name
```

```
preferences.title=User Preference
help.title=Help
logout.title=Logout
```

The SimpleApp.app XML configuration file configures the following elements in the application banner of the application:

- An application name (title)
- An application subtitle (subtitle)
- A welcome message (user-message)
- An application menu (application-menu)

### Adding a section to an application

Add a section to an application, where an application can define between one and five sections. You can configure each section to display multiple object tabs.

The SimpleApp.app application file references one section by using the SimpleAppHomeSection id attribute. The id attribute refers to a section configuration file, which is an XML configuration file with the extension .sec. Similar to the SimpleApp.app file, you must add the .sec file to the EJBServer\components\component-name\clientapps directory, and the id attribute must match the name of the file.

The following figure shows an example section file, SimpleAppHomeSection.sec.

```
<?xml version="1.0" encoding="ISO-8859-1"?>
<sc:section
  id="SimpleAppHomeSection"
  title="Section.Home.Title"
  hide-tab-container="true">

  <sc:tab id="SimpleHome"/>

</sc:section>
```

Figure 60. SimpleAppHomeSection.sec

The SimpleAppHomeSection.sec file has a corresponding SimpleAppHomeSection.properties file that details the localizable content, for example:

```
Section.Home.Title=Home
```

The title attribute defines the name of the section tab. In addition, because only one tab is defined for the section, which is SimpleHome, the hide-tab-container attribute is used to hide the object tab bar.

### Adding a tab to a section

Add a tab to section, where a tab represents a business object, for example, a case or a participant. However, a tab can also represent a logical grouping of information.

The SimpleAppHomeSection.sec file references one tab by using the id SimpleHome. The id refers to a tab configuration file, which is an XML configuration file with the extension .tab. Similar to the .app and .sec files, the tab configuration file is

added to the EJBServer\components\component-name\clientapps directory. The id attribute must match the name of the file.

```
<?xml version="1.0" encoding="ISO-8859-1"?>
<tc:tab-config
  id="SimpleHome">

  <tc:context tab-name="home.tab.name"
    tab-title="home.tab.name"/>

  <tc:navigation page-id="SimpleHome"/>
</tc:tab-config>
```

Figure 61. SimpleHome.tab

The SimpleHome.tab file has a corresponding SimpleHome.properties file that details the localizable content, for example:

```
home.tab.name=Home
```

The tab-title attribute defines what is displayed on the tab title bar. As the object tab bar is turned off in the .sec file, the tab-name attribute is ignored.

SimpleHome.tab references a single UIM page by using the page-id attribute of the navigation element.

### Add a UIM page to a tab

Add a Cúram user interface meta-data (UIM) format page to a tab. In a UIM page, you define page content by using files that have the extension .uim. The .uim files are in the webclient\components\component-name directory.

The SimpleHome.tab file references the SimpleHome UIM page.

```
<?xml version="1.0" encoding="UTF-8"?>

<!-- This is a sample home page. -->
<PAGE PAGE_ID="SimpleHome">

  <PAGE_TITLE>
    <CONNECT><SOURCE NAME="TEXT"
      PROPERTY="PageTitle.StaticText"/>
    </CONNECT>
  </PAGE_TITLE>

</PAGE>
```

Figure 62. SimpleHome.uim

The SimpleHome.uim file has a corresponding SimpleHome.properties file that details the localizable content, for example:

```
PageTitle.StaticText=Simple Home
```

The SimpleHome.uim file defines a UIM page that has no main content and only a page title, PAGE\_TITLE. The content includes the following items that are common to most UIM pages:

- Tab title
- Page title
- Refresh button

- Print button
- Help button

## Associating a user with an application

After you create the content for a simple application, create and link a user to the application.

A user exists as an entry on the Users database tab. Create a user by using a dmx file and adding the file to the EJBServer\components\component-name\Data\_Manager directory.

```
<table name="USERS">
  ...
  <row>
    <attribute name="USERNAME">
      <value>simple</value>
    </attribute>
    ...
    <attribute name="ROLENAME">
      <value>SUPERROLE</value>
    </attribute>
    <attribute name="APPLICATIONCODE">
      <value>SimpleApp</value>
    </attribute>
    ...
    <attribute name="DEFAULTLOCALE">
      <value>en</value>
    </attribute>
    <attribute name="FIRSTNAME">
      <value>Simple</value>
    </attribute>
    <attribute name="SURNAME">
      <value>User</value>
    </attribute>
  </row>
</table>
```

Figure 63. Users.dmx

You must reference the Users.dmx file in the datamanager\_config.xml file that is in the EJBServer\project\config directory, for example:

```
<entry name="components/custom/Data_Manager/USERS.dmx"
  type="dmx" base="basedir"/>
```

When the entry is referenced from the Users.dmx file, it is included in the database when the **database** target is executed.

The previous Users.dmx file example shows the creation of a single user who is named simple with a password of password. The APPLICATIONCODE field links the user to a particular application by referencing a code table entry in the APPLICATION\_CODE code table. When a user logs on, the value of the APPLICATIONCODE field in the Users database table is used to determine both the application and the user's home page. The value of the code matches the name of the application .app file to use. The description of the code value indicates the name of the UIM page to be displayed as the home page. The home page is displayed when a user first logs on.

The following example shows a CT\_APPLICATION\_CODE.ctx file that is in the EJBServer\components\component-name\codetable directory:

```
<?xml version="1.0"?>
<codetables package="curam.util.testmodel.codetable">
  <codetable java_idenfifier="APPLICATION_CODE"
    name="APPLICATION_CODE">
    <code default="false" java_idenfifier="SIMPLE_HOME"
      status="ENABLED" value="SimpleApp">
      <locale language="en" sort_order="0">
        <description>SimpleHome</description>
        <annotation></annotation>
      </locale>
    </code>
  </codetable>
</codetables>
```

Figure 64. CT\_APPLICATION\_CODE.ctx

The example defines a SimpleApp code with a description of SimpleHome. The SimpleApp code matches the id of the SimpleApp.app application. The description, SimpleHome, maps to the SimpleHome.uim file.

### Build targets required to create a simple application

To create a simple application requires several files to be added and modified, which requires several build targets to be executed.

The following table summarizes the files that are added and modified when you create a simple application, and the build targets that process each of the files.

Table 108. Files required to create an application and corresponding build targets

File	Location	Build target
SimpleApp.app and associated properties file	EJBServer\components\ component-name\clientapps	inserttabconfiguration
SimpleAppHomeSection.sec and associated properties file	EJBServer\components\ component-name\clientapps	inserttabconfiguration
SimpleHome.tab and associated properties file	EJBServer\components\ component-name\clientapps	inserttabconfiguration
SimpleHome.uim and associated properties file	webclient\components\ component-name\	client
Users.dmx	EJBServer\components\ component-name\ Data_Manager	database
datamanager_config.xml	EJBServer\project\config	database
CT_APPLICATION_CODE.ctx	EJBServer\components\ component-name\codetable	server

**Note:** The **inserttabconfiguration** target is included in the **database** target.

After all build targets have been completed and the server and client applications have been started, the application can be accessed by using the following URL:

[http://localhost:9080/'server\\_name'/AppController.do](http://localhost:9080/'server_name'/AppController.do)

To view the simple application, log on as the simple user, with the password password.



## Adding a shortcut panel

Extend a simple application to include a new section that contains an example of a shortcut panel. A shortcut panel provides quick links to open content and to perform actions within the section.

The new section will be named Workspace and will contain the following items:

- Shortcut Panel
- Group Node
- Leaf Node
- Workspace Section
- Search Tab

## Adding a section

Add a section that includes a shortcut panel to a simple application.

The following example shows a simple app file that includes a workspace section in addition to a home section.

```
<ac:application
id="SimpleApp"
logo="SimpleApp.logo"
title="SimpleApp.title"
subtitle="SimpleApp.subtitle"
user-message="SimpleApp.UserMessage">

<ac:application-menu>
  <ac:preferences title="preferences.title"/>
  <ac:help title="help.title"/>
  <ac:logout title="logout.title"/>
</ac:application-menu>

<ac:section-ref id="SimpleAppHomeSection"/>
  <ac:section-ref id="SimpleAppWorkspaceSection"/>
</ac:application>
```

Figure 65. *SimpleApp.app*

The workspace section is defined in the `SimpleAppWorkspaceSection.sec` file, which defines a structure with two tabs. A shortcut panel has also been added to the section by including a `shortcut-panel-ref` element, as shown in the following example.

```
<sc:section
id="SimpleAppWorkspaceSection"
title="Section.Home.Title">

  <sc:shortcut-panel-ref id="SimpleShortcutPanel"/>

  <sc:tab id="SimpleSearch"/>
  <sc:tab id="SimplePerson"/>

</sc:section>
```

Figure 66. *SimpleAppWorkspaceSection.sec*

The corresponding `.properties` contains the localizable content for the section:

```
Section.Home.Title=Workspace
```

## Defining the contents of a section shortcut panel

A section shortcut panel provides quick links to open content and perform actions within the section. Users can expand and collapse the shortcut panel as required.

Configure the contents of a shortcut panel in an XML configuration file that has an extension of .ssp and a corresponding properties file. The following example shows an example SimpleShortcutPanel.ssp file:

```
<sc:section-shortcut-panel
  id="SimpleShortcutPanel"
  title="Panel.Title">
  <sc:nodes>
    <sc:node type="group" title="Group.Title" id="UI">
      <sc:node type="leaf" id="search" page-id="SimpleSearch"
        title="Link.Title.Search"/>
    </sc:node>
  </sc:nodes>
</sc:section-shortcut-panel>
```

Figure 67. SimpleShortcutPanel.ssp

The corresponding .properties contains the localizable content for the shortcut panel:

```
Panel.Title=Shortcuts
Group.Title=Quick Links
Link.Title.Search=Person Search
```

The structure of the section shortcut panel consists of nodes of two different types, which are group and leaf nodes. The type is configured through the type attribute. Group nodes allow for logical grouping of leaf nodes. Each leaf node represents a link that is displayed on the section shortcut panel.

Both group and leaf nodes have a title attribute that allows the configuration of the text to be displayed. Additionally, leaf nodes must specify a page-id attribute that configures the target page of the link.

The SimpleShortcutPanel.ssp file defines a group node and a leaf node, where the group node contains the leaf node that in turn contains a hyperlink to the search tab. Clicking the hyperlink link causes the search tab to be opened.

## Defining a search tab

Define a search tab in a section that contains a single page where users can search for a person.

The following example shows the configuration of the search tab in a section.

```
<tc:tab-config
  id="SimpleSearch">

  <tc:context tab-name="search.tab.name"
    tab-title="search.tab.title"/>
  <tc:navigation page-id="SimpleSearch"/>
</tc:tab-config>
```

Figure 68. SimpleSearch.tab

The corresponding .properties contains the localizable content for the tab:

```
search.tab.name=Search
search.tab.title=Person Search
```

### Define the Search Page:

The Person Search page has two distinct areas, a cluster that allows the user to enter search criteria and a list to display the results of a search.

Figure 69 shows a screen shot of the page to search a person (named as Person Search) below.




Figure 69. Person Search Page

1. Cluster
2. Action Control
3. List

The following is the UIM code for the page:

```

<PAGE PAGE_ID="SimpleSearch">

  <SERVER_INTERFACE NAME="ACTION" CLASS="PersonFacade"
    OPERATION="advancedSearch" PHASE="ACTION"/>

  <PAGE_TITLE>
    <CONNECT>
      <SOURCE NAME="TEXT"
        PROPERTY="PageTitle.StaticText"/>
    </CONNECT>
  </PAGE_TITLE>

  <CLUSTER TITLE="Cluster.Title.Search" NUM_COLS="2">
    <FIELD LABEL="Field.Label.LastName">
      <CONNECT>
        <TARGET NAME="ACTION" PROPERTY="key$dtls$lastName"/>
      </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Label.Gender">
      <CONNECT>
        <TARGET NAME="ACTION" PROPERTY="key$dtls$gender"/>
      </CONNECT>
    </FIELD>
    <ACTION_SET TOP="false">
      <ACTION_CONTROL LABEL="Control.Label.Search"
        TYPE="SUBMIT">
        <LINK PAGE_ID="THIS"/>
      </ACTION_CONTROL>
    </ACTION_SET>
  </CLUSTER>

  <LIST TITLE="List.Title.Results">
    <CONTAINER LABEL="Container.Label.Actions">
      <ACTION_CONTROL LABEL="Control.Label.View">
        <LINK PAGE_ID="SimplePerson">
          <CONNECT>
            <SOURCE NAME="ACTION" PROPERTY="personID"/>
            <TARGET NAME="PAGE" PROPERTY="personID"/>
          </CONNECT>
        </LINK>
      </ACTION_CONTROL>
    </CONTAINER>
    <FIELD LABEL="Field.Label.FirstName">
      <CONNECT>
        <SOURCE NAME="ACTION" PROPERTY="firstName"/>
      </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Label.LastName">
      <CONNECT>
        <SOURCE NAME="ACTION"
          PROPERTY="result$dtls$dtls$lastName"/>
      </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Label.Title">
      <CONNECT>
        <SOURCE NAME="ACTION" PROPERTY="title"/>
      </CONNECT>
    </FIELD>
  </LIST>
</PAGE>

```

Figure 70. SimpleSearch.uim

The following are the main elements of note on this UIM page:

- The SERVER\_INTERFACE element defines which server interface method is called by the server when the form is submitted.

- The CLUSTER defines the cluster on the page that contains two fields that allow the user to enter the search criteria. These are mapped to the input parameters of the server interface method. Refer to User Interface Element 1 in Figure 69 on page 177.
- An ACTION\_CONTROL element defines the action control on the page that allows the search to be submitted. Refer to User Interface Element 2 in Figure 69 on page 177.
- The LIST defines the list on the page that contains the results of a submitted search. For each result a row is displayed which displays the person's details, and an ACTION\_CONTROL which defines a link to that person's home page. Refer to User Interface Element 3 in Figure 69 on page 177. Selecting this link will open the person tab which will be defined next.

The corresponding .properties should contain the localizable content for the search page:

```
PageTitle.StaticText=Person Search
```

```
Field.Label.FirstName=First Name
Field.Label.LastName=Last Name
Field.Label.Title=Title
Field.Label.Gender=Gender
Control.Label.View=View
```

```
Container.Label.Actions=Actions
```

```
Cluster.Title.Search=Search Criteria
List.Title.Results=Results
Control.Label.Search=Search
```

## Build targets required to add a shortcut panel

To add a shortcut panel requires several files to be added and modified, which requires several build targets to be executed.

*Table 109. Files required to add a shortcut panel and corresponding build targets*

File	Location	Build target
SimpleApp.app and associated properties file	EJBServer\components\ <i>component-name</i> \clientapps	inserttabconfiguration
SimpleWorkspaceSection.sec and associated properties file	EJBServer\components\ <i>component-name</i> \clientapps	inserttabconfiguration
SimpleSearch.tab and associated properties file	EJBServer\components\ <i>component-name</i> \clientapps	inserttabconfiguration
SimpleSearch.uim and associated properties file	webclient\components\ <i>component-name</i> \	client

## Adding tab content

Extend a simple application to add more complex structured tabs to a section, including a context panel and a content area.

In a section, configure a person tab that displays details about a person and whose content includes a context panel and a content area that displays a person page.

### Defining a person tab

A person tab contains a single page that displays the details of a person.

The following example shows the configuration of the person tab and the context panel. The configuration requires a parameter to be passed to the tab when it is opened, as defined by the page-param element.

```
<tc:tab-config>
  <tc:page-param name="personID"/>
  <tc:context page-id="SimplePersonContext"/>
  <tc:navigation page-id="SimplePerson"/>
</tc:tab-config>
```

*Figure 71. SimplePerson tab*

The corresponding .properties file contains the localizable content for the person tab:

```
no.property.required=true
```

### Defining a context panel:

A context panel is displayed at the top of the tab's content area and provides important contextual information. If configured, the context panel is always displayed regardless of the information that is displayed in the page below it.

Define a context panel by using a UIM page. Some limitations apply to the UIM that you can use. The following example shows the UIM code for the context panel that is defined in the person tab:

```
<PAGE PAGE_ID="SimplePersonContext" TYPE="DETAILS">

  <PAGE_TITLE>
    <CONNECT>
      <SOURCE NAME="TEXT"
        PROPERTY="PageTitle.StaticText"/>
    </CONNECT>
  </PAGE_TITLE>

  <TAB_NAME>
    <CONNECT>
      <SOURCE NAME="TEXT" PROPERTY="Tab.title"/>
    </CONNECT>
  </TAB_NAME>

  <PAGE_PARAMETER NAME="personID"/>

  <CLUSTER>
    <FIELD LABEL="Field.Label.ContextPanelFor">
      <CONNECT>
        <SOURCE NAME="PAGE" PROPERTY="personID"/>
      </CONNECT>
    </FIELD>
  </CLUSTER>

</PAGE>
```

*Figure 72. SimplePersonContext.uim*

Note the following elements and attributes in the example:

#### TYPE attribute

Can specify that a UIM page is intended as a context panel.

**TAB\_NAME element**

Defines the content that is used as the name of the tab.

**PAGE\_TITLE element**

Defines the tab title.

**PAGE\_PARAMETER element**

Must match the page-param value that is specified in the tab configuration.

In the example, the context panel contains only one single field that outputs the unique identifier of the person.

The corresponding .properties file contains the localizable content for the context panel:

```
PageTitle.StaticText=Person Context Panel  
Tab.title=Person Tab
```

```
Field.Label.ContextPanelFor=Context Panel for user with ID:
```

**Defining a person page:**

Configure a person page that is displayed in the content area of a person tab.

The following example shows the UIM that is required to display a person page in a person tab:

```

<PAGE PAGE_ID="SimplePerson">
  <PAGE_TITLE>
    <CONNECT>
      <SOURCE NAME="TEXT" PROPERTY="Page.Title"/>
    </CONNECT>
  </PAGE_TITLE>

  <PAGE_PARAMETER NAME="personID"/>

  <SERVER_INTERFACE NAME="DISPLAY"
    CLASS="PersonFacade"
    OPERATION="readPerson" />

  <CONNECT>
    <SOURCE NAME="PAGE" PROPERTY="personID"/>
    <TARGET NAME="DISPLAY" PROPERTY="key$personID"/>
  </CONNECT>

  <CLUSTER TITLE="Cluster.Title.Details" NUM_COLS="2">

    <FIELD LABEL="Field.Label.FirstName">
      <CONNECT>
        <SOURCE NAME="DISPLAY" PROPERTY="firstName"/>
      </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Label.LastName">
      <CONNECT>
        <SOURCE NAME="DISPLAY" PROPERTY="lastName"/>
      </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Label.Title">
      <CONNECT>
        <SOURCE NAME="DISPLAY" PROPERTY="title"/>
      </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Label.Gender">
      <CONNECT>
        <SOURCE NAME="DISPLAY" PROPERTY="gender"/>
      </CONNECT>
    </FIELD>
  </CLUSTER>
  <CLUSTER TITLE="Cluster.Title.ContactDetails" NUM_COLS="2">
    <FIELD LABEL="Field.Label.Email">
      <CONNECT>
        <SOURCE NAME="DISPLAY" PROPERTY="email"/>
      </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Label.PhoneNumber">
      <CONNECT>
        <SOURCE NAME="DISPLAY" PROPERTY="phoneNumber"/>
      </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Label.Address">
      <CONNECT>
        <SOURCE NAME="DISPLAY" PROPERTY="address"/>
      </CONNECT>
    </FIELD>
  </CLUSTER>
</PAGE>

```

Figure 73. SimplePerson uim

This UIM is similar to what has been previously defined.



The corresponding .properties should contain the localizable content for the page:

Page.Title=Person Home Page

Cluster.Title.Details=Details

Cluster.Title.ContactDetails=Contact Details

Field.Value.Welcome=Field Value

Field.Label.Welcome=Field Label

Field.Label.FirstName=First Name

Field.Label.LastName=Last Name

Field.Label.Title=Title

Field.Label.Gender=Gender

Field.Label.Email=Email

Field.Label.PhoneNumber=Phone Number

Field.Label.Address=Address

## Build targets required to add tab content

To add tab content requires several files to be added and modified, which requires several build targets to be executed.

Table 110. Files required to add tab content and corresponding build targets

File	Location	Build Target
SimpleSearch.tab and associated properties file	EJBServer\components\ <i>component-name</i> \clientapps	inserttabconfiguration
SimpleSearch.uim and associated properties file	webclient\components\ <i>component-name</i> \	client
SimplePerson.tab and associated properties file	EJBServer\components\ <i>component-name</i> \clientapps	inserttabconfiguration
SimpleContextPerson.uim and associated properties file	webclient\components\ <i>component-name</i> \	client
SimplePerson.uim and associated properties file	webclient\components\ <i>component-name</i> \	client

## Configuring modal dialogs

A modal dialog is a window that is displayed in the user interface where users can view or edit certain types of data in the application. Configure modal dialogs and the content that is displayed in them. You can also configure a wizard progress bar that displays a sequence of modal dialogs to create a wizard that can be used to edit more complex data or a larger set of data.

Modal dialogs are widely used for editing data in the Cúram application because they facilitate the transactional editing of data. The user is forced to either submit changes or cancel them, and ambiguity is avoided by preventing users from switching context while they configure a particular set of data.

The topics in this section demonstrate how to extend the application to add an employment history modal dialog for a person. The modal dialog will contain the following items:

- Title bar
- Close button
- Action controls

The user cannot switch focus back to the parent interface until the modal dialog is closed, either by submitting it or canceling it.

## Opening a modal dialog

Add page level action controls to a page that open modal dialogs.

For this example, the person page that was defined in “Defining a person page” on page 181 will be extended. The extended page will contain two action controls, one of which opens a basic modal dialog and another that opens a wizard progress bar.

The following example shows the extended SimplePerson.uim file.

```
<PAGE PAGE_ID="SimplePerson">

...
  <ACTION_SET>
    <ACTION_CONTROL LABEL="Control.Label.CreateEmployment">
      <LINK PAGE_ID="CreateEmployments" OPEN_MODAL="true">
        <CONNECT>
          <SOURCE NAME="PAGE" PROPERTY="personID"/>
          <TARGET NAME="PAGE" PROPERTY="personID"/>
        </CONNECT>
      </LINK>
    </ACTION_CONTROL>
    <ACTION_CONTROL LABEL="Control.Label.CreateEmploymentWizard">
      <LINK PAGE_ID="CreateEmploymentWizard_pageOne"
        OPEN_MODAL="true">
        <CONNECT>
          <SOURCE NAME="PAGE" PROPERTY="personID"/>
          <TARGET NAME="PAGE" PROPERTY="personID"/>
        </CONNECT>
      </LINK>
    </ACTION_CONTROL>
  </ACTION_SET>
  ...
</PAGE>
```

Figure 74. SimplePerson uim

The corresponding .properties file is extended to include the label properties for the action controls:

```
Control.Label.CreateEmployment=Add Employment History
Control.Label.CreateEmployment=Add Employment in Wizard
```

## Defining the content of the modal dialog

Define the content of a modal dialog. The content of a modal dialog is a standard UIM page, although it is styled differently when it is displayed by the browser.

The key features of the modal dialog that is defined in the following example are outlined in the following list:

- The title is displayed in the title bar of the window.
- The action controls are displayed in a bar at the bottom of the window.
- The user can click the close button on the title bar to close the window without submitting changes.

The following example shows the UIM code for the modal dialog:

```

<PAGE PAGE_ID="CreateEmployments" WINDOW_OPTIONS="width=250">

  <PAGE_TITLE>
    <CONNECT>
      <SOURCE NAME="TEXT" PROPERTY="Page.Title"/>
    </CONNECT>
  </PAGE_TITLE>

  <PAGE_PARAMETER NAME="personID"/>

  <CONNECT>
    <SOURCE NAME="PAGE" PROPERTY="personID"/>
    <TARGET NAME="ACTION" PROPERTY="personID"/>
  </CONNECT>

  <SERVER_INTERFACE NAME="ACTION"
    CLASS="EmploymentFacade"
    OPERATION="createEmployment"
    PHASE="ACTION"/>

  <CLUSTER TITLE="Cluster.Title.Details" NUM_COLS="2">
    <FIELD LABEL="Field.Label.EmployerName">
      <CONNECT>
        <TARGET NAME="ACTION" PROPERTY="employerName"/>
      </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Label.JobTitle">
      <CONNECT>
        <TARGET NAME="ACTION" PROPERTY="jobTitle"/>
      </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Label.FromDate">
      <CONNECT>
        <TARGET NAME="ACTION" PROPERTY="fromDate"/>
      </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Label.ToDate">
      <CONNECT>
        <TARGET NAME="ACTION" PROPERTY="toDate"/>
      </CONNECT>
    </FIELD>
  </CLUSTER>

  <ACTION_SET TOP="false">
    <ACTION_CONTROL LABEL="Control.Label.Save" TYPE="SUBMIT">
    <ACTION_CONTROL LABEL="Control.Label.Cancel" TYPE="SUBMIT"/>
  </ACTION_SET>

</PAGE>

```

*Figure 75. CreateEmployments.uim*

Note the WINDOW\_OPTIONS attribute of the PAGE element. In the example, the width is set to 250. Because the height is not set, it is automatically calculated when the dialog is displayed.

The corresponding .properties file contains the localizable content for the modal dialog:

```

Page.Title=Create Employment
Cluster.Title.Details=Details
Field.Value.Welcome=Here's the details panel for a person

Control.Label.Save=Save
Control.Label.Cancel=Cancel

Field.Label.PersonID=Person ID
Field.Label.EmployerName=Employer Name
Field.Label.JobTitle=Job Title
Field.Label.FromDate=From
Field.Label.ToDate=To

```

## Adding a wizard progress bar

In scenarios where users need to edit a more complex set of data or a larger set of data, you might want to split the data modifications over several windows. In the Cúram application, you configure a wizard progress bar to create a wizard.

A modal dialog that is configured within a wizard includes the following items:

### Wizard progress bar

Indicates the sequence of pages in the wizard, and highlights the current page in the sequence.

### Step title

Indicates the title of the current page in the sequence.

### Step description

Describes the content of the current page.

To illustrate the use of a wizard, the example in this section shows how to add an employment history to the application by splitting the data entry over a sequence of two pages.

## Defining the wizard progress bar configuration file:

Define the wizard configuration in the CreateEmploymentWizard.properties file

The following example shows the configuration file for the wizard progress bar. The wizard has two pages and the configuration specifies the text that is displayed in the progress bar, the step title, and the step description for each page.

```

Number.Wizard.Pages=2

CreateEmploymentWizard_pageOne.Wizard.Item.Text=Employer Details
CreateEmploymentWizard_pageOne.Wizard.Page.Title=
  Step 1: Employer Details
CreateEmploymentWizard_pageOne.Wizard.Page.Desc=
  Capture some details about Employer
Wizard.PageID.1=CreateEmploymentWizard_pageOne

CreateEmploymentWizard_pageTwo.Wizard.Item.Text=Employment Dates
CreateEmploymentWizard_pageTwo.Wizard.Page.Title=Step 2:
  Employment Period
CreateEmploymentWizard_pageTwo.Wizard.Page.Desc=
  Record the time person worked for employer
Wizard.PageID.2=CreateEmploymentWizard_pageTwo

```

*Figure 76. CreateEmploymentWizard.properties*

To load the wizard configuration file into the data, add the following lines to the AppResource.dmx file:

```
<row>
  <attribute name="resourceid">
    <value>1</value>
  </attribute>
  <attribute name="localeIdentifier">
    <value/>
  </attribute>
  <attribute name="name">
    <value>CreateEmploymentWizard</value>
  </attribute>
  <attribute name="contentType">
    <value>text/plain</value>
  </attribute>
  <attribute name="contentDisposition">
    <value>inline</value>
  </attribute>
  <attribute name="content">
    <value>./blob/CreateEmploymentWizard.properties</value>
  </attribute>
  <attribute name="internal">
    <value>1</value>
  </attribute>
  <attribute name="lastWritten">
    <value>2008-06-13-19.29.40</value>
  </attribute>
  <attribute name="versionNo">
    <value>1</value>
  </attribute>
  <attribute name="category">
    <value>RS_PROP</value>
  </attribute>
</row>
```

### Defining wizard pages:

An example shows how to configure a UIM file to define the content of a wizard for adding employment history for a person. The wizard contains two pages, where the first page requires the user to enter employer details and the second page requires the user to enter dates.

The following example shows the UIM that implements the first page of the wizard:

```

<PAGE PAGE_ID="CreateEmploymentWizard_pageOne">

  <MENU MODE="WIZARD_PROGRESS_BAR">
    <CONNECT>
      <SOURCE NAME="CONSTANT" PROPERTY="Wizard" />
    </CONNECT>
  </MENU>

  <SERVER_INTERFACE NAME="ACTION" CLASS="EmploymentFacade"
    OPERATION="validateEmployerAndJobTitle" PHASE="ACTION"/>

  <PAGE_TITLE>
    <CONNECT>
      <SOURCE NAME="TEXT" PROPERTY="Page.Title"/>
    </CONNECT>
  </PAGE_TITLE>

  <CONNECT>
    <SOURCE NAME="PAGE" PROPERTY="personID"/>
    <TARGET NAME="ACTION" PROPERTY="personID"/>
  </CONNECT>

  <PAGE_PARAMETER NAME="personID"/>

  <CLUSTER TITLE="Cluster.Title.Details">
    <FIELD LABEL="Field.Label.EmployerName">
      <CONNECT>
        <TARGET NAME="ACTION" PROPERTY="employerName"/>
      </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Label.JobTitle">
      <CONNECT>
        <TARGET NAME="ACTION" PROPERTY="jobTitle"/>
      </CONNECT>
    </FIELD>
  </CLUSTER>

  <ACTION_SET TOP="false">
    <ACTION_CONTROL LABEL="Control.Label.Next" TYPE="SUBMIT">
      <LINK PAGE_ID="CreateEmploymentWizard_pageTwo"
        DISMISS_MODAL="false">
        <CONNECT>
          <SOURCE NAME="ACTION" PROPERTY="personID"/>
          <TARGET NAME="PAGE" PROPERTY="personID"/>
        </CONNECT>
        <CONNECT>
          <SOURCE NAME="ACTION" PROPERTY="employerName"/>
          <TARGET NAME="PAGE" PROPERTY="employerName"/>
        </CONNECT>
        <CONNECT>
          <SOURCE NAME="ACTION" PROPERTY="jobTitle"/>
          <TARGET NAME="PAGE" PROPERTY="jobTitle"/>
        </CONNECT>
      </LINK>
    </ACTION_CONTROL>
  </ACTION_SET>
</PAGE>

```

Figure 77. CreateEmploymentWizard\_pageOne.uim

The wizard progress bar items are added to the page by including a MENU element with the attribute MODE="WIZARD\_PROGRESS\_BAR". The element references a property that is named Wizard, which is defined in the Constants.properties file as CreateEmploymentWizard. The Wizard property associates the page with the wizard progress bar configuration file that is loaded into the database.

The corresponding .properties file for the first page of the wizard includes the localizable content for the page:

```
Page.Title=Create Employment  
Cluster.Title.Details=Details
```

```
Control.Label.Next=Next
```

```
Field.Label.EmployerName=Employer Name  
Field.Label.JobTitle=Job Title
```

The following example shows the UIM that implements the second page of the wizard:

```

<PAGE PAGE_ID="CreateEmploymentWizard_pageTwo">

  <MENU MODE="WIZARD_PROGRESS_BAR">
    <CONNECT>
      <SOURCE NAME="CONSTANT" PROPERTY="Wizard" />
    </CONNECT>
  </MENU>

  <PAGE_TITLE>
    <CONNECT>
      <SOURCE NAME="TEXT" PROPERTY="Page.Title"/>
    </CONNECT>
  </PAGE_TITLE>

  <PAGE_PARAMETER NAME="personID"/>

  <CONNECT>
    <SOURCE NAME="PAGE" PROPERTY="personID"/>
    <TARGET NAME="ACTION" PROPERTY="personID"/>
  </CONNECT>

  <PAGE_PARAMETER NAME="employerName"/>

  <CONNECT>
    <SOURCE NAME="PAGE" PROPERTY="employerName"/>
    <TARGET NAME="ACTION" PROPERTY="employerName"/>
  </CONNECT>

  <PAGE_PARAMETER NAME="jobTitle"/>

  <CONNECT>
    <SOURCE NAME="PAGE" PROPERTY="jobTitle"/>
    <TARGET NAME="ACTION" PROPERTY="jobTitle"/>
  </CONNECT>

  <SERVER_INTERFACE NAME="ACTION" CLASS="EmploymentFacade"
    OPERATION="createEmployment" PHASE="ACTION"/>

  <CLUSTER TITLE="Cluster.Title.Details" NUM_COLS="2">

    <FIELD LABEL="Field.Label.FromDate">
      <CONNECT>
        <TARGET NAME="ACTION" PROPERTY="fromDate"/>
      </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Label.ToDate">
      <CONNECT>
        <TARGET NAME="ACTION" PROPERTY="toDate"/>
      </CONNECT>
    </FIELD>
  </CLUSTER>

  <ACTION_SET TOP="false">
    <ACTION_CONTROL LABEL="Control.Label.Save" TYPE="SUBMIT">
      <LINK PAGE_ID="Employments" DISMISS_MODAL="TRUE">
        <CONNECT>
          <SOURCE NAME="ACTION" PROPERTY="personID" />
          <TARGET NAME="PAGE" PROPERTY="personID"/>
        </CONNECT>
      </LINK>
    </ACTION_CONTROL>
  </ACTION_SET>

</PAGE>

```

Figure 78. CreateEmploymentWizard\_pageTwo.uim



The corresponding .properties file includes the localizable content for the page:

```
Page.Title=Create Employment
Cluster.Title.Details=Details
Control.Label.Save=Save
```

```
Field.Label.FromDate=From
Field.Label.ToDate=To
```

### Build targets required to add modals and wizard progress bars

To add modal dialogs and wizard progress bars requires several files to be added and modified, which requires several build targets to be executed.

*Table 111. Files required to add modal dialogs and corresponding build targets*

File	Location	Build target
SimplePerson.uim and associated properties file	webclient\components\ <i>component-name</i> \	client
CreateEmployments.uim and associated properties file	webclient\components\ <i>component-name</i> \	client
CreateEmployments Wizard_pageOne.uim and associated properties file	webclient\components\ <i>component-name</i> \	client
CreateEmployments Wizard_pageTwo.uim and associated properties file	webclient\components\ <i>component-name</i> \	client
CreateEmploymentsWizard .properties	EJBServer\components\ <i>component-name</i> \Data_Manager\scripts\blob	client
APPRESOURCES.DMX	EJBServer\components\ <i>component-name</i> \Data_Manager\scripts	client

## Adding tab navigation

Add navigation features to a tab. An example shows how to modify a person tab to include a navigation bar.

The modified person tab will contain a content area navigation bar within one navigation tab, and a page group navigation bar with two navigation pages.

### Defining a navigation bar

Configure a tab file to contain a navigation bar in the content area. Then, configure a nav file to include a navigation group with two navigation pages.

To configure a tab to contain a navigation bar in the content area, it is necessary to include the id of the navigation bar configuration in the navigation element of the tab.

The following example shows the modified version of a SimplePerson.tab file.

```

        <tc:tab-config
        id="SimplePerson">

<tc:page-param name="personID"/>

<tc:context page-id="SimplePersonContext" height="60"/>
        <tc:navigation id="SimplePersonNav"/>
    </tc:tab-config>

```

Figure 79. SimplePerson Tab

Define the navigation bar configuration by using an XML configuration file with the extension .nav. Similar to other tab configuration artifacts, the .nav files are in the EJBServer\components\component-name\clientapps directory, where component-name is a custom component.

The following example shows the contents of the SimplePersonNav.nav file. It defines one navigation group, with two navigation pages.

```

<nc:navigation id="SimplePersonNav">
    <nc:nodes>
        <nc:navigation-group id="PersonHome" title="PersonHome"
            description="Person Details Group">
            <nc:navigation-page id="SimplePerson" page-id="SimplePerson"
                title="PersonDetails.Title"/>
            <nc:navigation-page id="Employments" page-id="Employments"
                title="EmploymentHistory.Title"/>
        </nc:navigation-group>
    </nc:nodes>
</nc:navigation>

```

Figure 80. SimplePersonNav.nav

The corresponding .properties file contains the localizable content for the page:

```

PersonHome.Title=Person Home
EmploymentHistory.Title=Employment History
PersonDetails.Title=Person Details

```

## Build targets required to add tab navigation

To add a navigation bar to a tab requires several files to be added and modified, which requires several build targets to be executed.

Table 112. Files required to add tab navigation and corresponding build targets

File	Location	Build target
SimplePersonNav.nav and associated properties file	EJBServer\components\ component-name\clientapps	inserttabconfiguration
SimplePerson.tab and associated properties file	EJBServer\components\ component-name\clientapps	inserttabconfiguration

## Working with lists

Extend a person search page to add an expandable list and a list actions menu.

The examples in this section show how to add an expandable list and a list actions menu to the person search page that is defined in “Define the Search Page” on page 177.

## Defining an expandable list

Add an expandable list to a person search page. In an expandable list, users can see more information than is displayed in a simple list, without having to navigate away from the page that contains the list.

In an expandable list, expand each row by clicking a toggle control. In the expanded state, a page that is relevant to the row is displayed. Note the following key points:

- A toggle control is added to the start of each row that enables the row to be expanded and collapsed. It is possible to expand more than one row at a time and the size of the content area adjusts automatically.
- Page level action sets are displayed as buttons in a page.

The following SimpleSearch.uim example shows a person search page UIM file that has been modified to include an expandable list.

```
<PAGE PAGE_ID="SimpleSearch">

<SERVER_INTERFACE NAME="ACTION"
  CLASS="PersonFacade"
  OPERATION="advancedSearch"
  PHASE="ACTION"/>

...

<LIST TITLE="List.Title.Results">
  <DETAILS_ROW>
    <INLINE_PAGE PAGE_ID="SimplePerson">
      <CONNECT>
        <SOURCE NAME="ACTION" PROPERTY="personID"/>
        <TARGET NAME="PAGE" PROPERTY="personID"/>
      </CONNECT>
    </INLINE_PAGE>
  </DETAILS_ROW>
  ...
</LIST>
</PAGE>
```

Figure 81. SimpleSearch.uim

A new element, the DETAILS\_ROW, has been added to the LIST element. The DETAILS\_ROW element defines the inline page that is displayed when a row is expanded, including the parameters that are passed to the page for each row.

## Defining a list actions menu

Add a list actions menu to a person page. A list actions menu contains a set of actions that are associated with a particular row.

A list actions menu icon is displayed at the end of each row. Clicking the icon expands the list actions menu. The list actions menu contains one or more menu items, which are defined by action controls.

The following SimpleSearch.uim example shows a person search page UIM file that has been modified to include a list actions menu.

```

<PAGE PAGE_ID="SimpleSearch">

...

<LIST TITLE="List.Title.Results">

...
  <ACTION_SET TYPE="LIST_ROW_MENU">
    <ACTION_CONTROL LABEL="Control.Label.View">
      <LINK PAGE_ID="SimplePerson">
        <CONNECT>
          <SOURCE NAME="ACTION" PROPERTY="personID"/>
          <TARGET NAME="PAGE" PROPERTY="personID"/>
        </CONNECT>
      </LINK>
    </ACTION_CONTROL>

    <ACTION_CONTROL LABEL="Control.Label.CreateEmployment">
      <LINK PAGE_ID="CreateEmployments" OPEN_MODAL="true">
        <CONNECT>
          <SOURCE NAME="ACTION" PROPERTY="personID"/>
          <TARGET NAME="PAGE" PROPERTY="personID"/>
        </CONNECT>
      </LINK>
    </ACTION_CONTROL>
    <ACTION_CONTROL
      LABEL="Control.Label.CreateEmploymentWizard">
      <LINK PAGE_ID="CreateEmploymentWizard_pageOne"
        OPEN_MODAL="true">
        <CONNECT>
          <SOURCE NAME="ACTION" PROPERTY="personID"/>
          <TARGET NAME="PAGE" PROPERTY="personID"/>
        </CONNECT>
      </LINK>
    </ACTION_CONTROL>
  </ACTION_SET>

  <!-- Removing Actions Column -->
  <!--<CONTAINER LABEL="Container.Label.Actions">
    <ACTION_CONTROL LABEL="Control.Label.View">
      <LINK PAGE_ID="SimplePerson">
        <CONNECT>
          <SOURCE NAME="ACTION" PROPERTY="personID"/>
          <TARGET NAME="PAGE" PROPERTY="personID"/>
        </CONNECT>
      </LINK>
    </ACTION_CONTROL>
  </CONTAINER>-->
  ...

</LIST>
</PAGE>

```

Figure 82. SimpleSearch.uim

Note the following points:

- An ACTION\_SET that contains the three action controls has been added to the list.
- The attribute TYPE has been set to LIST\_ROW\_MENU to indicate that the action controls that are in this set are to be displayed on a list actions menu.
- Because the View action control has been added to the list actions menu, the column that contains it is no longer necessary, and therefore the corresponding UIM code has been commented out.

Localizable labels for the new action controls are in the corresponding .properties file content, for example:

```
Control.Label.CreateEmployment=Create Employment  
Control.Label.CreateEmploymentWizard=Create Employment Wizard
```

### Build targets required to add lists and list actions

To add and expandable list and list actions menu requires several files to be added and modified, which requires several build targets to be executed.

*Table 113. Files required to add an expandable list and a list actions menu, and corresponding build targets*

File	Location	Build target
SimpleSearch.uim and associated properties file	webclient\components\component-name\	client

---

## Session Management

Learn how browser sessions are handled in the Cúram application. A browser session can be defined as a continuous period of user activity in the web browser, where successive events are separated by no more than 30 minutes.

The following are common examples of when a Cúram browser session is started or finished:

- A session starts when a user first logs into the application.
- As long as the user is actively using the browser, the session remains active.  
If the browser is left inactive for a period of time, the session will timeout. In this case, the user will be required to log back in and a new session is started. The default timeout is 30 minutes, but this can be configured using the application server's configuration settings. See the *Cúram Deployment Guide* for more information on application server configuration.
- The user can explicitly logout, using the logout link in the application banner. The session is terminated in this case and logging back in will start a new one.
- The browser is shutdown and a new browser instance is started. In this case, a new session is started and the user will be required to log in.

## Session Overview

There is a maximum limit on the number of tabs that can be opened per section of an application. The system administrator can configure this limit by updating the `curam.environment.max.open.tabs` property in the system administration application. The default value for the maximum limit of open tabs per section of an application is set to fifteen.

If a user requests to open a tab and the number of open tabs reaches the maximum limit within the current section then an informational modal dialog will be displayed immediately after the tab is initially opened (before content in the tab is displayed). As instructed in this modal dialog, existing open tabs within the current section should be closed before any new tabs can be opened in an application. If the information displayed in the informational dialog is ignored and the user attempts to open more tabs within the current section of an application, the requested tabs will not be opened and an error modal dialog will be displayed instructing that new tabs can only be opened after existing open tabs within the

current section of the current application are closed. An error modal dialog can simply be dismissed by clicking on the button on the bottom of the dialog.

The message and title of both the dialog can be customized by customizing by adding the `GenericModalError.js.properties` file within the custom component. For more information on localizing JavaScript property files, consult “Java properties files” on page 44.

The text on the button can be customized by changing the value of the `Text.Ok` property in `CDEJResources.properties`. For more information on localizing `CDEJResources.properties`, please see “`CDEJResources.properties`” on page 51.

The current set of open tabs for a particular user is restored each time the user logs out of the application and logs back in. In addition, if the browser is refreshed (e.g. using the F5 button), the currently open tabs are also restored. There are two exceptions to this:

- If the the system administrator has decreased the maximum limit of tabs that can be opened within a section of an application since the termination of the last session then only the new maximum number of tabs within each section will be restored. An error dialog will be displayed informing the user that the maximum limit of open tabs has been exceeded.
- If the system administrator has updated the tab configuration to remove tabs from sections via the User Interface administration screens, then the removed tabs will not be restored.

The browser session plays an important role in the expected behavior when restoring tabs, and this chapter will detail how browser sessions interact with the restoration of tabs. In addition, a number of configuration options for the tab restoration feature are detailed.

## Tab Restoration

The list of currently open tabs per user is stored temporarily in the web tier, associated with the browser session, and more permanently on the database so that it can be restored after a user logs out of the application.

The data is persisted from the web tier to the database intermittently. As a result, there are cases where the last few changes to the open tabs may not be restored when the user logs in. This is most likely to happen where the session times out or the browser is restarted.

The behavior of tab restoration is different depending on whether it was the result of a browser refresh (F5) or the start of a new session (i.e. the user has logged in).

- **Browser Refresh**  
If the browser is refreshed, tabs are restored to their current state from the web tier session data, for the current user. No tab changes will be lost.
  - The tab that was last selected for the current user in the selected section will remain the selected tab.
  - The selected tab for the current user in other sections will revert to the first tab in those sections.
  - The expanded or collapsed states of the shortcut panel, smart panel and page contents for the current user are not restored.
- **New Session**

When a new session starts, usually requiring the user to login, the tabs are restored to their current state using the session data stored on the database.

- The “Home” tab is restored as the selected tab.
- The selected tab in other sections will revert to the first tab in those sections.
- The expanded or collapsed states of the shortcut panel, smart panel and page contents are not restored.
- If no previous tab session data is available, only the “Home” tab is opened.

**Note:** See “Direct browsing” on page 10 for a special case of tab restoration, where pages are directly accessed through the browser navigation bar.

## Session Configuration

Each time a new tab is opened, a tab is closed or the content area of a tab is updated, the information is stored in the web tier. The tab session data is persisted from the web tier to the database intermittently. How often the data is persisted can be configured using the following options, which can be set in the `ApplicationConfiguration.properties` file.

- **tabSessionUpdateCountThreshold**

Specifies the number of tab session data updates that must be received before the data is persisted from the web tier to the database. Once the threshold is reached, the recent updates are written and counting starts again from zero until the threshold is reached. A value of one causes writes on every update. A value of zero (or a negative or invalid value) disables writing based on update counts. The default is every 10 updates.

- **tabSessionUpdatePeriodThreshold**

Specifies the number of seconds that must have elapsed since the last time session data was persisted from the web tier to the database before a new update will trigger another write. A value of zero (or a negative or invalid value) disables writing based on update periods. The default value is 120 seconds, or 2 minutes.

The properties work together based on which value is reached first. In other words, if the update count threshold (`tabSessionUpdateCountThreshold`) is not reached, but the update period threshold (`tabSessionUpdatePeriodThreshold`) has been reached, a write will occur, and vice versa.

If the update count threshold is set to one, the update period threshold is ignored. The reason for this is that writes will happen on every update, so there is no need to write based on a time period.

**Note:** Tab session data is persisted to the database when the user logs out, regardless of the value of the current update count and update period. The exception to this is if both the update count threshold and the update period threshold are set to zero.

Each user account has one persistent tab session database record for an application. The same user logging in to the application from different browser sessions will cause some interference and unpredictability in what data is persisted across sessions.

The interference and unpredictability of the persisted data, when multiple users are using the same login ID, is most likely encountered in a testing environment. It is recommended that the `tabSessionUpdatePeriodThreshold` and

tabSessionUpdateCountThreshold properties are set to zero for testing environments to prevent this. Setting both properties to zero ensures that the tab session data is only persisted for the length of a browser session and not across sessions, i.e. login and logout.

It is also recommended that these settings are used where an "external" application is deployed and the external users all share the same generic user account.

## Session Timeout Warning

A browser session is timed from when data was most recently sent to or received from the server. In some cases, a user might enter much data into the application without realizing that the current session has timed out. When the user does initiate a server call, for example to submit the entered data, the browser prompts the user to reauthenticate to the application. Therefore, the user loses all the data that the user has entered into the application. To prevent users from losing data when their session times out, a system administrator can configure a session timeout warning.

Before a browser session times out, a session timeout warning dialog is displayed to users at a configured time. The dialog contains a timer that indicates the remaining period before the session times out. Users can either reset the session timeout and continue working in the application, or end the session and quit the application.

In IBM Cúram Social Program Management, the session timeout warning is enabled by default. Default configuration values are defined for the session timeout warning in properties.

### Session timeout warning default values

The session timeout warning uses default values that are defined in the ApplicationConfiguration.properties file and in the CDEJResources.properties file.

### CDEJ resources properties

You can configure the default values of the following properties that are defined in the CDEJResources.properties file:

#### **timeout.warning.modal.title**

Configures the title that is displayed on the timeout warning modal dialog. The default value is Timeout Warning.

#### **timeout.warning.modal.user.message**

Configures the message that is displayed to the user before the session expires. The default value is You will be timed out when the countdown reaches 0 seconds. Click Continue to resume using the application or Quit to exit.

#### **timeout.warning.modal.expired.user.message**

Configures the message that is displayed to the user after the session expires. The default value is You have been automatically timed out due to a period of inactivity on your account.

#### **timeout.warning.modal.continue.button**

Configures the text that is displayed on the **Continue** button in the modal dialog that is displayed to the user before the session expires. The default value is Continue.



**timeout.warning.modal.quit.button**

Configures the text that is displayed on the **Quit** button in the modal dialog that is displayed to the user before the session expires. The default value is **Quit**.

**Application configuration properties**

The following default values are defined in the `ApplicationConfiguration.properties` file:

**Session timeout warning modal width**

Configures the default width of the session timeout warning modal in pixels. The default value is 580. You can override the default property value only by customizing the timeout-warning element in an application.

**Session timeout warning modal height**

Configures the default height of the session timeout warning modal in pixels. The default value is 150. You can override the default property value only by customizing the timeout-warning element in an application.

**Default buffering period**

Configures the default buffering period in seconds to allow a server more time to respond to a client request over a slow network. The default value is 20. You cannot override the default property value.

**Customizing the session timeout warning in the caseworker application**

Customize the session timeout warning in the caseworker application by configuring system application properties, and CDEJ resource properties.

**About this task**

Settings that you customize in CDEJ properties apply to the whole of IBM Cúram Social Program Management.

If the timeout-warning element is configured for a specific application, the application configuration takes precedence over the corresponding values that are configured in the application configuration properties and the CDEJ properties.

To customize system application properties, do the following preliminary steps:

1. Log on to IBM Cúram Social Program Management as a system administrative user.
2. Click **System Configurations**.
3. In the Shortcuts panel, click **Application Data > Property Administration**.
4. Search for and edit each property that you want to configure.
5. To publish the property change, click **Publish**.

**Procedure****Application configuration properties**

- Customize the following application configuration properties for the session timeout warning as required:

**Enable or disable the session timeout warning**

Edit the `curam.environment.internal.enable.timeout.warning.modal` application configuration property. The property configures whether the

session timeout warning is displayed to users, A valid Boolean value is required, where the default value is true.

#### **Customize the session timeout warning notice period**

Edit the **curam.environment.internal.timeout.warning.modal.time** application configuration property. The property configures the notice period that users are given in seconds, through the display of the session timeout warning, that their browser session is about to time out. For example, if the default browser session length is 30 minutes, and the timeout attribute value is configured to 120, which corresponds to a value of 2 minutes, the session timeout warning is displayed after 28 minutes of inactivity. Then, users must click a button in the user interface to prevent the session from automatically timing out. A valid integer value is required, where the default value is 120.

#### **Customize the session expiry logout page**

Edit the **curam.environment.internal.timeout.warning.modal.logoutpage** application configuration property, where the default value is internal-logout-wrapper. The property configures the logout page that is displayed when a user's session expires and the user is automatically logged out. The property value must be a valid UIM page.

#### **CDEJ resource properties**

- Customize the following CDEJ resource properties for the session timeout warning as required:

##### **Customize the title on the session timeout warning modal dialog**

Edit the **timeout.warning.modal.title** CDEJ property. The property configures the title that is displayed on the timeout warning modal dialog. The default value is Timeout Warning.

##### **Customize the message in the session timeout warning modal dialog**

Edit the **timeout.warning.modal.user.message** CDEJ property. The property configures the message that is displayed to the user before the session expires. The default value is You will be timed out when the countdown reaches 0 seconds. Click Continue to resume using the application or Quit to exit.

##### **Customize the session expiry message**

Edit the **timeout.warning.modal.expired.user.message** CDEJ property. The property configures the message that is displayed to the user after the session expires. The default value is You have been automatically timed out due to a period of inactivity on your account.

##### **Customize the Continue button text in the session timeout warning modal dialog**

Edit the **timeout.warning.modal.continue.button** CDEJ property. The property configures the text that is displayed on the **Continue** button in the modal dialog that is displayed to the user before the session expires. The default value is Continue.

##### **Customize the Quit button text in the session timeout warning modal dialog**

Edit the **timeout.warning.modal.quit.button** CDEJ property. The property configures the text that is displayed on the **Quit** button in the modal dialog that is displayed to the user before the session expires. The default value is Quit.

## Customizing the session timeout warning in Universal Access

Customize the session timeout warning in Universal Access by configuring system application properties, and CDEJ resource properties.

### About this task

Settings that you customize in CDEJ properties apply to the whole of IBM Cúram Social Program Management.

If the timeout-warning element is configured for a specific application, the application configuration takes precedence over the corresponding values that are configured in the application configuration properties and the CDEJ properties.

To customize system application properties, do the following preliminary steps:

1. Log on to IBM Cúram Social Program Management as a system administrative user.
2. Click **System Configurations**.
3. In the Shortcuts panel, click **Application Data > Property Administration**.
4. Search for and edit each property that you want to configure.
5. To publish the property change, click **Publish**.

### Procedure

#### Application configuration properties

- Customize the following application configuration properties for the session timeout warning as required:

##### Enable or disable the session timeout warning

Edit the `curam.environment.enable.timeout.warning.modal` application configuration property. The property configures whether the session timeout warning is displayed to users. A valid Boolean value is required, where the default value is true.

##### Customize the session timeout warning notice period

Edit the `curam.environment.timeout.warning.modal.time` application configuration property. The property configures the notice period that users are given in seconds, through the display of the session timeout warning, that their browser session is about to time out. For example, if the default browser session length is 30 minutes, and the `timeout` attribute value is configured to 120, which corresponds to a value of 2 minutes, the session timeout warning is displayed after 28 minutes of inactivity. Then, users must click a button in the user interface to prevent the session from automatically timing out. A valid integer value is required, where the default value is 120.

##### Customize the session expiry logout page

Edit the `curam.environment.timeout.warning.modal.logoutpage` application configuration property, where the default value is `LogoutWrapper`. The property configures the logout page that is displayed when a user's session expires and the user is automatically logged out. The property value must be a valid UIM page.

#### CDEJ resource properties

- Customize the following CDEJ resource properties for the session timeout warning as required:

#### Customize the title on the session timeout warning modal dialog

Edit the **timeout.warning.modal.title** CDEJ property. The property configures the title that is displayed on the timeout warning modal dialog. The default value is Timeout Warning.

#### Customize the message in the session timeout warning modal dialog

Edit the **timeout.warning.modal.user.message** CDEJ property. The property configures the message that is displayed to the user before the session expires. The default value is You will be timed out when the countdown reaches 0 seconds. Click Continue to resume using the application or Quit to exit.

#### Customize the session expiry message

Edit the **timeout.warning.modal.expired.user.message** CDEJ property. The property configures the message that is displayed to the user after the session expires. The default value is You have been automatically timed out due to a period of inactivity on your account.

#### Customize the Continue button text in the session timeout warning modal dialog

Edit the **timeout.warning.modal.continue.button** CDEJ property. The property configures the text that is displayed on the **Continue** button in the modal dialog that is displayed to the user before the session expires. The default value is Continue.

#### Customize the Quit button text in the session timeout warning modal dialog

Edit the **timeout.warning.modal.quit.button** CDEJ property. The property configures the text that is displayed on the **Quit** button in the modal dialog that is displayed to the user before the session expires. The default value is Quit.

### Customizing the timeout warning in an application

You can configure the session timeout warning individually for each application by configuring the optional timeout-warning element.

#### About this task

Optionally, configure the timeout-warning element in the application configuration XML file, which has the extension .app. If you configure the timeout-warning element in the application, the values takes precedence over both the values that are configured in the system application configuration properties and the default values.

#### Procedure

- Configure the following attributes as required in an application's configuration file:

**title** Configures the title that is displayed on the timeout warning dialog.

**user-message**

Configures the message that is displayed to the user before the session expires.

**expired-user-message**

Configures the message that is displayed to the user after the session expires.

**quit-button**

Configures the text that is displayed on the **Quit** button in the modal dialog that is displayed to the user before the session expires.

**continue-button**

Configures the text that is displayed on the **Continue** button in the modal dialog that is displayed to the user before the session expires.

**timeout**

Configures the notice period that users are given in seconds, through the display of the session timeout warning, that their browser session is about to time out. For example, if the default browser session length is 30 minutes, and the `timeout` attribute value is configured to 120, which corresponds to a value of 2 minutes, the session timeout warning is displayed after 28 minutes of inactivity. Then, users must click a button in the user interface to prevent the session from automatically timing out.

**width** Configures the width of the session timeout warning modal in pixels.

**height** Configures the height of the session timeout warning modal in pixels.

- For an application in Universal Access, you can enable a specific logout page to be associated with the **Quit** button for a modal dialog. On the logout banner menu item that is on the person banner menu, you must set the `logout` attribute to `true`, as shown in the following example:

```
<ac:banner-menu type="person" title="person.title" page-id="somPageID"/>
<ac:menu-item id="logout" title="menu.logout.title" text="menu.logout.text"
page-id="LogoutWrapper" logout="true"/>
<ac:banner-menu/>
<ac:timeout-warning title="timeout.title"
user-message="timeout.user-message"
expired-user-message = "timeout.expired-message"
continue-button="timeout.continue"
quit-button="timeout.logout"
timeout="300"
width="650"
height="300"/>
```

**Example**

The following example demonstrates how to specify values for the `timeout-warning` attributes:

```
<ac:timeout-warning title="timeout.title"
user-message="timeout.user-message"
expired-user-message = "timeout.expired-message"
continue-button="timeout.continue"
quit-button="timeout.logout"
timeout="300"
width="580"
height="280"/>
```

**Configuring a customized logon page**

If a browser session times out because of no user interaction, users are redirected to an application logon page that is specified by the configuration properties. The logon page displays a session expiry message that tells users that they have been logged out because of a period of inactivity on their account.

**About this task**

In the configuration properties, you can specify the application logon page that is displayed both in the IBM Cúram Social Program Management application and in the Universal access application.

If the application is configured to display a customized logon page instead of the default page, then use the following procedure to insert a customized session expiry message into the customized logon page. If a user's session times out automatically, the customized session expiry message is then displayed in the customized logon page that the user is redirected to.

## Procedure

1. To configure the custom logon JSP page, do the following steps:
  - a. Import the class JSPUtil by using the following page directive:

```
<jsp:directive.page import="curam.util.client.jsp.JspUtil"/>
```
  - b. Insert the scriptlet to print the session expired message on the page:

```
<jsp:scriptlet>
  <![CDATA[ JspUtil. printSessionExpiredMessage(pageContext); ]]>
</jsp:scriptlet>
```
2. To configure the custom logon renderer class, do the following steps:
  - a. Create a div with a custom ID on your logon page to wrap the session expired message.
  - b. Call the following method and pass in the ID of the div as a parameter:

```
JspUtil.getSessionExpiredMessageScript(div.id);
```

## Tab Session Limitations

The tab session data records a limited number of tabs. The limit imposed relates to the total size of the tab session data and is approximately 70-80 tabs. Once this limit has been exceeded, tab session data is maintained only in the web tier and is no longer written to the database.

Restoration of the tab session when the browser is refreshed is not affected. However, if a user logs out with more tabs open than can be recorded for a session, only the state of the tabs at the time the limit was first exceeded will be restored.

Closing tabs will reduce the size of the tab session data and writing to the database will then resume as normal.

## Browser Specific Session Management

The version of the browser used can have an effect on when new sessions are started and when they are shared. Two browser instances that share the same session will result in the same set of open tabs displayed in both instances. This can cause similar interference and unpredictability of the persisted data as with two users using the same login ID from different machines.

**Example Session Issue:** A user logs into the Cúram application in one browser instance as the 'admin' user. They then open a new browser tab, which is sharing the same session. From here, they directly access the Cúram login page and login as a 'caseworker' user.

In this situation, the original browser tab still displays the tabs for the admin user. If the user performs a refresh in this original tab then the tabs and application view will be restored for the caseworker application. Alternatively, if the user opens new tabs that apply to the admin application only, these will not be persisted for the caseworker user.

Within the same browser session, a user must always logout to end the session and be able to login as a new user.

The most common browsers supported are Internet Explorer 7 and Internet Explorer 8 and they share sessions across browser instances in different ways:

- *Internet Explorer 7*

If a new browser instance, or browser tab, is opened in Internet Explorer 7 using the **File > New Tab** or **File > New Window** options, from an existing browser instance, the session is shared across the instances. This means that if the user was already logged into the Cúram application in the original browser instance, they will also be logged into Cúram in the new tab or window.

If a new browser instance is started using the Internet Explorer link in the **Start** menu, the sessions are not shared and the user must login again to Cúram.

- *Internet Explorer 8*

Sessions are always shared in Internet Explorer 8, no matter where the browser instance or tab was started from. This is the default behavior.

To start a new instance of the browser that does not share the existing session, the **File > New Session** option should be used.

For further information on browser specific behavior, please consult the relevant online documentation.

---

## Browser Management

Configure the browser that users use to view the IBM Cúram Social Program Management user interface. For example, notifications can alert users about when to upgrade their browser version. Notifications can request confirmation when a user attempts to leave the current page in a browser.

### Optimal Browser Support

Learn about optimal browser support and how to notify the user when they are using a sub-optimal browser with the Cúram application.

Users can be notified when they are not using the optimal version of a supported web browser. The user's web browser is considered sub-optimal if it is below the supported minimum version of the browser, or above the supported maximum version of the browser. The supported minimum/maximum version of a web browser is configurable. The out of the box settings for these versions of the web browser is in line with those supported by IBM for external applications.

**Note:** IBM Cúram external applications are public facing applications, where `mode="external"` is set in the application configuration file (\*.app). Health Care Reform and Universal Access are examples of this type of application.

This feature appears in the form of a message at the top of the banner, which can be dismissed. Once the optimal browser message is dismissed and if the browser is not updated, the message will be displayed again when a certain number of days have elapsed. This is assuming that the fully qualified URL to the application remains the same. An example of a fully qualified URL might be `https://myserver.ibm.com:9044/CitizenPortal/application.do`. The number of days that have elapsed before the next optimal browser check is configurable and by default it is sixty days in the future. The out of the box optimal browser message by default has a link to a website which assists the user to take action and update their version of the web browser to an optimal one.

The optimal browser message essentially has three components as follows:

- **Warning Icon**

The warning icon gets the attention of the user that they should update their web browser.

- **Optimal Browser Message Content**

The message content that will be displayed to the user. It will consist of plain text and optionally a hyperlink which directs the user to a website where they can take action to update their web browser. Please refer to “Text Configuration” on page 207 for more information on configuring the message content.

- **Optimal Browser Message Exit Icon**

Allows the user to dismiss the optimal browser message.

**Related reference:**

“Configuring the Application” on page 22

“CDEJResources.properties” on page 51

## **Feature Configuration**

All aspects of the optimal browser message feature, with the exception of the text, are configured in the `ApplicationConfiguration.properties` file. Please refer to “Text Configuration” on page 207 for how to configure the text associated with this feature.

The following properties within the `ApplicationConfiguration.properties` file can be used to configure whether the feature is enabled/disabled, and the number of days before the next optimal browser check will take place:

**`optimal.browser.detection.enabled`**

Example: `optimal.browser.detection.enabled=true`. This is an application wide setting. It allows this feature to be enabled or disabled. Valid values for this property are; “true”, and “false”. The default value is “false”.

**`optimal.browser.next.check`**

Example: `optimal.browser.next.check=20`. This property configures the number of days that will elapse before the next check is done to determine if a user's web browser is at an optimal level.

**Note:** This must be an integer value. It is recommended to use a value between 1 and 60 (inclusive). The default value is set to 60.

If this value is incorrectly configured it will be set to the default value. Additionally, an exception will be reported in the server logs when client side tracing is enabled. Please see “Tracing” on page 26 for more information on setting client side tracing. It should be noted that if this value is changed, it will not take effect until the optimal browser message is displayed again.

A number of properties within the `ApplicationConfiguration.properties` file are available to define what constitutes an optimal minimum and maximum browser for each supported web browser.

**Note:** The value of these properties must be an integer or double value, otherwise a default value of “0” will be set and the optimal browser feature will not work as expected when using the application in the associated web browser. An exception will be reported in the server logs if client side tracing is enabled.

The default value for each of these properties is in line with that supported by IBM for external applications.

The following are the properties that define what constitutes an optimal browser:

**`ie.min.version`**

Example: `ie.min.version=9`. This property is used to configure the minimum supported version of the Internet Explorer web browser. Any



version below this is not considered an optimal Internet Explorer web browser when using a IBM Cúram application.

**ie.max.version**

Example: `ie.max.version=11`. This property is used to configure the maximum supported version of the Internet Explorer web browser. Any version above this is not considered an optimal Internet Explorer web browser when using a IBM Cúram application.

**chrome.min.version**

Example: `chrome.min.version=29`. This property is used to configure the minimum supported version of the Chrome web browser. Any version below this is not considered an optimal Chrome browser when using a IBM Cúram application. The default value is set to zero because there is no minimum supported version for Chrome.

**chrome.max.version**

Example: `chrome.max.version=35`. This property is used to configure the maximum supported version of the Chrome web browser. Any version above this is not considered an optimal Chrome browser when using a IBM Cúram application. The default value is set to zero because there is no maximum supported version for Chrome.

**ff.min.version**

Example: `ff.min.version=18`. This property is used to configure the minimum supported version of the Firefox web browser. Any version below this is not considered an optimal Firefox browser when using a IBM Cúram application. The default value is set to zero because there is no minimum supported version for Firefox.

**ff.max.version**

Example: `ff.max.version=20`. This property is used to configure the maximum supported version of the Firefox web browser. Any version above this is not considered an optimal Firefox browser when using a IBM Cúram application. The default value is set to zero because there is no maximum supported version for Firefox.

**safari.min.version**

Example: `safari.min.version=5.0`. This property is used to configure the minimum supported version of the Safari web browser. Any version below this is not considered an optimal Safari browser when using a IBM Cúram application.

**safari.max.version**

Example: `safari.max.version=5.1`. This property is used to configure the maximum supported version of the Safari web browser. Any version above this is not considered an optimal Safari browser when using a IBM Cúram application.

## **Text Configuration**

The following properties can be used to configure the text associated with the optimal browser message:

**optimal.browser.msg.description**

Example: `optimal.browser.msg.description=optimal browser message banner`. This property configures the text for the description of the optimal browser support feature so that it can be read by the screen reader. A default value is provided.

**optimal.browser.msg.text**

Example: `optimal.browser.msg.text=For a better experience, please`

`{0.link:http://www.whatbrowser.org/}`update your browser`{0.end}`. This property configures content of the optimal browser message. The text between the `{0.link:}` and `{0.end}` mark-up tags configures the hyperlink and hyperlink text. These mark-up tags are optional. If they are omitted from the value of this property then the optimal browser message will be displayed as plain text. If the mark-up tags are included but not specified correctly, i.e. the specified hyperlink (URL) is not in the correct format or the format of the markup tags themselves are not correct, then the optimal message content will not be displayed as expected.

**optimal.browser.msg.info**

Example: `optimal.browser.msg.info=Rendering...` This property is used to configure the text while the optimal browser message is being rendered. A default value for this property is provided.

**optimal.browser.dismiss**

Example: `optimal.browser.dismiss=dismiss`. This property is used to configure the tooltip text associated with the button to dismiss the optimal browser message. A default value for this property is provided.

**optimal.browser.warning**

Example: `optimal.browser.warning=warning`. This property is used to configure the text for the warning icon so that it can be read by the screen reader. A default value for this property is provided.

## Configuring Browser Back, Refresh, and Close Button Behavior

The IBM Cúram Social Program Management application does not support using the browser back and refresh buttons to navigate the application. Also, if users click the close button to close the application, they might lose data. In both the caseworker user interface and the Universal Access user interface, if users click either the back, refresh, or close browser buttons, by default a warning message is displayed in a confirmation window. The warning message asks users whether they want to either stay on the page, or leave the page as requested. You can configure properties to either enable or disable the confirmation message from being displayed.

### Before you begin

You must log on to IBM Cúram Social Program Management as a system administrative user.

### About this task

Use the following procedure to either enable or disable confirmation messages from being displayed when users click either the back, refresh, or close browser buttons in either the caseworker user interface or the Universal Access user interface.

The content of the confirmation message depends on the browser, and cannot be customized.

**Note: Browser specific behavior**

**All browsers**

In all browsers, when a warning message confirmation window is displayed after clicking either the back, refresh, or close browser buttons, the following actions are recommended:

- If users click the back, refresh, or close button and a warning message confirmation window is displayed that asks users whether they want to leave the page, it is recommended that users do not click the **Leave** button. Clicking the **Leave** button causes unpredictable results that depend on the browser that is being used, and on where users are within the application. Instead, it is recommended that users click the **Stay** button in the warning message confirmation window.
- If users click the browser refresh button and a warning message confirmation window is displayed that asks users to confirm whether they want to reload the page, it is recommended that users do not click the **Reload** button. Clicking the **Reload** button causes unpredictable results that depend on the browser that is being used, and on where users are within the application. Instead, it is recommended that users click the **Don't Reload** button in the warning message confirmation window.

Users can then use the supported navigational options that are provided in the application to perform the wanted action.

### Chrome and Microsoft Edge

If you enable the confirmation message to be displayed, both Chrome and Microsoft Edge display an extra check box that users can select to stop the page from opening more message or confirmation windows. If users select the check box, the message or confirmation window is not displayed again when users click the back, refresh, or close buttons. It is recommended that users do not select the check box.

### Firefox

In Universal Access, if a user has not interacted with a page by clicking, touching, scrolling, or typing on the elements, the warning message is not displayed when the user clicks the **Back** button. In this case, data will not be lost if the user leaves the page.

### Procedure

1. Click **System Configurations**.
2. In the Shortcuts panel, click **Application Data > Property Administration**.
3. Choose one of the following options:
  - To enable or disable the confirmation window in the IBM Cúram Social Program Management user interface, search for and edit the value of the **curam.internal.app.guard.against.leaving** property.
  - To enable or disable the confirmation window in the Universal Access user interface, search for and edit the value of the **curam.app.guard.against.leaving** property.
4. To publish the property change, click **Publish**.

---

## Domain-Specific Controls

Learn about the domain-specific controls that are provided by the Cúram Client Development Environment (CDEJ). Domain-specific controls are employed to provide a more sophisticated interface for user information than the standard set of HTML controls.

Examples of domains that require sophisticated controls include dates, date-times, the meeting view, and the rules decision tree. Any Cúram User Interface Metadata (UIM) page that contains a server access bean with fields of this nature will have a web page generated containing a custom control appropriate to the type. For example, when a server bean contains the CALENDAR\_XML\_STRING domain, a calendar is generated that expects server information in a particular XML format. Each of the following sections details the custom controls converted for particular domains.

## Dates

Dates are mapped to the SVR\_DATE domain. Any server access bean that contains fields of this type shows a date selector to the user for data input. These selectors are HTML fields with an adjacent pop-up icon that causes a menu to be displayed allowing the user to select a date or date time with ease.

**Note:** This function is based on JavaScript and it is important that the user enable JavaScript in their browser for this selector to work. The appearance of the date selector pop-up can be altered by overriding its dedicated cascading stylesheet. For more information, see “Cascading Stylesheets” on page 33.

The initially configured date dialog has three input controls; a drop-down field for the month, a text input field for the year, and the days of the month are displayed so that a day can be selected. When the day of the month is selected, this selection populates the date field.

The date format string that is associated with date format validations are customizable in the file CDEJResources.properties and defined by the property `curam.validation.calendar.dateFormat`:

```
curam.validation.calendar.dateFormat=M/dd/yyyy
```

*Figure 83. Customizing the date format*

If this value is not set, the date format string will default to the date format setting that is specified in the `ApplicationConfiguration.properties` file.

### Three Field Date Selector

Dates can be mapped to the THREE\_FIELD\_DATE domain to enable use of an alternative date selector widget. Server access beans that contain fields of this type will display three drop-down elements to the user for data input.

The order of the drop-down elements and the display values of the month element reflect the date format, as configured by the `dateFormat` property in the `ApplicationConfiguration.properties` file. The day drop-down is populated with numbers that range 1 - 31. Validation at the infrastructure level prevents users from selecting an invalid date, for example, February 31, 2015. The year drop-down element is populated with values that start 100 years in the past to 30 years in the future. The range and order of the options are not configurable.

A selection from the drop-down elements is made either by scrolling to the wanted value or by typing the value when the drop-down element is active.

To use the Three Field Date Selector widget, model a property on a struct to use a data type derived from the THREE\_FIELD\_DATE domain.

## Date-Times

Date-times are mapped to the SVR\_DATETIME domain. Any server access bean that contains fields of this type will display a date selector (as described in the Dates topic) next to a time entry field.

Similar to the date selector, the pop-up here requires JavaScript to function correctly. An extra control exists for entering time as hours and minutes. It is displayed as two side-by-side drop-down lists for selecting the hour and minute values.

**Note:** The user needs to enable JavaScript in their browser for these selectors to work.

The date input field will not be displayed when the CURAM\_TIME domain (a descendant of the SVR\_DATETIME domain) is used,

The date time format string that is associated with date-time format validations are customizable in the file CDEJResources.properties and defined by the property `curam.validation.calendar.dateTimeFormat`:

```
curam.validation.calendar.dateTimeFormat=HH:mm
```

*Figure 84. Customizing the Date-Time format*

If this value is not set, the date time format string will default to HH mm ss.

### Related reference:

“Dates” on page 210

Dates are mapped to the SVR\_DATE domain. Any server access bean that contains fields of this type shows a date selector to the user for data input. These selectors are HTML fields with an adjacent pop-up icon that causes a menu to be displayed allowing the user to select a date or date time with ease.

## Representing Time-Only Values

As is described in related topics, Cúram has a base type for **date-only** and **date-time** values. No specific base type exists for **time-only** values.

A CURAM\_TIME domain is provided in the initial configuration of Cúram and this configuration is used by the client infrastructure to display a corresponding time-only widget. The widget also initiates certain processing when parsing and formatting values based on this domain. However, the underlying data representation is the same as for SVR\_DATETIME and when it is working with time-only domains the corresponding server-side code must ignore completely the date part of the value.

Because time-only domains are based on the SVR\_DATETIME domain, the default values also will be the same. The **zero date time** of 0001-01-01 00:00:00 is the value sent to the server if the field is left blank. If the field is set to 00:00, then 00:00 time value of today's date is sent.

The time input field that is rendered for CURAM\_TIME domain is an editable combination box as the following example shows. The time input field contains selectable time values for every 30 minutes. The exact time value also can be entered directly in the field.

The values to be selected are in the application-wide format set in `ApplicationConfiguration.properties`, including AM/PM for the 12-hour display. A manually typed value ends to follow the same format.

### Customizing the Time Format

The application-wide time format setting can be changed by setting or modifying the `timeformat` and `timeseparator` values in the `ApplicationConfiguration.properties` file

For more information, see “Configuring the Application” on page 22.

## Frequency Pattern Selector

In the frequency pattern selector pop-up, users can configure a frequency pattern; for example, daily, weekly, monthly, bi-monthly or yearly. Frequency patterns are mapped to the `FREQUENCY_PATTERN` domain. Any server access bean containing fields of this type will display a frequency pattern selector to the user for data input. These selectors are non editable HTML text fields with an adjacent pop-up icon which causes a pop-up menu to be displayed allowing the user to select a frequency pattern with ease.

Note that the functionality is based on JavaScript and it is important that the user have JavaScript enabled in their browser for this selector to work. The appearance of the frequency pattern selector pop-up can be altered by overriding its dedicated cascading stylesheet. See “Cascading Stylesheets” on page 33 for more details.

It is worth noting that the frequency pattern text selected varies in length, depending on the pattern selected. This makes the display of the selected pattern prone to re-sizing and wrapping, depending on the layout of the UIM page and the display space available.

## Selection Lists

Within the Cúram application, the use of the standard HTML selection list i.e. the `select` element is supported. Selection lists will truncate long data strings in order to preserve the correct page layout. To combat this, the data's full value is available as a tooltip for each item in the list. The list can be populated with data in a number of ways as described in the following sections.

### Populated from a Code-Table

If a `FIELD` has a target connection mapped to a property based on a code-table domain, a drop-down selection list will be displayed containing all code-table entries that are marked as “enabled”. The entries will be sorted alphabetically according to their code descriptions. This can be overridden by setting the “sort order” of each entry. Consult the *Cúram Server Developers Guide* for full details on creating code-tables in a Cúram application.

When the selection list is displayed the initially selected item is evaluated as follows:

1. The code value specified by the source connection of the field.
2. The default code of the code-table if the `FIELD` element's `USE_DEFAULT` attribute is not set to `false`.
3. The first item in the selection list, if no default code is defined or the default code is marked as “disabled”.
4. Blank, if the `FIELD` element's `USE_DEFAULT` attribute is set to `false`.

A drop-down selection list can also be displayed as a scrollable selection list where a number of entries are initially displayed instead of just one. To do this simply set the HEIGHT attribute of the FIELD element to a value greater than 1.

### Populated from Server Interface Properties

Data retrieved through server interface properties can also be used to populate a selection list. The INITIAL connection end-point is used in this case. The following are examples of a selection list on an insert and a modify page.

```
<FIELD LABEL="Field.Label">
  <CONNECT>
    <INITIAL NAME="DISPLAY" PROPERTY="personName"
      HIDDEN_PROPERTY="personID"/>
  </CONNECT>
  <CONNECT>
    <TARGET NAME="ACTION" PROPERTY="personID"/>
  </CONNECT>
</FIELD>
```

Figure 85. Selection List on an Insert Page

In this example the field has an INITIAL connection end-point to populate the selection list and a TARGET connection end-point to specify what field the selected value should be mapped to. The PROPERTY attribute of the INITIAL connection end-point is the list of values you want the user to see in the selection list. When the list is displayed, the first item in the list will initially be selected. The HIDDEN\_PROPERTY attribute specifies a list of corresponding values, when selected, will be mapped to the property specified in the TARGET connection end-point. The target property is a single field, *not* a list. In this example a list of people's names will be displayed but it is the selected person's unique ID that will be mapped to the target property. In certain circumstances the set of values visible to the user may also be what you want mapped to the target property. In this case do not use the HIDDEN\_PROPERTY attribute.

The following example shows the same selection list, but used on a modify page. The only difference is a SOURCE connection end-point is used to specify what is selected in the list when the page is first displayed.

```
<FIELD LABEL="Field.Label">
  <CONNECT>
    <INITIAL NAME="DISPLAY" PROPERTY="personName"
      HIDDEN_PROPERTY="personID"/>
  </CONNECT>
  <CONNECT>
    <SOURCE NAME="DISPLAY" PROPERTY="sourcePersonID" />
  </CONNECT>
  <CONNECT>
    <TARGET NAME="ACTION" PROPERTY="personID"/>
  </CONNECT>
</FIELD>
```

Figure 86. Selection List on a Modify Page

### Drop-down, Scrollable and Checkboxed List types

#### Drop-down and Scrollable List:

The selection list can be displayed as a drop-down list or as a scrollable selection list with a number of entries visible. A drop-down selection list is displayed by default. To change this to a scrollable selection list set the HEIGHT attribute of the FIELD element to a value greater than 1. The appearance of a selection list differs from a drop-down list in two noticeable ways. For a drop-down list only the

default value is displayed and all the other selectable values are displayed only when the drop down arrow is selected. Additionally the drop-down list is not scrollable. However, a scrollable selection list does not have the drop-down arrow, a subset of the values are initially displayed - the size of the subset is dependent on the value of the HEIGHT that is set. This list has a scrollbar which can be used to scroll the list, and view and select the remainder of the selectable values.

#### **Checkboxed List:**

Checkboxed selection list offers an alternative method of selecting individual entries, in this case using the check box control. This variation will be used if CONTROL attribute is set to CHECKBOXED\_LIST. It is just an alternative way of representation, so everything else applicable to Scrollable List applies for Checkboxed List without change.

#### **Adding an Empty Entry to a List for Non-Mandatory Fields**

Browsers will select the first item in a selection list by default if no item is marked as selected. In certain cases you may not want to “suggest” a value to the user. A blank entry would be more suitable. Set the USE\_BLANK attribute of the FIELD element to true to add a blank entry as the first item on the selection list.

#### **Enabling Multiple Selection**

Browsers allow multiple items to be selected in a selection list. To enable this first use a scrollable list as described above (you cannot select multiple items from a drop-down list). Then add the following to the curam-config.xml file.

```
<MULTIPLE_SELECT>
  <DOMAIN NAME="MY_DOMAIN" MULTIPLE="true"/>
</MULTIPLE_SELECT>a
```

*Figure 87. Enabling multiple selection in curam-config.xml*

For each domain which you want to enable multiple selection add a DOMAIN child element to the MULTIPLE\_SELECT element. If a FIELD has a target connection which is based on a domain listed in the MULTIPLE\_SELECT element, multiple selection will be enabled. When the form containing the selection list is submitted, the selected values will be packaged into a tab-delimited string. Therefore the target property must be based on a string domain. The same way, the source property in this case is also expected in the form of a tab-separated string of values to be selected initially (the values should match some of those specified via HIDDEN\_PROPERTY).

#### **Transfer List Widget**

##### **Overview:**

The Transfer List widget is a control used to facilitate multiple selections for a user (i.e. it is used as an alternative to an regular list which has multiple selection enabled). It consists of two HTML select controls placed side by side. The left control contains the items from which selections can be made (see See “Drop-down, Scrollable and Checkboxed List types” on page 213 for more details on selection lists.), the one to the right displays already selected items. Four buttons between the lists allow for selecting/de-selecting individual or all items (transferring them from one list to another and back as required).

##### **Configuration:**

The Transfer List widget is displayed instead of a regular HTML multiple selection control when configured in one of the two ways described below. In order for all multiple selection controls in an application to be displayed as Transfer List widgets, curam-config.xml should contain the TRANSFER\_LISTS\_MODE element with its value is set to true. Alternatively, individual multiple select controls might be



configured to be displayed that way by setting the CONTROL attribute on the appropriate UIM FIELD to be TRANSFER\_LIST. This setting is applicable just for fields rendered as multiple selection controls on the resulting UIM page and will be ignored in any other case.

The Transfer List widget requires the same data and the same configuration for enabling multiple selection as a regular selection list.

## User Preferences Editor

The User preferences editor allows a user to edit a user preference value for use anywhere within the application. For details on the definition of user preferences please consult the *Cúram Server Developers Guide*.

The editor may be accessed from the taskbar by clicking the preferences button. On clicking this button a popup window should be displayed with a list of all visible user preferences. Those preferences that are editable will appear as either a text field, radio buttons or a drop-down menu, depending on the type.

If the user wishes, they may edit the value of a preference and save the value using the Submit Changes link. When the user returns to the editor the updated values will appear. Any changes to user preferences using the editor will be applied immediately.

To return the values to those that were originally defined, the user should click the Reset to Default link. Selecting either of these buttons will close the popup window.

## Rules Trees

### Introduction

The RESULT\_TEXT domain contains information about the success or failure of a particular claim against a set of rules. When the server supplies this information it is translated into a tree view displaying all rules.

The RULES\_DEFINITION domain also produces a rules tree, in this case displayed with the rules editor. For more details on the rules editor see “Rules Editor” on page 220.

It is possible to use the FIELD element's CONTROL attribute to change the format of the rules display. The following sections will describe the various options for this attribute. Furthermore, the FIELD element's CONFIG attribute can be used to configure these rules trees.

### Behavior of Summary and Highlight-On-Failure Rules Flags:

The summary-flag has no effect in this view. All rules items are displayed.

The highlight-on-failure flag causes failed rules to be highlighted in a different color to those that have succeeded.

### Default Rules View

The default rules view of the rules tree, specified by setting the CONTROL attribute of the FIELD element to DEFAULT, shows data in an expanded tree view using standard HTML. This view should be visible in most standard web browsers. However, as the rules result is often quite verbose, the resulting output can be confusing to the viewer of your web page.

## Summary Rules View

To display a summary rules view, set the `CONTROL` attribute of the `FIELD` element to `SUMMARY`. The view of this tree is very similar to the default rules tree view except that the details about why a rule failed or succeeded are not displayed in the tree.

Any rules, regardless of type, marked as summary items are displayed. The following section, “Failed Rules View,” describes a similar view that only displays rules items whose type is explicitly set to rule. This view can be configured in the same manner as the dynamic rules view mentioned below. See “Dynamic Rules View.”

## Failed Rules View

To display a failed rules view, set the `CONTROL` attribute of the `FIELD` element to `FAILURE`. This view is similar in layout to the previously mentioned summary view. See “Summary Rules View”

Any rules whose type is rule (and not objective or rule group for example) and are marked as summary items are displayed. This view can be configured in the same manner as the dynamic rules view mentioned below. See “Dynamic Rules View”

## Dynamic Rules View

When the `CONTROL` attribute is set to `DYNAMIC`, this causes an expanding/contracting version of the decision to be displayed instead of a static tree. In this view the entire tree is not displayed. The view is “compressed” into multiple trees for each rules-item that has failed coupled with the “summary” flag on the item. See “Behavior of Summary and Highlight-On-Failure Indicator” on page 218 for more details on the summary flag. This is accomplished using scalable vector graphics (SVG) content displayed in the Adobe SVG Viewer instead of HTML. Refer to the *Cúram v6 Supported Prerequisites* document to see the supported version of this Web Browser Plugin.

Although the dynamic view requires an extra browser plug-in, it provides the user with a much more comprehensive and interactive view of the rules data. The rules tree is more comprehensively organized with a supplementary conjunction text displayed next to the rules.

There is no need to set a `HEIGHT` or `WIDTH` as the rules window resizes itself automatically. The developer is limited to two dynamic rules windows per page.

Localization of the text to display within the viewer is accomplished through JavaScript property files as described in “JavaScript Externalized Strings” on page 47. The name of these JavaScript property files should be `SVGText`. For example, `SVGText.js_es.properties` would be the name of the Spanish language version of `SVGText.js.properties` file.

All style information related to the dynamic rules widgets is held in a separate file called `curam_svg.css`. For further details see “Cascading Stylesheets” on page 33.

The developer can configure the rules tree using an XML configuration file. For all rules widgets based on the `RESULT_TEXT` domain this configuration is read from `RulesDecisionConfig.xml`. A version of this file should be in your components directory. This XML configuration file is merged during the build process in a similar method to other XML configuration files.

The CONFIG attribute of the FIELD displaying rules is used to specify an ID matching a CONFIG element in the RulesDecisionConfig.xml file. The following is a sample of a RulesDecisionConfig.xml file:

```
<RULES-CONFIG DEFAULT="default-config">
  <CONFIG ID="default-config" HYPERLINK-TEXT="false">
    <TYPE NAME="PRODUCT"
      SUCCESS-ICON="Images/product-16x16.gif"
      FAILURE-ICON="Images/productFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="ASSESSMENT"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="SUBRULESET"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="OBJECTIVE_GROUP"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="OBJECTIVE_LIST_GROUP"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="OBJECTIVE"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="RULE_GROUP"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="RULE_LIST_GROUP"
      SUCCESS-ICON="Images/rule-group-16x16.gif"
      FAILURE-ICON="Images/ruleGroupFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="RULE"
      SUCCESS-ICON="Images/rule-16x16.gif"
      FAILURE-ICON="Images/ruleFail.gif"/>
  </CONFIG>
  <CONFIG ID="Rules.Config.Core"
    HYPERLINK-TEXT="true"
    OPEN-NODE-PARAM="openNode"
    DECISION-ID-SOURCE="source-Decision-ID"
    DECISION-ID-TARGET="decision-ID">
    <TYPE NAME="PRODUCT" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="ASSESSMENT" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="SUBRULESET" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="OBJECTIVE_GROUP" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="OBJECTIVE_LIST_GROUP" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="OBJECTIVE" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="RULE_GROUP" />
    <TYPE NAME="RULE_LIST_GROUP" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="RULE" EDIT-PAGE="RulesResult"/>
  </CONFIG>
</RULES-CONFIG>
```

Figure 88. Sample RulesDecisionConfig.xml File

Note that the RULES-CONFIG root element only contains the DEFAULT attribute. This attribute is mandatory and should match an ID attribute value on a CONFIG element in this document. The default configuration contains the icon information as well

as the default nodes to link to if no configuration is required for a widget. These are covered by the SUCCESS-ICON, FAILURE-ICON, and EDIT-PAGE attributes respectively.

Each CONFIG element has a HYPERLINK-TEXT attribute which is used to specify whether the text next to a rules node in the widget is also to be used as a hyperlink to the link page set by the EDIT-PAGE for the TYPE in question.

Note that the CONFIG with the ID of value of Rules.Config.Core has the optional attribute OPEN-NODE-PARAM. This attribute is the name of a page parameter whose value is the ID of a node to open when the page is loaded. This configuration file is also used for configuration of the dynamic full tree rules view described in the next section.

The CONFIG attributes DECISION-ID-SOURCE and DECISION-ID-TARGET are used to identify a page parameter whose value will be the source for a new parameter (named by the DECISION-ID-TARGET) appended to each link on the widget. The above example will look for a page parameter called source-Decision-ID and pass on its value as a parameter to any links on the widget. This new value will be identified by a parameter named decision-ID.

The decision ID parameter may also be sourced from a field on a server bean instead of from a page parameter. This is achieved by adding DECISION-ID-SOURCE-BEAN and DECISION-ID-SOURCE-FIELD attributes to the CONFIG element instead of a DECISION-ID-SOURCE attribute. A validation error is thrown if all three are present. The DECISION-ID-SOURCE attribute should be the name of a bean on the page and the DECISION-ID-SOURCE-FIELD attribute should be the full name of a field providing the decision ID value. The following is an example of this configuration:

```
<CONFIG ID="Decision.ID.Bean.Source"
  HYPERLINK-TEXT="true"
  OPEN-NODE-PARAM="openNode"
  DECISION-ID-TARGET="decision-ID"
  DECISION-ID-SOURCE-BEAN="DISPLAY"
  DECISION-ID-SOURCE-FIELD="dtls$decision-ID">
  <TYPE NAME="PRODUCT" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="ASSESSMENT" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="SUBRULESET" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="OBJECTIVE_GROUP" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="OBJECTIVE_LIST_GROUP" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="OBJECTIVE" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="RULE_GROUP" EDIT-PAGE="RulesResult" />
  <TYPE NAME="RULE_LIST_GROUP" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="RULE" EDIT-PAGE="RulesResult"/>
</CONFIG>
```

*Figure 89. Example of Decision ID Sourced from a Bean*

#### **Behavior of Summary and Highlight-On-Failure Indicator:**

The highlight-on-failure indicator on a rules item does not have any effect in this view.

If an item fails and is marked as a summary item, this item should only be displayed as a separate tree if no item along its parent path (i.e. any group that contains it) has failed and is marked as a summary item. Consider the following tree of rule groups and rules and note the result and summary attributes on each item. Note that this is purely for illustrative purposes and does not represent the data-format created by the Rules Engine.

```

<decision>
  <rules-item id="B" type="rule-group"
    result="success" summary="true">
    <rules-item id="C" type="rule"
      result="success" summary="false" />
    <rules-item id="D" type="rule"
      result="fail" summary="true" />
  </rules-item>
  <rules-item id="E" type="rule-group"
    result="fail" summary="true">
    <rules-item id="F" type="rule"
      result="fail" summary="false" />
    <rules-item id="G" type="rule"
      result="success" summary="false" />
  </rules-item>
  <rules-item id="H" type="rule-group"
    result="success" summary="true">
    <rules-item id="I" type="rule"
      result="success" summary="true" />
    <rules-item id="J" type="rule"
      result="fail" summary="false" />
  </rules-item>
</decision>

```

*Figure 90. Example of Rules Tree Items with Summary Flag*

A rule that fails and is marked as "not a summary item" may still display as long as it is contained within another node that fails and has summary set to "true". A rule that fails and is marked as "not a summary item" will never display as the root of a tree in the dynamic rules view. So, the data above will result in separate "trees" as follows.

```

- D

- E
-- F
-- G

```

From the first rule-group "B", only the item "D" is displayed because it has failed and is marked as a summary item. It appears as a single-node tree.

The rule-group "E" is marked as a summary item and it has failed, therefore it and all its child nodes are displayed no matter what the success\failure status or summary flag on the child nodes is.

The entire rule-group "H" is filtered out. "H" itself, and "I" have succeeded and will not be displayed. Although "J" has failed it is not marked as a summary item and therefore is not displayed.

## Dynamic Full Tree Rules View

When the CONTROL attribute is set to DYNAMIC\_FULL\_TREE a view, similar in functionality to the dynamic rules view described in the previous section, is displayed. The main difference is that the entire rule set is displayed, similar to the default rules view, although the tree is interactive thus requiring the SVG viewer. There is no filtering of the display of rule groups in this view, potentially making it difficult to understand for someone who is not familiar with the rules engine. Configuration of this view is through the RulesDecisionConfig.xml file described in the previous section.

## Rules Editor

The RULES\_DEFINITION domain produces the rules editor. This control has a default HTML-only view or, if the FIELD's CONTROL attribute is set to DYNAMIC, an SVG view. See “Default Rules View” on page 215 and “Dynamic Rules View” on page 216 for more information.

This widget uses the CONFIG attribute to specify an ID attribute value matching the ID attribute value of a CONFIG element in the RulesEditorConfig.xml file. This XML configuration file is merged during the build process in a similar method to other XML configuration files. The following is a sample of RulesEditorConfig.xml:

```

<RULES-CONFIG DEFAULT="DefaultConfig">
  <CONFIG ID="DefaultConfig" HYPERLINK-TEXT="true">
    <TYPE NAME="Product"
      SUCCESS-ICON="Images/product-16x16.gif"
      FAILURE-ICON="Images/productFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="Assessment"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="SubRuleSet"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="ObjectiveGroup"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="ObjectiveListGroup"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="Objective"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="SubRuleSetLink"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="RuleGroup"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="RuleListGroup"
      SUCCESS-ICON="Images/rule-group-16x16.gif"
      FAILURE-ICON="Images/ruleGroupFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
    <TYPE NAME="Rule"
      SUCCESS-ICON="Images/rule-16x16.gif"
      FAILURE-ICON="Images/ruleFail.gif"/>
    <TYPE NAME="DataItemAssignment"
      SUCCESS-ICON="Images/default-16x16.gif"
      FAILURE-ICON="Images/defaultFail.gif"
      EDIT-PAGE="RatesNewColumn"/>
  </CONFIG>
  <CONFIG ID="Editor.Config"
    HYPERLINK-TEXT="true"
    OPEN-NODE-PARAM="openNode"
    DECISION-ID-SOURCE="source-Decision-ID"
    DECISION-ID-TARGET="decision-ID">
    <TYPE NAME="Product" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="Assessment" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="SubRuleSet" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="ObjectiveGroup" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="ObjectiveListGroup" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="Objective" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="SubRuleSetLink" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="RuleGroup" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="RuleListGroup" EDIT-PAGE="RulesResult"/>
    <TYPE NAME="Rule"/>
    <TYPE NAME="DataItemAssignment" EDIT-PAGE="RulesResult"/>
  </CONFIG>
</RULES-CONFIG>

```

Figure 91. Sample RulesEditorConfig.xml File

Note that the RULES-CONFIG root element only contains the DEFAULT attribute. This attribute is mandatory and should match an ID on a CONFIG element in this document. The default configuration contains the icon information as well as the default nodes to link to if no configuration is present for a widget. These are covered by the SUCCESS-ICON, FAILURE-ICON, and EDIT-PAGE attributes respectively.

Each CONFIG element has a HYPERLINK-TEXT attribute which is used to specify whether the text next to a rules node in the widget is also to be used as a hyperlink to the link page set by the EDIT-PAGE for the TYPE in question.

Note that the CONFIG with the ID of value of Editor.Config has the optional attribute OPEN-NODE-PARAM. This attribute is the name of a page parameter whose value is the ID of a node to open to when the page is opened.

The CONFIG attributes DECISION-ID-SOURCE and DECISION-ID-TARGET are used to identify a page parameter whose value will be the source for a new parameter (named by the DECISION-ID-TARGET) appended to each link on the widget. The above example will look for a page parameter called source-Dcision-ID and pass on its value as a parameter to any links on the widget. This new value will be identified by a parameter named decision-ID.

The decision ID parameter may also be sourced from a field on a server bean instead of from a page parameter. This is achieved by adding DECISION-ID-SOURCE-BEAN and DECISION-ID-SOURCE-FIELD attributes to the CONFIG element instead of a DECISION-ID-SOURCE attribute. A validation error is thrown if all three are present. The DECISION-ID-SOURCE attribute should be the name of a bean on the page and the DECISION-ID-SOURCE-FIELD attribute should be the full name of a field providing the decision ID value. The following is an example of this configuration:

```
<CONFIG ID="Decision.ID.Bean.Source"
  HYPERLINK-TEXT="true"
  OPEN-NODE-PARAM="openNode"
  DECISION-ID-TARGET="decision-ID"
  DECISION-ID-SOURCE-BEAN="DISPLAY"
  DECISION-ID-SOURCE-FIELD="dtls$decision-ID">
  <TYPE NAME="PRODUCT" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="ASSESSMENT" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="SUBRULESET" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="OBJECTIVE_GROUP" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="OBJECTIVE_LIST_GROUP" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="OBJECTIVE" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="RULE_GROUP" EDIT-PAGE="RulesResult" />
  <TYPE NAME="RULE_LIST_GROUP" EDIT-PAGE="RulesResult"/>
  <TYPE NAME="RULE" EDIT-PAGE="RulesResult"/>
</CONFIG>
```

*Figure 92. Example of Decision ID Sourced from a Bean*

## Meeting View

### Overview

The meeting view is a control that displays scheduling information in a chart format. It is associated with the USER\_DAILY\_SCHEDULE domain. The data to display in the meeting view is in XML format. Configuration settings for the meeting view must be in a file called MeetingViewConfig.xml in a component. The format for the XML data and configuration settings are described below. Finally, the control has two modes of operation: single and multiple selection.



## Single Selection Mode

In the single selection mode meeting view, the first column contains a list of users. The second column indicates the duration of the event to be scheduled. The third column displays the times during the day that the user is available or busy. The available times are hyperlinks that can be clicked to indicate the schedule the start time for the meeting. Note that any parameters passed to a page containing the meeting view will be included in any links within the view. Only start times that can accommodate the relevant meeting duration will be hyperlinks. For example, if John Smith is busy from 10:30 until 12:30, it is not possible to select 10:00 as the start time for a meeting with a duration of one hour and the 10:00 time slot will not be a hyperlink.

Note that any parameters passed to a page containing the meeting view will be included in any links within the view.

## Multiple Selection Mode

This view returns a tab-delimited list of the user IDs of selected rows. The meeting view widget in this mode is the same as that described above for the single selection mode except that it has an extra column which is inserted as the first column in the list and has a selectable checkbox for each list item. The users in this mode of widget are chosen by selecting their associated check boxes. Time slots are not hyperlinked and are for display only.

## XML Formats

The meeting view control expects information in a specific XML format. Below is an example of this:

```
<SCHEDULE MODE="Single|Multiple" TYPE="User"
  READ_ONLY="False" DATE="2003-30-10">
  <USER NAME="John Smith" ID="12345" DURATION="90">
    <BUSY START="2003-30-10 10:30:00" END="2003-30-10 12:30:00"/>
    <BUSY START="2003-30-10 15:45:00" END="2003-30-10 16:15:00"/>
  </USER>
  <USER NAME="James Smith" ID="12346" DURATION="90">
    <BUSY START="2003-30-10 12:30:00" END="2003-30-10 13:30:00"/>
    <BUSY START="2003-30-10 15:00:00" END="2003-30-10 18:15:00"/>
  </USER>
</SCHEDULE>
```

Note that in the format above: the MODE attribute is either Single or Multiple; the DURATION attribute is in minutes; START and END attributes are date-times in the format "yyyy-MM-dd HH:mm:ss". The READ\_ONLY attribute, if set to false, indicates that no time slot will be selectable as a hyperlink. The DATE attribute contains the date of the current scheduling and must be supplied. It should be in the format "yyyy-MM-dd". Finally, the TYPE attribute associates the schedule information with configuration settings which are also specified in an XML format as below:

```
<SCHEDULE_CONFIG>
  <CONFIG_TYPE="User" INTERVAL="15" START="08:00" END="16:00">
    <USER_HOME PAGE="PersonHome"
      ID_PARAM="UserID" NEW_WINDOW="True" />
    <NEW_EVENT PAGE="AddNewEvent" ID_PARAM="UserID"
      START_PARAM="start" END_PARAM="end" />
    <MULTI_SELECT PAGE="SelectedUsers"
      TAB_STRING_PARAM="selectedUsers"
      DATE_PARAM="eventDate" />
  </CONFIG>
</SCHEDULE_CONFIG>
```

Where INTERVAL is the duration in minutes of each segment of the time line. This can be 15, 30, or 60. Only these values are acceptable. The START and END attributes detail the beginning and end times of the time line. They are in the form “HH:mm”. Each CONFIG element can have the following sub-elements:

#### **USER\_HOME**

The PAGE attribute details which page to link to when clicking on the user's name. The ID\_PARAM attribute is the name of the parameter to supply with the user's ID as a value. NEW\_WINDOW attribute, true by default, specifies if the link opens in a new window or not.

#### **NEW\_EVENT**

The PAGE attribute details which page to link to when clicking on a time slot. The ID\_PARAM attribute is the name of the parameter to supply with the user's ID as a value. The START\_PARAM attribute is the name of the parameter to supply with the start time of the new event. Similarly, the END\_PARAM describes the name of the end time parameter. Both of these attributes will be in the current application's date-time format.

#### **MULTI\_SELECT**

The PAGE attribute details which page to link to when the submit button on the multi-select view is pressed. TAB\_STRING\_PARAM is the name of the link parameter to supply containing the tab-delimited string of selected users. DATE\_PARAM is the name of another link parameter containing the date of the event in question. The date value is taken from the value of the DATE attribute on the SCHEDULE element.

## **Charts**

### **Overview**

Charts are displayed when one of the domains of CHART\_XML, LINE\_CHART\_XML, PIE\_CHART\_XML or BARCHART\_XML domains (or any derivation of them) is used as the source of a field.

**Note:** Charts are rendered in the browser using Adobe Flex technology, which requires Adobe Flash Player. Refer to the *Cúram Third-Party Tools Installation Guide for Windows* document to see the supported version of Adobe Flash Player.

### **Chart appearance**

A bar chart displays a number of rows horizontally with a horizontal and vertical axis. Each row represents a unit of information comprised of a caption and a stack of differently colored bars of variable length. Their length represents the quantity of the unit in question and can be ascertained using the numbered marks on the horizontal axis, or a data tip which is available when you hover over the unit, as described below. The chart scale is chosen to fit the biggest stack of bars (this might be overridden by a configuration setting). Each bar is a hyperlink to a page containing further information. The vertical axis of this chart displays captions, describing each bar stack category. Captions might be dates, date ranges or textual values. They are optionally rendered as hyperlinks leading to pages with additional information, in which case captions are additionally visually indicated when hovered over. Both bar links and caption links are configurable, as described in “Chart configuration” on page 225.

Textual captions might get longer than one line. In such a case long captions are wrapped within the category segment. If a caption text exceeds two lines, though, it is truncated at that point and an additional tool tip with the full label text is displayed when such a label is hovered over.

Both bar links and caption links are configurable, as described in “Chart configuration.”

A column chart is similar to the bar chart and configurable the same way, except that units of information are displayed in column stacks rather than bars, and axes are interchanged accordingly. It is also possible to configure a column chart so that it has a legend that describes what each of the possible shaded areas in a column represents. The user can hover over a shaded area in a column, which displays what it represents when mapped to an entry in the legend.

Another way of presenting chart information is to use a line chart. In this chart, information is rendered as points in each category group, with points of the same type joined by straight lines (e.g. to represent data changes over time). Line charts differ from bar and column charts in that neither the points nor lines are currently hyperlinks. The same applies to line chart captions.

The last available chart type is a pie chart. Charts of this type are typically used to illustrate relative magnitudes, frequencies or percentages. The arc length of each sector is proportional to the quantity it represents. Together, the sectors create a full disk. Pie charts use callout-like labels, which provide details of the item represented by a sector and its percentage in the pie. Sectors are rendered as hyperlinks, leading to pages with additional information; however, chart labels are not currently available as hyperlinks.

By default, charts are displayed without a legend so that all the available space can be dedicated to the chart itself. However, charts can be configured to include a legend which shows extra information on what is represented by the elements of the chart.

Data tips are displayed on a chart when you hover the mouse over a particular chart data element. Data tips are shown regardless of whether a legend is included or not.

- The data tip for bar and column charts shows absolute and relative quantitative information attributed to the element and the element stack, the category (group) to which that element belongs and the type of the element (corresponding to an entry in the legend, if present).
- As line charts are not stacked, relative quantity information is not shown in their data tips; line chart data tips are also displayed only when the mouse is over a data point and not over a line.
- For a pie chart, a data tip displays absolute quantitative information for the particular sector and the percentage of the sector within the disk.

**Note:** Line charts always display a legend and this is currently not configurable.

## Chart configuration

Various aspects of charts can be configured. This is accomplished by setting the CONFIG attribute on the UIM field in question. The appropriate XML configuration file must contain a configuration section with a unique identifier matching the text in the CONFIG attribute.

All the necessary chart configuration files are to be in your component directory.

Different types of charts are currently configured in separate configuration files:

- Bar charts and column charts both use ChartConfig.xml and are also backward compatible with the previous configuration file version, BarChartConfig.xml

(data is taken from whichever of those two files contains a configuration with the required ID; if configurations with the same ID exist in both files, the one found in ChartConfig.xml takes precedence).

- LineChartConfig.xml configuration file is used to look for line chart configuration data.
- Pie chart configuration data is to be placed into file PieChartConfig.xml

The following is a sample of a chart configuration file:

```
<CHART-CONFIG>
  <CONFIG ID="Column.Chart.Config" ORIENTATION="VERTICAL"
    X_AXIS_LABEL="Vert.BarChart.X-Axis"
    Y_AXIS_LABEL="Vert.BarChart.Y-Axis">
    <LEGEND CODETABLE="Attendance">
      <ITEM CODE="CR1"/>
      <ITEM CODE="CR2"/>
      <ITEM CODE="CR3"/>
    </LEGEND>
    <LINK LOCATION="ComponentRedirect">
      <PARAMETER NAME="vertID" VALUE="ID" USE_PAGE_PARAM="false"/>
      <PARAMETER NAME="dueDate" VALUE="START_DATE"
        USE_PAGE_PARAM="false"/>
      <PARAMETER NAME="transID" VALUE="ID" USE_PAGE_PARAM="true"/>
    </LINK>
    <CAPTION_LINK LOCATION="AnotherPage">
      <PARAMETER NAME="vertID" VALUE="ID" USE_PAGE_PARAM="false"/>
      <PARAMETER NAME="dueDate" VALUE="START_DATE"
        USE_PAGE_PARAM="false"/>
      <PARAMETER NAME="transID" VALUE="ID" USE_PAGE_PARAM="true"/>
    </LINK>
  </CONFIG>

  <CONFIG ID="BarChart.Config" ORIENTATION="HORIZONTAL"
    CAPTION="Status.Caption"
    CAPTION_TEXT_CODETABLE="Cars"
    MIN_HEIGHT="200" MAX_HEIGHT="500">
    <LEGEND VISIBLE="true" CODETABLE="OldCars">
      <ITEM CODE="CR1"/>
      ...
    </LEGEND>
    <LINK LOCATION="TransferPage">
      <PARAMETER NAME="horID" VALUE="ID" USE_PAGE_PARAM="false"/>
      ...
    </LINK>
  </CONFIG>

  <CONFIG ID="BarChart.Config" TYPE="line"
    CAPTION="Line.Chart.Caption">
    <LEGEND>
      <ITEM CODE="CR1"/>
      ...
    </LEGEND>
    <LINK LOCATION="ComponentRedirect">
      <PARAMETER NAME="horID" VALUE="ID" USE_PAGE_PARAM="false"/>
      ...
    </LINK>
  </CONFIG>
</CHART-CONFIG>
```

The CHART-CONFIG root element contains only CONFIG elements. The CONFIG element contains all configuration for a particular field, identified by the ID attribute. The following table describes all attributes of the CONFIG element. BarChart.properties referred to in this table is a properties file in the client application's <CLIENT\_DIR>\components\core folder, used to look up values required.

Table 114. Attributes of the CONFIG element

Attribute	Description
ID	Unique identifier for this CONFIG element.
TYPE	Can be either line or pie, depending on required type of chart. If not present, ORIENTATION attribute will be used to define if bar or column chart is to be displayed.
ORIENTATION	Can be either HORIZONTAL or VERTICAL, depending on required type of chart, HORIZONTAL meaning bar chart and VERTICAL - column chart.
CAPTION_TEXT_CODETABLE	Code table currently used for label captions throughout a chart. If not specified, literal values from chart data will be used.
MAX_VALUE	Maximum value for a numeric axis of column or bar chart. Automatically calculated to fit the maximum element, if not specified.
MAX_INCREMENT	Maximum increment value for a numeric axis of a chart. Numbered ticks are drawn on a chart at the specified intervals. If not specified, numbered ticks are placed at uniform intervals along the numeric axis, taking into account it's maximum value.
X_AXIS_LABEL	Key to a text property in BarChart.properties. This text is used as the label for the x-axis in the column or line chart, or y-axis in the bar chart. Not used on pie chart.
Y_AXIS_LABEL	Key to a text property in BarChart.properties. This text is used as the label for the y-axis in the column or line chart, or x-axis in the bar chart. Not used on pie chart.
MIN_HEIGHT	This setting is used to define minimum chart object height and is to be specified in pixels. Where a chart contains a small number of items and would be short based on that content size, minimum height introduced by this setting is used. The setting is optional, so 250px default minimum height is used if MIN_HEIGHT is not specified.
MAX_HEIGHT	This setting is used to define the maximum chart object height on screen and should be specified in pixels. Where a chart contains numerous items and its contents exceeds the MAX_HEIGHT specified, this setting is used for the chart object height and a vertical scrollbar appears to allow for access to the rest of the items in the chart. The setting is optional and a default of 250px is used if the attribute is not specified. A value of -1 for MAX_HEIGHT means that the chart takes whichever height its content needs to be displayed in full. It is worth noting that the minimum height setting, either default or explicit, is still taken into account in this case. As a result, charts with little content will not be shorter than minimum or default height implies. Finally, a chart with MAX_HEIGHT set to -1 will not display its vertical scrollbar and the browser scrollbar will appear once the chart is too big to fit into the screen area available.
CAPTION	Key to a text property in BarChart.properties. This text is used as the label for the whole chart.

**Note:** The example lists sample ChartConfig.xml contents. The older format in BarChartConfig.xml is almost the same except that the root element is called BARCHART-CONFIG.

The older versions of BarChartConfig.xml do not contain configuration for label links. This element might be added, if required to this file directly; it is preferable, though, to create appropriate full configuration with the same ID in the ChartConfig.xml which will override the older version.

MIN\_HEIGHT and MAX\_HEIGHT settings currently do not apply to line or pie charts and will be ignored for these types.

The CONFIG element has three child elements: LEGEND, LINK and optional CAPTION\_LINK.

- The LEGEND element defines the items available for use in the TYPE attribute of a BLOCK element in chart data returned from the server. The element has an optional CODETABLE attribute, specifying the code table used for legend item translation, and an optional VISIBLE attribute which indicates if the legend should be seen on screen or not. This attribute has a default value of false, so it must be explicitly set to true in order for the legend to be displayed.

The ITEM child element of specifies each legend entry. Its CODE attribute is the text or code table code used to identify a legend item. The code table containing the CODE value will be ascertained first from the CAPTION\_TEXT\_CODETABLE value of the CONFIG element, then the CODETABLE attribute on the LEGEND element value, or, in case neither of these attributes are present or do not apply to a particular CODE, the literal value will be used as a caption. The same caption is used for a context data tip displayed when mouse pointer is over a corresponding chart element.

- The LINK child element is used to configure hyperlinks on bar chart bars and column chart columns or pie chart segments. Its LOCATION attribute is the ID of the UIM page to link to. A LINK element can have any number of PARAMETER child elements. The NAME attribute of a PARAMETER is the name to give the parameter when transferred as part of hyperlink. The VALUE attribute is the name of the attribute on the BLOCK element or the CAPTION element in the chart input data returned from the server (see below) to use as a parameter value unless USE\_PAGE\_PARAM is true, in which case VALUE is the name of a page parameter.
- Finally, the CAPTION\_LINK element is used whenever chart captions are intended to be rendered as links and contains separate settings for such links. The CAPTION\_LINK element contents are similar to those of the LINK element. When this element is skipped, captions are displayed as static text. Also, captions as links are currently supported on bar and column charts only.

Texts for chart caption and axes labels can be customized and localized by creating a properties file called BarChart.properties in the client application's <CLIENT\_DIR>\components\core folder and placing there values under keys, corresponding to the ones specified among CONFIG element parameters as described above.

In addition, the text displayed for the word total displayed in the bar tool-tips is customizable using the key total.tooltip.text in the BarChart.properties file.

**Note:** Bar colors are not customizable in charts and are automatically calculated by Adobe FLEX.

**Collapsible Cluster Support:** Collapsible clusters are not supported for any cluster containing this widget.

## Chart Data Formats

The data to be displayed in a chart comes from the server in XML format.

Below is example of the XML used to create a chart:

```
<CHART>
  <UNIT>
    <CAPTION TEXT="TR1" START_DATE="2004-12-31"
      END_DATE="2005-03-06"/>
    <BLOCK ID="1" TYPE="CR1" DUE_DATE="2005-01-01" LENGTH="33"/>
    <BLOCK ID="2" TYPE="CR3" DUE_DATE="2005-02-01" LENGTH="14"/>
  </UNIT>
  <UNIT>
    <CAPTION TEXT="TR2" START_DATE="2004-12-31" />
    <BLOCK ID="3" TYPE="CR3" DUE_DATE="2005-01-02" LENGTH="11"/>
  </UNIT>
  <UNIT>
    <CAPTION TEXT="TR3" END_DATE="2005-03-08" />
    <BLOCK ID="4" TYPE="CR1" DUE_DATE="2005-01-03" LENGTH="22"/>
    <BLOCK ID="5" TYPE="CR2" DUE_DATE="2005-01-09" LENGTH="15"/>
    <BLOCK ID="6" TYPE="CR3" DUE_DATE="2005-01-01" LENGTH="8"/>
  </UNIT>
</CHART>
```

Figure 93. Sample Horizontal Bar Chart XML

The root element, CHART, can contain any number of UNIT elements. These elements are used to group related information into groups (clusters) and contain one CAPTION element and one or more BLOCK child elements.

The CAPTION element displays an appropriate caption depending on what attributes are set:

- If either the START\_DATE or both START\_DATE and END\_DATE attributes are set, then the caption will be either a single start date or a range of dates.
- If the TEXT attribute is set, then the caption text is first looked for in the code table specified in the CAPTION\_TEXT\_CODETABLE attribute of the CONFIG element (see above), then looked for as a property in BarChart.properties using the TEXT value as a key, or, if neither attempt is a match, the literal TEXT value is rendered as a caption.

Each BLOCK element represents a block to be drawn on a chart as a bar, column, line chart point or pie chart sector. This element must have an associated TYPE attribute to match it with a particular item. The LENGTH attribute is necessary to define the measurement of the block. In the bar or column chart this is the length/height of a bar/column; in a line chart it's the position of an edge point; in a pie chart it's the relative sector arc length. The ID attribute is a unique identifier for a block and can be used as a parameter for any hyperlinks. The optional DUE\_DATE attribute can also be used as an ID parameter for hyperlinks on a particular block. It represents the due date for a given block.

**Note:**

- There are no restrictions on the number or names of the attributes of BLOCK element. This facilitates passing an arbitrary set of attributes in the links from a chart (provided the configuration is updated appropriately). However, one should keep in mind, that the names of the attributes provided in this section are reserved and bound to the particular elements, i.e. even though START\_DATE attribute could be added to a BLOCK element, in this case it will be interpreted as a literal value and not a date as it would be in the context of CAPTION element.
- Due to the nature of pie chart, no more than one BLOCK element will be processed and displayed in this type of chart.

# Heatmap Widget

## Overview

The Heatmap widget is a control which displays a grid of items of different importance. Items in the widget are presented by color shades varying from red to blue, indicating their importance level from highest to lowest.

The widget is inserted into the page when the XML\_HEATMAP domain is associated with UIM source property of a FIELD.

The Heatmap widget expects XML data from the server in the following format:

```
<HEATMAP>
  <REGION REGION_ID="R1" LABEL="highest importance"/>
  <REGION REGION_ID="R2" LABEL="middle importance">
    <ITEM ITEM_ID="id9" LABEL="0009" />
    <ITEM ITEM_ID="id10" LABEL="0010"/>
    <ITEM ITEM_ID="id21" LABEL="0021"/>
  </REGION>
  <REGION REGION_ID="R3" LABEL="lowest importance">
    <ITEM ITEM_ID="id22" LABEL="0022"/>
  </REGION>
  ...
</HEATMAP>
```

Here, the REGION elements specify the importance level ("heat") of their contained ITEM s. There should be at least two regions in a heatmap widget. The color will always start from red, so if no items of that importance are there, empty REGION elements should be inserted for the widget to render properly.

## Configuration

Different types of heatmap can be configured by creating entries in the HeatmapConfig.xml file in your components directory, using the following format:

```
<HEATMAP_CONFIG>
  <CONFIG ID="Map1" NUM_COLS="10" NUM_ROWS="4"
    LEGEND_POSITION="LEFT"
    LEGEND_TITLE="Deadline"
    LEGEND_TITLE_PROPERTY="Localised.Legend.Title">
    <ITEM_LINK PAGE_ID="Sample_page">
      <PARAM NAME="configParameter" VALUE="ITEM_ID"/>
    </ITEM_LINK>
  </CONFIG>
  <CONFIG ID="Map2" NUM_COLS="6">
    ...
  </CONFIG>
</HEATMAP_CONFIG>
```

The attributes of a CONFIG element are summarized in the following table:

Table 115. Attributes for CONFIG element

Attribute	Description
NUM_COLS	This attribute allows you to set the number of items displayed in each row of the Heatmap
NUM_ROWS	This attribute allows you to specify the number of visible rows in the Heatmap. If this attribute is set to less rows than are required to display the data, a vertical scrollbar will be provided. If this attribute is not present, the widget will expand to display as many rows as are required.



Table 115. Attributes for CONFIG element (continued)

Attribute	Description
LEGEND_POSITION	By default, the Heatmap legend is drawn to the right of the widget. This attribute can be used to draw the legend to the left instead, by setting it's value to LEFT.
LEGEND_TITLE	The default title for a legend is Legend. This attribute can be used to specify a more logical title to use.
LEGEND_TITLE_PROPERTY	Optional attribute used to customize/localize the displayed title. The value here is the key in the CDEJResources.properties file or its localized version (see "Localization" on page 43 for more details on localization).

The ITEM\_LINK element can be used to specify the page to which to link when a user clicks on an item in the Heatmap, by setting it's PAGE\_ID attribute. The PARAM child element can be used to specify what page parameters to pass (the NAME attribute) and what data items to use as their value (the VALUE attribute). Values which don't match any attributes in the ITEM elements in the Heatmap XML are assumed to be literal values.

To specify which configuration to use for a given instance of the Heatmap widget, the CONFIG attribute of the field containing the widget should be set to the ID of the desired configuration.

## Workflow

### Overview

A workflow depicts a series of steps that routinely take place in order for a unit of work to be completed. The WORKFLOW\_GRAPH\_XML domain, or any derivation of it, causes a workflow to be displayed. The data to be displayed in a workflow comes from the server in XML format. Configuration settings for the Workflow must be in a file called WorkflowConfig.xml, of which there can be only one per component. The format for the XML data and configuration settings are described below. Any static text for this view can be customized and localized by creating a properties file called Workflow.properties in the client application's <CLIENT\_DIR>\components\core folder.

### Workflow Details

In a workflow view, a box, along with a representative icon, represents a discrete unit of work and is called an activity. Any line connecting nodes is called a transition and is intended to illustrate the flow of work. For this reason, the start and end activities are represented by icons only. Workflow proceeds from the left and ends at the right-most activity. An activity is a hyperlink to a tab containing further details on that activity. An activity can have a second, smaller icon indicating that there is a notification on this activity. Clicking on the notification icon (a small envelope in the image below) will open a separate tab with details of the notification.

An activity has an entry point and an exit point for a transition, on the right and the left respectively. When two or more transitions leave an exit point this is called a split. The transitions in a split can be given a number to indicate their relative progression. When two or more transitions meet at an activity's entry point this is called a join. If either a join or a split is an "and" type, also called a "conjunction", then it is represented as a small square. This implies that a series of transitions have to take place together in order for the workflow to proceed. If a join or a split

is an “xor” type, an either-or situation, then a small circle is used. There are examples of both in the figure below. Finally, a transition can have an associated transition condition. This means that certain criteria have to be met in order for a transition to proceed. This is represented by an asterisk on the transition and the full condition information is displayed in a pop-up if the user hovers the mouse over the symbol.




Figure 94. Workflow

## Workflow XML Formats

The workflow widgets require XML data that conforms to the workflow schema defined in the workflow.xsd file located in the lib\curam\xml\schema folder of your CDEJ installation folder. Below is an example of workflow XML data:

```

<WORKFLOW ID="4791830003522207744" PROCESS-VERSION="1">
  <NODE ID="6953557824660045824" X="2.0" Y="1.0"
    TEXT="Loop Activity [End]" HIDDEN="false"
    ACTIVITY-TYPE-CODE="AT9" HAS-NOTIFICATION="true"
    IS-EXECUTED="false" SPLIT-TYPE="AND" JOIN-TYPE="AND"
    TASK-ID="1"/>
  <NODE ID="-3566850904877432832" X="3.0" Y="1.0"
    TEXT="EndProcessActivity" HIDDEN="false"
    ACTIVITY-TYPE-CODE="AT7" IS-EXECUTED="false"
    JOIN-TYPE="AND" TASK-ID="2"/>
  <NODE ID="2702159776422297600" X="1.0" Y="2.0"
    TEXT="Activity 1" HIDDEN="false"
    ACTIVITY-TYPE-CODE="AT5" IS-EXECUTED="false"
    SPLIT-TYPE="AND" JOIN-TYPE="AND" TASK-ID="3"/>
  <EDGE FROM="6953557824660045824" TO="-3566850904877432832"
    HIDDEN="false" TRANSITION-ID="1621295865853378560"
    IS-EXECUTED="false" REVERSE-ARROW="false"/>
  <EDGE FROM="3566850904877432832" TO="2702159776422297600"
    HIDDEN="false" TRANSITION-ID="0" IS-EXECUTED="false"
    REVERSE-ARROW="true"/>
</WORKFLOW>

```

The root element, WORKFLOW, can have any number of NODE (activity) and EDGE (transition) elements. The ID attribute on WORKFLOW identifies this particular workflow as does the PROCESS-VERSION attribute.

The NODE element represents a single activity in the workflow. All attributes of a node are defined in the following table:

*Table 116. Attributes of a Node*

Attribute	Description
ID	Unique identifier for this element, supplied as a parameter in the row header hyperlink.
X	An x-coordinate for an element on the workflow graph.
Y	A y-coordinate for an element on the workflow graph.
TEXT	The text of an activity.
ACTIVITY-TYPE-CODE	Code for an activity type. Used as a parameter in a hyperlink.
HIDDEN	Boolean property to indicate if an edge or node is to be hidden. If true the node will not be displayed.
IS-EXECUTED	Boolean property to indicate if an activity has already been executed for a particular process instance. If set to true then the activity has been executed.
SPLIT-TYPE	The split type associated with an activity.
JOIN-TYPE	The join type associated with an activity.
ACTIVITY-INSTANCE-ID	The unique identifier of an activity instance for a particular process instance.
START-DATE-TIME	The start date time of an activity instance or transition instance for an executed or currently executing process.
END-DATE-TIME	The end date time of an activity instance or transition instance for an executed or currently executing process.
STATUS	The current status of an activity instance.
TASK-STATUS	Code for the status of a task.
TASK-RESERVED-BY	The name of the user reserving the task.
TASK-TOTAL-TIME-WORKED	The total time worked on a task in seconds.

Table 116. Attributes of a Node (continued)

Attribute	Description
NUMBER-ITERATIONS	The number of times the activity contained in a node has been executed.
TASK-ID	The unique identifier for the task.

The EDGE element represents a single transition in the workflow. All attributes of an edge are defined in the following table:

Table 117. Attributes of an Edge

Attribute	Description
FROM	The ID of the node this edge is from.
T0	The ID of the node this edge is to.
TRANSITION-ID	The unique identifier of a transition.
IS-FOLLOWED	Boolean property to indicate if a particular transition has already been followed for a process instance.
TRANSITION-INSTANCE-ID	The unique identifier of a transition instance for a particular process instance.
REVERSE-ARROW	Boolean property to indicate if an arrow on an edge should be reversed. In this case, the arrow will be going into the FROM node instead of the T0 node.
IS-EXECUTED	Boolean property to indicate if an activity has already been executed for a particular process instance. If set to true then the activity has been executed.
TRANSITION-CONDITION	The condition associated with a transition in an edge.
REAL_FROM	ID of a node that this edge is actually from as opposed to an intermediate hidden node identified by the FROM attribute.
REAL_TO	ID of a node that this edge is actually to as opposed to an intermediate hidden node identified by the T0 attribute.
ENABLED	Boolean property to indicate if an edge is to be enabled as a hyperlink. This attribute is false by default.
ORDER	Indicates the order of an edge relative to other edges.

As mentioned above, workflow charts are configurable. This is accomplished by setting the CONFIG attribute on the UIM field in question. The WorkflowConfig.xml XML configuration file must contain a configuration section with a unique identifier matching the text in the CONFIG attribute. The XML schema format for this file is defined in the workflow-config.xsd file located in the lib\curam\xml\schema folder of your CDEJ installation folder. The following is a sample of this file:

```

<WORKFLOW_CONFIG>
  <ICON CODE="AT1" PATH="Images/manual.gif"/>
  <ICON CODE="AT2" PATH="Images/automatic.gif"/>
  <ICON CODE="AT4" PATH="Images/subflow.gif"/>
  <ICON CODE="AT5" PATH="Images/route.gif"/>
  <ICON CODE="AT6" PATH="Images/eventwait.gif"/>
  <ICON CODE="AT7" PATH="Images/endprocess.gif"/>
  <ICON CODE="AT8" PATH="Images/loopbegin.gif"/>
  <ICON CODE="AT9" PATH="Images/loopend.gif"/>
  <ICON CODE="AT10" PATH="Images/decision.gif"/>
  <ICON CODE="AT11" PATH="Images/startprocess.gif"/>
  <ICON NOTIFICATION="true"
    PATH="CDEJ/cdej-images/notification.gif"/>
  <CONFIG ID="WorkFlow.Config"
    NOTIFICATION_PAGE="viewActivityNotification"
    DETAILS_PAGE="componentRedirect"
    START_PROCESS_TYPE="AT11" END_PROCESS_TYPE="AT7"/>
</WORKFLOW_CONFIG>

```

The WORKFLOW\_CONFIG root element contains CONFIG elements and ICON elements. The CONFIG element contains all configuration for a particular field, identified by the ID attribute. The following table describes all attributes of the CONFIG element:

*Table 118. Attributes of Workflow CONFIG element*

Attribute	Description
ID	Unique identifier for this configuration.
DETAILS_PAGE	ID of a UIM page to use as a destination for a hyperlink on a node.
HEIGHT	Height in pixels of a workflow chart. If height is not specified, a height will be chosen that attempts to maximize the use of available space.
ACTIVITY_CODETABLE	Codetable name for resolving ACTIVITY-TYPE-CODE attribute values.
TASKSTATUS_CODETABLE	Codetable name for resolving TASK-STATUS attribute values.
PROCESSSTATUS_CODETABLE	Codetable name for resolving the status of a process instance (e.g. In Progress, Completed, Suspended or Aborted).
SHOW_INSTANCE_DATA	Determines if the chart should display a text area containing all instance data information. Valid settings are true and false.
START_PROCESS_TYPE	Code identifying the ACTIVITY-TYPE-CODE set as the start process type. This activity will be drawn without a box.
END_PROCESS_TYPE	Code identifying the ACTIVITY-TYPE-CODE set as the end process type. This activity will be drawn without a box.
NOTIFICATION_PAGE	ID of a UIM page to use as a destination for a hyperlink on a notification icon.
READONLY_VIEW	Determines if the links on a workflow graph should be disabled.
HIGHLIGHT_ACTIVITY_PARAM	Represents the parameter used to determine the current activity in a workflow. The value of the parameter is matched with a corresponding attribute in the XML data returned from the server to indicate which node has to be highlighted.

The ICON child element of the WORKFLOW\_CONFIG root element defines all icons for the workflow chart. Either the CODE attribute or the NOTIFICATION attribute defines what kind of icon this is. If CODE is set then the ACTIVITY-TYPE-CODE on a NODE is used to match an icon to a particular activity type. If the NOTIFICATION attribute is set to true then this icon is used as a graphic depicting a notification present on an activity. The PATH attribute on ICON is used to point to an image file, relative to your project's WebContent directory.

## Evidence View

This view has two modes for displaying and comparing evidence data.

### Evidence Display Mode

The EVIDENCE\_XML domain results in a table displaying evidence items. There are three columns in the table. The first displays the evidence item name, the second shows the group to which evidence item belongs and the value of the item is displayed in the third column. The value of the item will be formatted based on it's domain.

### Evidence Comparison Mode

The EVIDENCE\_XML\_COMPARE domain results in three tables displaying evidence comparison results. The comparison results consist of three tables to display items which were modified, added or deleted. All three tables follow the same format: the first column displays the evidence item name; the second column displays the group which the evidence item belongs to and corresponding values are displayed in the third (the modified evidence table will have a fourth fourth column to show previous values against current values) column.

### Configuration

The evidence view is configurable by changing settings in appropriate properties files. For Evidence Display mode this is the DisplayEvidence.properties file and for Evidence Comparison mode configuration, ComparedEvidence.properties file is used. These properties files should be created in the <CLIENT\_DIR>\components\core folder.

Configuration files contain table headers and captions for all the columns as well as visibility settings for each column. There is also a links section for specifying links to pages for each evidence item and item group column if needed. If a link is not required, leave the value empty rather than deleting the property itself. Also there are properties containing textual substitution for an empty value case and textual insert used in evidence item name.

**Note:** The properties specifying visibility settings are not localizable strings and should contain either "true" or "false" depending on desired visibility of the corresponding column.

Below is an example of the configuration settings for display evidence mode:

```
#Textual descriptions for comparison sections.
Table.Summary.Single=This table contains evidence items.

# Comparison section labels
Evidence.Table.Label=Evidence Items

#Column headers
Description.Column.Header=Rule
Group.Column.Header=Group
Value.Column.Header=Value

#Visibility
Description.Column.Visible=true
Group.Column.Visible=true
Value.Column.Visible=true

# Localizable messages
Message.No.Value=This item is not set
Message.Item.Joint=referenced by rule item

#Links (Values should be UIM PAGE_IDs)
Description.Column.Link=Home
Group.Column.Link=GroupHome
```

The following is an example of the configuration settings for the evidence comparison mode:

```
#Textual descriptions for comparison sections.
Table.Summary.MODIFIED=This table contains modified evidence
Table.Summary.NEW=This table contains newly added evidence items.
Table.Summary.REMOVED=This table contains removed evidence.

# Comparison section labels
Evidence.Label.MODIFIED=Modified evidence
Evidence.Label.NEW=Newly added evidence items
Evidence.Label.REMOVED=Removed evidence items

#Column headers
Description.Column.Header=Rule
Group.Column.Header=Group
Oldval.Column.Header=Previous Value
Value.Column.Header=New Value

#Visibility
Description.Column.Visible=true
Group.Column.Visible=true
Oldval.Column.Visible=true
Value.Column.Visible=true

#Links (Values should be UIM PAGE_IDs)
Description.Column.Link=Home
Group.Column.Link=GroupHome
```

## Data Format

The Evidence view expects the following XML format. Below is an example for Evidence Comparison mode:

```

<EVIDENCE_COMPARE>
  <EVIDENCE TYPE="MODIFIED">
    <GROUP ID="mod1ID"
      DESCRIPTION="en|EvidenceGroup1">
        <EVIDENCE_ITEM ID="modItem1ID"
          DESCRIPTION="en|Number of Children"
          OLDVAL="11" VALUE="13"
          DOMAIN="SVR_INT32"/>
        </GROUP>
      <GROUP ID="mod2ID"
        DESCRIPTION="en|EvidenceGroup2">
          <EVIDENCE_ITEM ID="modItem3ID"
            DESCRIPTION="en|Are you married"
            OLDVAL="false" VALUE="true"
            DOMAIN="SVR_BOOLEAN"/>
          </GROUP>
        </EVIDENCE>
      <EVIDENCE TYPE="NEW">
        <GROUP ID="new1ID"
          DESCRIPTION="en|EvidenceGroup1">
            <EVIDENCE_ITEM ID="newItem1ID"
              DESCRIPTION="en|Number of cars"
              VALUE="6"
              DOMAIN="SVR_INT32"/>
            </GROUP>
          </EVIDENCE>
        <EVIDENCE TYPE="REMOVED">
          <GROUP ID="del1ID"
            DESCRIPTION="en|Deletion">
              <EVIDENCE_ITEM ID="delItem1ID"
                DESCRIPTION="en|Number of houses"
                OLDVAL="1"
                DOMAIN="SVR_INT32"/>
              </GROUP>
            </EVIDENCE>
          </EVIDENCE_COMPARE>

```

The following is an example of the Evidence Display mode:



```

<evidence>
  <group id="group1" display-name="EvidenceGroup1">
    <item name="item11"
      display-name="Number of Children"
      initial-value="13" no-value="false"
      type="SVR_INT32"/>
    <item name="item12"
      display-name="item with no value"
      initial-value="" no-value="true"
      type="SVR_STRING"/>
  </group>
  <group id="group2" display-name="EvidenceGroup2">
    <item name="item21"
      display-name="Are you married"
      initial-value="true" no-value="false"
      type="SVR_BOOLEAN"/>
    <item name="item22"
      display-name="Some important dates"
      initial-value="" no-value="false"
      type="SVR_DATE">
      <value position="10" description="Important date 1"
        value="20050401T000000">
      <value position="18" description="Important date 2"
        value="20050601T000000">
      <value position="5" description="Important date 3"
        value="20051231T000000">
    </item>
  </group>
</evidence>

```

The display-name attribute represents a description for every item or group, the description does the same for the value element. Group ids, evidence item names and value descriptions are supplied by the evidence text returned from the rules engine. The type attribute is used to select particular representation for different data types from the server. The name attribute of item and the id attribute of group are used as link parameters if a link is specified for the first or second column.

## Calendar

The calendar is used by any UIM page which displays a field from a server access bean containing a CALENDAR\_XML\_STRING domain. This view allows for scheduling of events from different time-frames; monthly, weekly and daily.

Programmatically, the calendar expects to be populated with information about events in an XML format.

The following is an example of what the XML received from the server might look like:

```

<CURAM_CALENDAR_DATA TYPE="UserCalendar">
  <EVENT>
    <ID>1</ID>
    <DATE>2002-10-10</DATE>
    <STARTTIME>10:10:10</STARTTIME>
    <ENDTIME>10:10:10</ENDTIME>
    <DURATION>0</DURATION>
    <DESCRIPTION>Hello World!</DESCRIPTION>
    <STATUS>ATS1</STATUS>
    <PRIORITY>AP1</PRIORITY>
    <LEVEL>AL1</LEVEL>
    <RECURRING>false</RECURRING>
    <READ_ONLY>false</READ_ONLY>
    <ALL_DAY>false</ALL_DAY>
    <ATTENDEE>true</ATTENDEE>
    <ACCEPTANCE>true</ACCEPTANCE>
  </EVENT>
  <SINGLE_DAY_EVENT>
    <ID>2</ID>
    <DATE>2003-04-01</DATE>
    <TYPE>ET1</TYPE>
    <DESCRIPTION>April Fool's Day</DESCRIPTION>
  </SINGLE_DAY_EVENT>
</CURAM_CALENDAR_DATA>

```

Figure 95. Calendar XML Stream

Notice that there can be two kinds of event elements contained within the CURAM\_CALENDAR\_DATA XML data: EVENT and SINGLE\_DAY\_EVENT. In the schema of the XML data expected the root element, CURAM\_CALENDAR\_DATA, can hold any number (zero to many) of EVENT and SINGLE\_DAY\_EVENT elements; CURAM\_CALENDAR\_DATA can optionally have a TYPE attribute which associates this sequence of events with a particular calendar configuration (see example below).

The following tables describe the schema definitions for each of the attributes allowed on the EVENT and the SINGLE\_DAY\_EVENT elements respectively.

Table 119. EVENT attributes in schema

Attribute Name	Description	Required
ID	A string to uniquely identify this event.	
DATE	The date of the event in xs:date format: (CCYY-MM-DD) I.e. 21- Aug-2002 is represented as 2002-08-21.	No
STARTTIME	The start time in xs:time format: (hh:mm:ss). I.E. 1:34 pm and 56 seconds is represented as 13:34:56.	
ENDTIME	The start time in xs:time format: (hh:mm:ss).	No
DURATION	The duration of the event in minutes. This should be an integer.	No
DESCRIPTION	A Description of the event.	No
STATUS	The status of the event. This node is limited to values stored in the ActivityTimeStatus code table in the reference application.	No
PRIORITY	The priority of the event. This node is limited to values stored in the ActivityPriority code table in the reference application.	No

Table 119. EVENT attributes in schema (continued)

Attribute Name	Description	Required
LEVEL	Code that shows the level of the activity. This node is limited to the values stored in the ActivityLevel code table in the reference application.	No
RECURRING	Recurring indicator: true if this event is a recurring event. Otherwise false.	No
READ_ONLY	Read-only indicator: true if this event is a read-only event. Otherwise false.	No
ALL_DAY	All-day indicator: True if this is an all-day event. Otherwise false.	No
ATTENDEE	Attendee indicator: true if the user is attending a meeting. Otherwise false.	No
ACCEPTANCE	Acceptance indicator: True if the user has accepted an invitation to a meeting. Otherwise false.	
POSITION	For a spanning event, indicates first or last component of the event.	No

Table 120. SINGLE\_DAY\_EVENT attributes in schema

Attribute Name	Description	Required
ID	A string to uniquely identify this event.	No
DATE	The date of the event in xs:date format.	No
TYPE	The type of a single day event.	No
DESCRIPTION	A Description of the event.	No

Once a field based on the CALENDAR\_XML\_STRING domain returns XML information formatted according to the aforementioned schema, it will be displayed in the appropriate time position by the calendar. Any web page containing a calendar can be set to open on different dates and views by specifying the *startDate* and *calendarViewType* parameters in the page's URL. The *startDate* parameter should be formatted according to the date format expected by the application and the *calendarViewType* parameter should be one of the following codes.

Table 121. Calendar View Type Values

Code	Value
CVT1	Day view
CVT2	Week view
CVT3	Month view

You can configure the display of calendar information using the CalendarConfig.xml file. There should be at least one copy of this in the components folder. This file should contain configuration information for each type of calendar, the TYPE attribute of the CURAM\_CALENDAR\_DATA element mentioned above associates a calendar data stream with a particular type. The following is an example of the structure of the CalendarConfig.xml

```

<CONFIGURATION MONTH_CELL_HEIGHT="4"
    SHOW_REPEAT_EVENT_TEXT="true">
  <CALENDAR TYPE="UserCalendar">
    <DESCRIPTION_LOCATION>DetailsPage.do</DESCRIPTION_LOCATION>
    <DAY_VIEW_TIME_FORMAT>24</DAY_VIEW_TIME_FORMAT>
  </CALENDAR>
  <EVENT_TYPES>
    <TYPE NAME="ET1" ICON="Images/mandatory.gif"/>
    <TYPE NAME="ET2" ICON="Images/case.gif"/>
    <TYPE NAME="ET3" ICON="Images/concern.gif"/>
  </EVENT_TYPES>
</CONFIGURATION>

```

Figure 96. CalendarConfig.xml Example

The overall schema for this configuration file specifies the CONFIGURATION element as the root element. The CONFIGURATION has an optional MONTH\_CELL\_HEIGHT attribute which sets the maximum number of rows to display in a single cell in the month view. The default value is three. The SHOW\_REPEAT\_EVENT\_TEXT optional attribute, if set to true, will display the event description in each month cell if an event spans multiple days. This attribute is false by default.

The CONFIGURATION root element can hold any number of CALENDAR elements and a single EVENT\_TYPES element. The TYPE attribute of CALENDAR associates this configuration information with an XML stream returned from the server. The DESCRIPTION\_LOCATION element of CALENDAR is for constructing a link to a page containing more information on any event in the calendar. The following table lists the parameters passed with this hyperlink.

Table 122. Parameters Passed to Event Description Pages

Parameter Name	Description
ID	the event ID
RE	Recurrence indicator
AT	Attendee indicator
RO	Read-only indicator
LV_	Activity level
AC	Acceptance indicator

The CALENDAR element should also contain an element called DAY\_VIEW\_TIME\_FORMAT. The valid values for this element are 12 and 24. They specify whether the time in the day view is displayed using a 12 or 24 hour format.

The EVENT\_TYPES element is used for mapping images to display as icons next to single day events. The NAME attribute of the TYPE element must match a TYPE element on a SINGLE\_DAY\_EVENT supplied by the server for the image specified by the ICON attribute to be displayed.

The schema for the calendar configuration file (CalendarConfiguration.xsd) and the schema for the CALENDAR\_XML\_STRING domain (CuramCalendar.xsd) are located in your project's WebContent/WEB-INF/CDEJ/schema folder.

## Payment Statement View

The payment statement view is used for displaying under or over payment within the Cúram application framework.

The payment statement view supports the display of benefits as well as liabilities. The domain BENEFIT\_REASSESSMENT\_RESULT\_TEXT should be used for a benefit payment statement view. The domain LIABILITY\_REASSESSMENT\_RESULT\_TEXT should be used for a liability payment statement view. It is expected that all string data returned for this field follows a specific tab-delimited format. Examples of using these domains can be found in the Cúram reference application.

There is also a properties file associated with this view:

PaymentStatement.properties in the <CLIENT\_DIR>\components\core folder. The link to a page providing further details on a statement can be defined using a set of four parameters:

```
PaymentStatement.RowLink.Benefit.PageID
PaymentStatement.RowLink.Benefit.ParameterName
PaymentStatement.RowLink.Benefit.Label
PaymentStatement.RowLink.Benefit.Image
```

There is one set of parameters for Benefit pages and one for Liability pages. PageID is the name of the page to link to. ParameterName is the name of the parameter to be passed to this page to identify the id of the payment in question. Label supplies the text of the link, if Image is not used. Otherwise it supplies the tool-tip for the image-based link.

The remaining properties are simply externalized strings for the widget.

```
PaymentStatement.RowLink.Benefit.PageID=FromBenefit
PaymentStatement.RowLink.Liability.PageID=FromLiability

PaymentStatement.RowLink.Benefit.ParameterName=param1
PaymentStatement.RowLink.Liability.ParameterName=param2

PaymentStatement.RowLink.Benefit.Label=Link Text 1
PaymentStatement.RowLink.Liability.Label=Link Text 2

#PaymentStatement.RowLink.Benefit.Image=Images/icon.gif
PaymentStatement.RowLink.Liability.Image=Images/icon.gif

PaymentStatement.Text.fromToDateSeparator=\ to
PaymentStatement.Text.Action=Action
PaymentStatement.Text.Period=Period
PaymentStatement.Text.Desc=Description
PaymentStatement.Text.Actual=Actual
PaymentStatement.Text.Reassessed=Reassessed
PaymentStatement.Text.Liability.Received=Received
PaymentStatement.Text.Diff=Difference
PaymentStatement.Text.GrossTotal=Total Gross Over Payment
PaymentStatement.Text.TaxTotal=Total Tax Deduction
PaymentStatement.Text.UtilityTotal=Total Utility Deduction
PaymentStatement.Text.LiabilityTotal=Total Liability Deduction
PaymentStatement.Text.NetTotal=Net Under or Over Payment
```

*Figure 97. A Sample PaymentStatement.properties File*

## Batch Function View

The batch function view is generated from the PARAM\_TAB\_LIST domain. It allows you to enter parameters to submit a batch program for execution. The labels of each field are provided to the view by a single tab-delimited string.

## Addresses

The ADDRESS\_DATA domain type maps to a tag for entering and displaying addresses. Although the user sees several fields, addresses are stored as a single string field. Each of the fields displayed as part of the out-of-the-box address are text input fields except for the state field which is drop-down field.

To parse the address and display it, the elements that make up the address have to be defined in the curam-config.xml file. Different address configurations for different locales in the Cúram application can be defined. “Addresses” demonstrates how to set this configuration using the ADDRESS\_CONFIG element.

```
<ADDRESS_CONFIG>
  <LOCALE_MAPPING LOCALE="en_US"
    ADDRESS_FORMAT_NAME="US" />
  <LOCALE_MAPPING LOCALE="en_GB"
    ADDRESS_FORMAT_NAME="UK" />
  <ADDRESS_FORMAT NAME="US" COUNTRY_CODE="US">
    <ADDRESS_ELEMENT LABEL="Address.Label.AptSuite"
      NAME="ADD1" />
    <ADDRESS_ELEMENT LABEL="Address.Label.Street.1"
      NAME="ADD2" />
    <ADDRESS_ELEMENT LABEL="Address.Label.Street.2"
      NAME="ADD3" />
    <ADDRESS_ELEMENT LABEL="Address.Label.City"
      NAME="CITY" />
    <ADDRESS_ELEMENT CODETABLE="AddressState"
      LABEL="Address.Label.State"
      NAME="STATE" />
    <ADDRESS_ELEMENT LABEL="Address.Label.Zip"
      NAME="ZIP" />
  </ADDRESS_FORMAT>

  <ADDRESS_FORMAT NAME="UK" COUNTRY_CODE="GBR">
    <ADDRESS_ELEMENT LABEL="Address.Label.Address.1"
      MANDATORY="true" NAME="ADD1" />
    <ADDRESS_ELEMENT LABEL="Address.Label.Address.2"
      NAME="ADD2" />
    <ADDRESS_ELEMENT LABEL="Address.Label.Address.3"
      NAME="ADD3" />
    <ADDRESS_ELEMENT LABEL="Address.Label.Address.4"
      NAME="ADD4" />
    <ADDRESS_ELEMENT LABEL="Address.Label.County"
      NAME="ADD5" />
    <ADDRESS_ELEMENT LABEL="Address.Label.City"
      NAME="CITY" />
    <ADDRESS_ELEMENT LABEL="Address.Label.PostCode"
      NAME="POSTCODE" />
    <ADDRESS_ELEMENT CODETABLE="Country"
      LABEL="Address.Label.Country"
      NAME="COUNTRY" />
  </ADDRESS_FORMAT>
</ADDRESS_CONFIG>
```

Figure 98. Address Configuration in curam config xml

The ADDRESS\_CONFIG element is built using multiple LOCALE\_MAPPING and ADDRESS\_FORMAT elements. In Cúram application deployments with multiple locales, a developer may wish to use a different address format for each locale. To do this we use the LOCALE\_MAPPING element. This element contains a LOCALE attribute which defines the locale and an ADDRESS\_FORMAT\_NAME attribute which defines the ADDRESS\_FORMAT element to be mapped. By default, the OOTB Cúram application has a number of ADDRESS\_FORMAT elements defined which are mapped to specific locales. As these locales are already mapped it is not required to define

LOCALE\_MAPPING elements for them, however customers are free to modify these or create new configuration(s) as per their implementation needs. Figure 76 above illustrates how the LOCALE\_MAPPING element is used for the US and UK address formats. The following address formats and their corresponding locale mappings are available OOTB.

*Table 123. Address Format configurations*

Address Format Name	Locale Mapping
US	en_US
UK	en_GB
DE	de
CA	en_CA
KR	ko
JP	ja
TW	zh_TW
CN	zh_CN

The ADDRESS\_FORMAT has an optional COUNTRY\_CODE attribute which is used in the address header when an address is first created. If it is not set, the COUNTRY\_CODE defaults to GBR when the address format specified is UK and to US for everything else. The COUNTRY\_CODE is not used by the infrastructure. It is one of the fields in the address string used by the application, but infrastructure provides an initial value for it.

The ADDRESS\_FORMAT elements contain ADDRESS\_ELEMENT elements which defines the fields in the address tag. The ADDRESS\_ELEMENT element has a LABEL attribute which refers to properties contained in the CDEJResources.properties file. The address is then built using ADDRESS\_ELEMENT tags which must be given a name and label. Note that a code table can also be specified for each ADDRESS\_ELEMENT. When a code table is specified, a drop-down list will display the code table entries and the default code will be pre-selected.

The optional MANDATORY attribute specifies if an address element is required to be filled in. The Mandatory indicator is an asterisk beside the field label as shown in the example above. Please note, that in order for MANDATORY settings in curam-config.xml to work, the field supplying the address data should be marked mandatory in application model.

## Schedule View

The schedule view is used for any domain of the type SCHEDULE\_DATA. This view displays a grid of time-line information for the hours between 8 am and 8 pm. Each row in this grid represents a person whose full name is displayed in the row header. Each cell in the person's row represents a half hour period containing an indicator for whether they are available or not. If a user clicks on a free cell, they should be linked to a page allowing them to enter further schedule events.

The information and setup of this particular view involves a particular setup in a page's UIM file. "Schedule View" is an example of the UIM for a schedule field.

```

<FIELD>
  <CONNECT>
    <SOURCE NAME="ACTION" PROPERTY="schedule"/>
  </CONNECT>
  <CONNECT>
    <LINK PAGE_ID="IncomeScreening_confirmAppointment">
  <CONNECT>
    <SOURCE NAME="ACTION" PROPERTY="appointmentDate"/>
    <TARGET NAME="PAGE" PROPERTY="date"/>
  </CONNECT>
  <CONNECT>
    <SOURCE NAME="ACTION" PROPERTY="userFullName"/>
    <TARGET NAME="PAGE" PROPERTY="fullUserName"/>
  </CONNECT>
  <CONNECT>
    <SOURCE NAME="ACTION" PROPERTY="userName"/>
    <TARGET NAME="PAGE" PROPERTY="userName"/>
  </CONNECT>
  <CONNECT>
    <SOURCE NAME="PAGE" PROPERTY="caseID"/>
    <TARGET NAME="PAGE" PROPERTY="caseID"/>
  </CONNECT>
  <CONNECT>
    <SOURCE NAME="PAGE" PROPERTY="pageDescription"/>
    <TARGET NAME="PAGE" PROPERTY="pageDescription"/>
  </CONNECT>
</LINK>
</FIELD>

```

Figure 99. UIM Example of Schedule View

The Cúram page generator expects any schedule FIELD element to be followed by a LINK element which details the PAGE\_ID of the page to go to when a free cell is clicked on. The following three CONNECT elements should be fields which provide the following attributes to the link: the date of the day in question (the time is appended to this date); the full name of the user; and the user's unique identifier. The order of these CONNECT elements is important or the schedule view will not contain the correct links.

The SCHEDULE\_DATA domain is expected to be a list of user names and 32 bit schedule fields separated by a tab. An example of one such element of this list would be:

John Smith<tab>16777212

Please note that 16777212 is the integer value which translates to the bit field 000000001111111111111111111100. A one represents a half hour when Mr. Smith is busy and a zero stands for free time. The bit field is read from the least significant bit first, i.e. from right to left, with 8 am represented by the right-most bit. As we are dealing with a twelve hour period and each bit stands for a half hour, only the first 24 bits are important. The last byte is disregarded.

The rendered widget is displayed as series of horizontal rectangular blocks (per user), with each block representing half an hour. Half hour blocks of free time are displayed differently than the other blocks (busy) in terms of color and size.

## Radio Button Group

An alternative way to present a set of code table values is as a radio button group, each radio button representing a code table item. To display in the form of radio



buttons, a field representing a code table value should be mapped to the SHORT\_CODETABLE\_CODE domain or to a domain directly inheriting from SHORT\_CODETABLE\_CODE.

## Pop-up Pages

This section describes how to set up a pop-up page. The Cúram application has a number of built-in pop-up pages such as the Date Selector pop-up described earlier which are “helpers” used to enter data. Developers are also allowed to specify their own pop-up pages. For example, when scheduling a meeting for a person you don't want the user to have to know or fill in that persons unique ID. Instead the user should be provided with a search facility or a pre-populated list of valid options they can select from. This is achieved in Cúram with pop-up pages.

The out-of-the-box pop-up widget has a input field (grey in color) with a search - in the form of a magnifying glass - and a clear icon beside it. When the user clicks on the search icon this will activate a pop-up page. The user can select an item from the pop-page which will populate the text input field on the pop-up widget.

The following sections describe the steps involved in creating a pop-up.

### Configure the Pop-up Page

The first step is to configure the pop-up page. This is performed by the POPUP\_PAGES element in curam-config.xml.

```
<POPUP_PAGES DISPLAY_IMAGES="true|false">
  <CLEAR_TEXT_IMAGE>Images/minus.gif<CLEAR_TEXT_IMAGE>
  <POPUP_PAGE PAGE_ID="PersonSearch"
    CREATE_PAGE_ID="RegisterPerson"
    CONTROL_TYPE="textunderline|textinput"
    CONTROL_EDITABLE="true|false"
    CONTROL_INSERT_MODE="overwrite|insert|append">
    <DOMAIN>PERSON_ID</DOMAIN>
    <WIDTH>800</WIDTH>
    <HEIGHT>600</HEIGHT>
    <SCROLLBARS>true</SCROLLBARS>
    <IMAGE>Images/search.gif</IMAGE>
    <LABEL>Search</LABEL>
    <CREATE_IMAGE>Images/new.gif</CREATE_IMAGE>
    <CREATE_LABEL>New</CREATE_LABEL>
  </POPUP_PAGE>
</POPUP_PAGES>
```

*Figure 100. Pop-up Configuration Example*

On the root element the DISPLAY\_IMAGES attribute can be used to configure whether images or text is used for the actions which open a pop-up or clear the currently selected value.

The nested elements are:

**CLEAR\_TEXT\_IMAGE** : The location of the image to use as a “clear this text” button. Note that this is an application wide setting.

**POPUP\_PAGE** : For each domain definition which requires a pop-up there must be instance of this element. Up to two pop-ups can be associated with a single domain; one to search for an existing item, another to create a new item. The following attributes and child elements control various aspects of how the pop-up is presented to the user.

Table 124. Attributes of the *POPUP\_PAGE* element.

Name	Description
PAGE_ID	Specifies the UIM page id of the pop-up page to open to search for an existing item.
CREATE_PAGE_ID	Specifies the UIM page id of the the pop-up page to open to create a new item.
CONTROL_TYPE	Specifies the type of control where the value returned from the pop-up will be written to. The default value is <code>textunderline</code> which displays static text with an underline. To display a text input field set the value to <code>textInput</code> . When a text input control is configured, on the UIM FIELD which uses a pop-up, the HEIGHT attribute can be used to change from a single line text input to a multi-line text area.
CONTROL_EDITABLE	This attribute is only valid when CONTROL_TYPE is set to <code>textInput</code> . It controls whether the text input field is editable or not. Set to true to create an editable field and false to create a non-editable field. Note that Internet Explorer does not give any visual indication that the text input field is not editable.
CONTROL_INSERT_MODE	This attribute is only valid when CONTROL_TYPE is set to <code>textInput</code> . It allows you to configure how a value selected from a pop-up is inserted into the associated input control. The default is <code>overwrite</code> which means the selected value will overwrite the previous contents. Setting the attribute to <code>insert</code> means the selected value will be inserted at the current cursor position. Setting the attribute to <code>append</code> means the selected value will be appended to the previous contents of the input control.

Table 125. Child elements of the *POPUP\_PAGE* element.

Name	Description
DOMAIN	Domain used to identify this pop-up page. If a FIELD element with a TARGET connection is based on this domain, a pop-up will be used instead of a standard text entry box.
CT_CODE	This is a second way to identify a pop-up page. The attribute contains a code table code value and is used when associating multiple pop-up pages with a single field and is described in further detail below.
WIDTH	Width in pixels of pop-up dialog. This element is optional. If not included, the default width of 600 pixels will be used.
HEIGHT	Height in pixels of pop-up dialog. This element is optional. If not included, the height will be automatically calculated based on the page contents.
IMAGE	Location of image which when clicked launches the pop-up defined by the POPUP_PAGE element's PAGE_ID attribute.
IMAGE_HOVER	Location of image that is displayed when a user hovers over the search pop-up icon. Set the IMAGE_HOVER element if the IMAGE element has been set to a location other than the default location. If the IMAGE_HOVER element is not set, then a default image is displayed when a user hovers over a search pop-up icon.

Table 125. Child elements of the POPUP\_PAGE element. (continued)

Name	Description
IMAGE_PROPERTY	Optional key in the CDEJResources.properties file under which the locale-specific location of the pop-up launcher image otherwise specified by IMAGE attribute is stored. If the IMAGE is also specified for the same configuration, it will take precedence over the IMAGE_PROPERTY and this attribute will be ignored.
HIGH_CONTRAST_IMAGE	Location of the high contrast image which when clicked launches the pop-up defined by the POPUP_PAGE element's PAGE_ID attribute.
HIGH_CONTRAST_IMAGE_PROPERTY	Optional key in the CDEJResources.properties file under which the locale-specific location of the pop-up launcher image otherwise specified by HIGH_CONTRAST_IMAGE attribute is stored. If the HIGH_CONTRAST_IMAGE is also specified for the same configuration, it will take precedence over the HIGH_CONTRAST_IMAGE_PROPERTY and this attribute will be ignored.
LABEL	Alternate text for the image defined by the IMAGE element. If the POPUP_PAGE element's DISPLAY_IMAGES attribute is set to false, this text will be displayed instead of the image.
LABEL_PROPERTY	Optional key in the CDEJResources.properties file under which the locale-specific value of the label attribute otherwise specified by the LABEL attribute is stored. If LABEL is also specified for the same configuration, it will take precedence over the LABEL_PROPERTY and this attribute will be ignored.
CREATE_IMAGE	Location of image which when clicked launches the pop-up defined by the POPUP_PAGE element's CREATE_PAGE_ID attribute.
CREATE_IMAGE_PROPERTY	Optional key in the CDEJResources.properties file under which the locale-specific location of the pop-up launcher image otherwise specified by CREATE_IMAGE attribute is stored. If the CREATE_IMAGE is also specified for the same configuration, it will take precedence over the CREATE_IMAGE_PROPERTY and this attribute will be ignored.
CREATE_LABEL	Alternate text for the image defined by the CREATE_IMAGE element. If the POPUP_PAGE element's DISPLAY_IMAGES attribute is set to false, this text will be displayed instead of the image.
CREATE_LABEL_PROPERTY	Optional key in the CDEJResources.properties file under which the locale-specific value otherwise specified by the CREATE_LABEL attribute is stored. If the CREATE_LABEL is also specified for the configuration, it will take precedence over the CREATE_LABEL_PROPERTY and this attribute will be ignored.

## Create the Pop-up Page

A Cúram pop-up page is written in UIM. It can be written to display a set of existing items for the user to select from or to register a completely new item.

### A pop-up which returns existing items:

The following is an example of a pop-up page which accepts user input, displays a list of search results, one of which can be selected and its unique identifier returned to the parent page.

```
<PAGE PAGE_ID="Person_search" POPUP_PAGE="true">
  <PAGE_TITLE ICON="PersonSearchPageIcon">
    <CONNECT>
      <SOURCE NAME="TEXT"
```

```

        PROPERTY="PageTitle.StaticText1"/>
    </CONNECT>
</PAGE_TITLE>
<SERVER_INTERFACE NAME="ACTION"
    CLASS="Person"
    OPERATION="search"
    PHASE="ACTION"
/>
<CLUSTER NUM_COLS="2" TITLE="Cluster.Title.SearchCriteria">

    <ACTION_SET ALIGNMENT="CENTER" TOP="false">
        <ACTION_CONTROL LABEL="ActionControl.Label.Search"
            TYPE="SUBMIT" DEFAULT="true">
            <LINK PAGE_ID="THIS"/>
        </ACTION_CONTROL>
        <ACTION_CONTROL LABEL="ActionControl.Label.Cancel"
            IMAGE="CancelButton" TYPE="DISMISS"/>
    </ACTION_SET>

    <FIELD LABEL="Field.Label.ReferenceNumber">
        <CONNECT>
            <TARGET NAME="ACTION"
                PROPERTY="personSearchKey$referenceNumber"/>
        </CONNECT>
    </FIELD>
</CLUSTER>

<LIST TITLE="List.Title.SearchResults">
    <CONTAINER LABEL="Container.Label.Action">
        <ACTION_CONTROL LABEL="ActionControl.Label.Select"
            TYPE="DISMISS" >
            <LINK>
                <CONNECT>
                    <SOURCE NAME="ACTION" PROPERTY="dtls$personID" />
                    <TARGET NAME="PAGE" PROPERTY="value" />
                </CONNECT>
                <CONNECT>
                    <SOURCE NAME="ACTION"
                        PROPERTY="dtls$personFullName" />
                    <TARGET NAME="PAGE" PROPERTY="description" />
                </CONNECT>
            </LINK>
        </ACTION_CONTROL>
    </CONTAINER>
    <FIELD LABEL="Field.Title.ReferenceNumber">
        <CONNECT>
            <SOURCE NAME="ACTION" PROPERTY="dtls$referenceNumber"/>
        </CONNECT>
    </FIELD>
    <FIELD LABEL="Field.Title.FirstName">
        <CONNECT>
            <SOURCE NAME="ACTION" PROPERTY="dtls$personName"/>
        </CONNECT>
    </FIELD>
</LIST>
</PAGE>

```

The points to note about this example are:

- The PAGE\_ID attributes of the UIM PAGE element and the POPUP\_PAGE element in curam-config.xml must match.
- The POPUP\_PAGE attribute of the UIM PAGE element must be set to true.
- The submit action is linked to THIS. This means the page will be redisplayed after the submit button is pressed.

- To cancel the pop-up an action control of type DISMISS is used. If the action control does not have a child LINK element, the pop-up will be closed without returning any values to the parent page which opened it.
- The search results list in this example is made up of three columns. The first contains a link which will close the pop-up and return the selected values, the remaining columns display further information about the person.
- To close the pop-up and return values, an action control of type DISMISS is used. This is placed in a CONTAINER so it is the first column in the search results list. The user can click this link to select one of the search results.
- To specify what values should be returned a child LINK element is added to the action control. When used in an action control to close a pop-up all standard attributes of the LINK element (e.g. PAGE\_ID) have no meaning and will be ignored.
- For Cúram pop-up pages two values must always be returned. These are specified using CONNECT elements. Both connections must use a target of PAGE and have the PROPERTY set to value and description. The value connection specifies the value required on the page that opened the pop-up, in this example the persons unique record ID. The description connection specifies descriptive text to be shown to the user, in this example the person's name. So, on the page which opened the pop-up, the person's name will be displayed to the user, but it is their unique ID which will be submitted to the server.

It is not necessary for pop-up pages to accept input. For example, the LIST can be populated from a display phase server interface if necessary.

#### **A pop-up which creates a new item:**

A pop-up may also create a new item and have the newly generated unique identifier for that item returned to the parent page. To do this create a page which a ACTION\_CONTROL of type SUBMIT\_AND\_DISMISS must be used. For example;

```
<ACTION_CONTROL TYPE="SUBMIT_AND_DISMISS" LABEL="Button.Submit">
  <CONNECT>
    <SOURCE NAME="ACTION" PROPERTY="dtls$personID" />
    <TARGET NAME="PAGE" PROPERTY="value" />
  </CONNECT>
  <CONNECT>
    <SOURCE NAME="ACTION"
      PROPERTY="dtls$personFullName" />
    <TARGET NAME="PAGE" PROPERTY="description" />
  </CONNECT>
</ACTION_CONTROL>
```

Once the type attribute is set to SUBMIT\_AND\_DISMISS the rules for the child LINK and CONNECT element is the same as described in the previous section for a DISMISS action control. After the form is successfully submitted the pop-up will be dismissed and the new values returned to the parent page.

### **Using the Pop-up Page**

Pop-up pages are opened using standard UIM FIELD elements. If the field has a target connection which is based on a domain as configured in curam-config.xml a link to open the pop-up will be generated rather than a standard text entry field. This is illustrated in the screen shot above with the “Preferred Office” input field.

The following is the most basic example of a FIELD opening a pop-up. It is from an insert page so only a target connection is specified. Using the current example, the person's unique ID will be assigned to the field specified in the target connection and the person's name will only be used for visual purpose to display to the user.

```

<FIELD LABEL="Field.Label.person">
  <CONNECT>
    <TARGET NAME="ACTION" PROPERTY="personID"/>
  </CONNECT>
</FIELD>

```

*Figure 101. Opening a Pop-up from an Insert Page*

The following example is from a modify page which means the field will have a source value which must be displayed to the user. It is slightly more complex than standard fields on a modify page because there are actually two source values to handle. The person's unique ID and the person's name. In this case the INITIAL connection is used to specify the person's name. This will only be used to display to the user and note that is not submitted to the server. Following that the field is just like any other on a modify page. The source connection specifies the existing value of the field, the target connection specifies where the value should be submitted to.

```

<FIELD LABEL="Field.Label.person">
  <CONNECT>
    <INITIAL NAME="DISPLAY" PROPERTY="personName"/>
  </CONNECT>
  <CONNECT>
    <SOURCE NAME="DISPLAY" PROPERTY="personID"/>
  </CONNECT>
  <CONNECT>
    <TARGET NAME="ACTION" PROPERTY="personID"/>
  </CONNECT>
</FIELD>

```

*Figure 102. Opening a Pop-up from a Modify Page*

When invoking a pop-up it is also possible to supply page parameters to the pop-up. This is a slight variation on the two examples above and involves the use of the LINK element. The following is an example of two parameters passed to a pop-up page, one sourced from an existing page parameter, the other from a server interface property. When a LINK element is used in this context no attributes such as PAGE\_ID should be specified. Also a TEXT source connection cannot be used to supply a parameter to a pop-up page.

```

<FIELD LABEL="Field.Label.person">
  <CONNECT>
    <TARGET NAME="ACTION" PROPERTY="personID"/>
  </CONNECT>
  <LINK>
    <CONNECT>
      <SOURCE NAME="PAGE" PROPERTY="personID"/>
      <TARGET NAME="PAGE" PROPERTY="param1"/>
    </CONNECT>
    <CONNECT>
      <SOURCE NAME="DISPLAY" PROPERTY="personName"/>
      <TARGET NAME="PAGE" PROPERTY="param2"/>
    </CONNECT>
  </LINK>
</FIELD>

```

*Figure 103. Supplying Parameters to a Pop-up Page*

## Using Multiple Pop-up Search Pages for a Single Field

In some cases we need to search for different types of Cúram entities but that search is associated with a single field. For example you may have a requirement to search for a Cúram client which has a generic domain of CURAM\_CLIENT\_ID. This

could be a person, an employer, a product provider etc. Individual search pages may already exist for these types so you should be able to reuse them. Assuming the pop-up search pages already exist, this involves two extra steps which are described in the following sections and. The resulting pop-up widget is as described in “Pop-up Pages” on page 247 except that there is an additional drop-down field rendered to the left of the text input field. In order to activate the pop-up page for this widget, the user first selects the type of search to be performed from the drop down list and then clicks on the search icon.

### Configure the Multiple Pop-up Page

This can be configured through the `MULTIPLE_POPUP_DOMAINS` element in `curam-config.xml`. The following is an example:

```
<MULTIPLE_POPUP_DOMAINS>
  <CLEAR_TEXT_IMAGE>Images/clear.gif</CLEAR_TEXT_IMAGE>
  <MULTIPLE_POPUP_DOMAIN>
    <DOMAIN>CURAM_CLIENT_ID</DOMAIN>
    <LABEL>Search</LABEL>
    <IMAGE>Images/search.gif</IMAGE>
  </MULTIPLE_POPUP_DOMAIN>
</MULTIPLE_POPUP_DOMAINS>
```

*Figure 104. Multiple Pop-up Domains*

The nested elements are:

`CLEAR_TEXT_IMAGE` : The location of the image to use as a “clear this text” button. This is an application wide setting.

`MULTIPLE_POPUP_DOMAIN` : For each domain which you wish to associate multiple pop-up windows create an instance of this element.

`DOMAIN` : The name of the domain which is associated with multiple pop-up windows

`IMAGE` : Location of image to be used for pop-up icon.

`LABEL` : Alternate text to be used for pop-up icon.

As shown above, when using multiple pop-up pages a drop-down list is required to select the pop-up type. This drop-down list is populated as normal from a code-table. The code-table codes are the link between the drop-down list and pop-up that is opened. This requires the `CT_CODE` child element of the `POPUP_PAGE` element to be set to the code-table code value.

### Using the Multiple Pop-up Page

Once the configuration is done the final step is the write the UIM necessary to display the pop-up search.

```

<CONTAINER LABEL="Label.person">
  <FIELD LABEL="Field.Label">
    <CONNECT>
      <TARGET PROPERTY="popupType" NAME="ACTION"/>
    </CONNECT>
  </FIELD>
  <FIELD LABEL="Field.Label">
    <CONNECT>
      <TARGET PROPERTY="clientID" NAME="ACTION"/>
    </CONNECT>
  </FIELD>
</CONTAINER>

```

Figure 105. UIM to Use Multiple Pop-up Windows

The main points to note are:

- A CONTAINER and two FIELD elements are required, one for the drop-down list, the other for the value which will be returned from the pop-up. The container must not include any other FIELD elements.
- The first field should be based on a code-table domain which contains a list of codes which corresponds to the CT\_CODE element described earlier.
- The second field should have a target connection which is based on a domain using the MULTIPLE\_POPUP\_DOMAIN element.

## Agenda Player

The Agenda Player (or player for short) is a wizard-like control which provides guided navigation through a specified set of screens. As the name implies the screens in the Agenda Player are supposed to be part of a certain agenda or scenario, most typically involving step-by-step collecting of information.

**Note:** Agenda Player widget is not supported outside the modal dialog context, an attempt to open it in the tab content panel or elsewhere (e.g., as the inline page of an expandable list) will lead to an explicit error message stating this.

### Agenda Player screen structure

Depending on how the Agenda Player player is configured, the screen is divided into either three or four parts:

- Along the top is the Agenda Player header. It contains a customizable Agenda Player title on the left and, where appropriate, a progress bar on the top right, which shows the user's progress through the agenda. The steps completed in the progress bar will be shaded in color whereas the steps that have yet to be completed will not.
- On the left of an Agenda Player, a navigation panel (optional) shows the list of pages in the current agenda. The user's progress through the sequence is continuously displayed there (in addition to progress bar) by highlighting of the current page. The appearance and behavior of the other pages in the agenda depends on the mode used (see below). The pages in an agenda can be grouped into sections and the player provides the ability to collapse and expand visited sections.

At the bottom of the navigation panel is the summary link, which allows users to jump directly to the player summary page (they would also get there by navigating through all the pages in the agenda). The summary link is only displayed if there is an appropriate element specified in the agenda XML. The navigation panel is not displayed in the navigator-less (claimant) view of the Agenda Player.



- Along the bottom, a set of buttons is displayed to allow the user to step forward and back through the Agenda Player. There are also buttons to jump to the summary page (displayed optionally) and to quit the Player.

**Note:** The text used for these buttons can be customized (see below). However, for the remainder of this section they are further referred as the **Back**, **Next**, **Finish** and **Cancel** buttons, which are their default captions.

- The main area of the screen is the content area. This area displays normal client pages which might also be used outside of the Agenda Player.

## Navigation modes

In addition to using the back and next buttons to navigate through an agenda, the player can provide additional options in the navigation panel, depending on the mode used.

The Agenda Player can be configured to operate in one of three navigation modes: basic, incremental or full, with incremental mode being the default.

- The basic mode is used for strictly sequential navigation through the agenda pages. In this mode the navigation panel is just used for additional information, indicating which page the user is currently on. The only navigation means are the standard player buttons.
- The incremental mode expands on the basic mode by providing links in the navigation panel to any pages which have already been visited. A user can use these links to skip back and forward between previously visited pages, but will still need to use the next button to progress any further.
- The full mode is actually a non-sequential mode as all the navigation panel elements are initially rendered as links. Sequential advancing is possible here as well, as the player buttons are fully functional, but there are no restrictions placed on the order in which you navigate through the agenda. This, however, means that things related to the sequential progress might be unavailable, or not work properly in this mode (for example, the progress bar is not displayed for this mode at all; dynamic parameters might not be available if a screen which expects these parameters is visited before the one where these parameters are initialized, etc.). Because of this the full navigation mode should be used where specifically required and the agenda should be designed/configured keeping in mind the possible consequences.

Agenda Player mode configuration is described in “Agenda Player Configuration” on page 256

**Note:** Within the Player screens there might be hyperlinks leading to other pages, which open in the client area, yet do not belong to the specified Player screen set. In this case all the navigation means on the Player, including buttons and links rendered for incremental or full mode are disabled until the flow returns back to an Agenda Player screen. This means in particular that such a 'side' page should provide means of returning to the AgendaPlayer page flow (by linking to the appropriate page or closing the modal opened from the Player).

## Navigator-less View

By default, an Agenda Player is displayed with all the screen parts present. However, in some situations, you may like to simplify the view and behavior of the player using the view without the navigation panel (also called Claimant view after the expected usage - i.e. online claimants). In this view Agenda Player is displayed without the navigation panel. Only the standard player buttons can be used for navigation, so the mode setting is effectively ignored.

The fourth player button, **Finish**, is automatically available on the button bar at the bottom of the page for the Claimant view. The button makes it possible to jump directly to the summary page rather than having to advance to it through all the pages. It is shown only when there is a summary page present in the agenda XML returned from the server.

Player configuration to allow for Claimant view is described in the section below.

## Agenda Player Configuration

The Agenda Player can be configured by adding/modifying entries in AgendaConfig.xml. A version of this file should be in your components directory.

The following is an example of the Agenda Player configuration file contents:

```
<AGENDA>
  <PLAYER ID="DefaultConfig" TITLE="Default.Title"
    MODE="incremental" CONFIRM-QUIT="false"/>
  ...
  <PLAYER ID="Claimant.Config" TITLE="Claimant.Title"
    NAVIGATOR-HIDDEN="true" MODE="incremental"
    CONFIRM-QUIT="true"/>
</AGENDA>
```

The attributes that can be used for particular configuration (PLAYER element) are as follows.

Table 126. Attributes of the PLAYER element

Attribute	Description
ID	The ID of this particular configuration (referred to by CONFIG attribute of FIELD element in UIM which contains Agenda Player).
TITLE	Title key for Agenda Player title, displayed on its header. This key is used to look up customized/localized title from appropriate properties file as described in "Agenda Player Customization."
MODE	This attribute allows for specifying Agenda Player navigation mode. It might have values of basic, incremental or full, incremental being the default one, used if the attribute is skipped in an configuration.
NAVIGATOR-HIDDEN	When this attribute is specified and set to true, Agenda Player will be displayed in Claimant View (see above).
CONFIRM-QUIT	This attribute can be used to display a confirmation dialog when a user clicks on the <b>Cancel</b> button. When present and set to true, a confirmation dialog will be displayed to confirm the user's intention to quit the Agenda Player or to cancel and return to the player.

## Agenda Player Customization

The Agenda Player comes with support for customization/localization of certain elements. The elements which can be customized are the player title, Progress Bar text, the player button texts, the quit confirm dialog text and descriptions for each of the frames in the player.

Player related properties are kept in the files <client-dir>/components/<component\_name>/CDEJResources.properties and <client-dir>/components/<component\_name>/AgendaPlayer.properties. where <component\_name> represents the name of the component where the customizations are being applied.

Player title is customized by specifying custom value under the key used for it in AgendaConfig.xml (see above). The value under the key is to be placed into AgendaPlayer.properties.

The Progress Bar text is customized within an Agenda Player header by modifying the AgendaPlayer.properties file to include values for the keys: Progress.Bar.Prefix, Progress.Bar.Middle, Progress.Bar.Suffix. Please note that all three keys must be present with blank values for unused ones in order to ensure clean rendering of the customized Progress Bar text. If this is not the case then a situation may occur where a non-blank default value is used instead of one undefined.

The text strings associated with Agenda Player control buttons are customizable in the file CDEJResources.properties and defined by properties wizard.button.back.title, wizard.button.forward.title, wizard.button.finish.title, and wizard.button.quit.title.

The frame descriptions are useful for users of screen readers but don't appear visually on the screen. The entries for frame description customizations in CDEJResources.properties are wizard.frameset.title, wizard.header.frame.title, wizard.navigation.frame.title, wizard.content.frame.title, wizard.button.frame.title.

**Note:** The Agenda Player was formerly known as the Wizard widget, so several attribute and property names still refer to wizard.

In order to change the default question in the quit confirmation dialog, the property Quit.Dialog.Question should be added/changed in AgendaPlayer.properties.

## Player data

There are some specific UIM pages related with Agenda Player:

- Navigation page: Each Player requires a navigation page that will become the navigation panel of the Agenda Player. This page has two required characteristics. First, the root PAGE element has a TYPE of SPLIT\_WINDOW. This indicates that the page will form part of a frame-set. Second, the page contains a field with a single source connection and domain type AGENDA\_XML. This field supplies the Agenda Player with the list of pages, parameters and other information that drives the Agenda Player.
- Summary page: This page is optional and might just be a regular UIM page. However, summary page, specifically displaying summary of visited and unvisited pages is also available. If this information is to be displayed in a summary page, a WIDGET element with TYPE attribute set to WIZARD\_SUMMARY should be present among page elements.
- Exit page: This is a regular UIM page to which the user is forwarded after quitting the player.

The following is an example of the UIM used to specify the navigation page. It contains a single field which supplies the agenda XML data.

```

<PAGE PAGE_ID="WizardTest" TYPE="SPLIT_WINDOW">

  <PAGE_TITLE>
    <CONNECT>
      <SOURCE NAME="TEXT" PROPERTY="page.title"/>
    </CONNECT>
  </PAGE_TITLE>

  <SERVER_INTERFACE NAME="DISPLAY" CLASS="Agenda"
    OPERATION="getAgenda"/>

  <PAGE_PARAMETER NAME="agendaRef"/>

  <CONNECT>
    <SOURCE NAME="PAGE" PROPERTY="agendaRef"/>
    <TARGET NAME="DISPLAY" PROPERTY="key$agendaRef"/>
  </CONNECT>

  <CLUSTER SHOW_LABELS="false">
    <FIELD>
      <CONNECT>
        <SOURCE NAME="DISPLAY" PROPERTY="agendaXML"/>
      </CONNECT>
    </FIELD>
  </CLUSTER>

</PAGE>

```

The following is an example of a specific summary page:

```

<PAGE PAGE_ID="WizardSummary">

  <PAGE_TITLE>
    <CONNECT>
      <SOURCE NAME="TEXT" PROPERTY="Page.Title"/>
    </CONNECT>
  </PAGE_TITLE>

  <CLUSTER SHOW_LABELS="false" TITLE="Cluster.Title">
    <WIDGET TYPE="WIZARD_SUMMARY"/>
  </CLUSTER>

</PAGE>

```

The agenda data that drives the Player looks like this:

```

<?xml version="1.0" encoding="UTF-8"?>
<agenda>
  <page-flow>
    <section description="First section"
      status="SCT1">
      <page id="Person_homePage" description="Home"
        status="SC1" initial="true"
        submittonnext="true"/>
    </section>
    <section description="Second section"
      status="SCT2">
      <page id="Person_listAddress" status="SC2"
        description="Addresses"/>
      <page id="Person_listBankAccount" status="SC1"
        description="Bank Accounts"
        submittonnext="true"/>
      <page id="Person_listCommunication" status="SC3"
        description="Communications"/>
      <page id="Person_listTask" status="SC2"
        description="Tasks"/>
      <page id="Person_listCitizenship" status="SC2"
        description="Citizenships"/>
    </section>
  </page-flow>
</agenda>

```

```

        <page id="Person_listFinancial" status="SC2"
            description="Financial"/>
        <page id="Person_listNote" status="SC4"
            description="Notes"/>
    </section>
    <summary id="WizardSummary"
        description="Summary Page"
        close-on-submit="true"
        status="SCT3"/>
</page-flow>
<parameters>
    <parameter name="concernRoleID" value="101"/>
    <parameter name="dynamicParam" value="0"/>
</parameters>
<exit-page id="Person_homePage">
    <parameters>
        <parameter name="concernRoleID" value="101"/>
    </parameters>
</exit-page>
</agenda>

```

There is one page element per screen to be displayed in the Agenda Player. The attributes that can be used in this element are as follows.

*Table 127. Attributes of the page element*

Attribute	Description
id	The page id for the page (as set in the PAGE_ID of the PAGE element in the page's UIM definition).
description	The description of the page that will be displayed in the Navigation Panel.
status	A status code that is mapped to an image.
initial	Set to true if this is the page that should be displayed when the Agenda Player is first opened.
disableback	Set to true if the <b>Back</b> button should be disabled on this page.
disableforward	Set to true if the <b>Forward</b> button should be disabled on this page.
submitonnext	Set to true if the <b>Forward</b> button should submit the form on this page.
close-on-submit	This attribute applies to summary element only and allows for alternative way of quitting the player, as described below.

The important features to note are:

- The sequence of screens in the Agenda Player is exactly as listed in the agenda data.
- One of the pages in the Agenda Player can be marked as the start page by setting the initial attribute to true. When the Agenda Player is first displayed, this page will be loaded but it will still be possible to navigate back to previous pages. If the Player is configured to use incremental mode, pages prior to the initial pages on the navigation panel will be rendered as hyperlinks; for a full navigation mode all the page items except current one will be hyperlinks.
- In the XML sent back by the application server, the page elements might be contained within section elements or there might be no section element at all. The optional summary element, however, is to be always placed directly within page-flow.

- All pages in the Agenda Player take the same set of parameters or a subset thereof. These parameters are specified in the agenda data.
- Page parameters can also be dynamic. These parameters initially carry special value of 0 (note dynamicParam in the Agenda Player sample data above) and are intended to be initialized during user interaction with Agenda Player (e.g., user ID is only available after a user registers herself).
- The exit-page denotes the page which the user will be taken to when the **Cancel** button is clicked. This page will completely replace the Agenda Player and can be any page in the application with any parameters (matching those specified by exit-page parameter sub-elements in agenda XML from the server).
- When submitonnext is set for a page, the submit button on that page (there should only be one) will be hidden when it is displayed within the player. The player's **Next** button can be used to submit the form instead and will proceed to the next page if no validation error occurs. If there are validation errors, the page will return to itself displaying the validation errors on the top, as it would for any other application page.

To allow for pages where the record itself is optional (i.e. you could move on to the next screen without creating one), but some of the fields are mandatory, if you do try to create a record, the infrastructure will not perform mandatory field validations if no value has been entered/chosen for any field on the page. The appropriate server interface will still be called, so it is up to the application logic to work out what was intended (e.g. don't create a record, delete an existing record, etc.). This behavior only applies when using the submitonnext feature.

- The summary page can provide an alternative way to quit the Player. In order to do this, the summary page should contain a submit button, and the summary element in the agenda XML from the server should have close-on-submit specified and set to be true. If the user clicks on the submit button on such a summary page and the submit succeeds, the player closes down and the user is forwarded to whatever page is specified by the link associated with the submit button.
- Each page can be assigned a status code using the status. These status codes can be anything at all as long as they are mapped in the ImageMapConfig.xml file under the domain AGENDA\_XML. When the list of pages is displayed in the left column, each will have an icon attached corresponding to its status code.

The following is an example of mapping status codes to images the ImageMapConfig.xml file.

```
<domain name="AGENDA_XML">
  <locale name="en">
    <mapping value="SC1" image="Images/Wizard/status1.gif"
      alt="English text..." />
    ...
    <mapping value="SC4" image="Images/Wizard/status4.gif"
      alt="English text..." />
  </locale>
  <locale name="fr">
    <mapping value="SC1" image="Images/Wizard/status1.gif"
      alt="French text..." />
    ...
  </locale>
</domain>
```

The appearance of the Agenda Player control buttons, the summary screen and the navigation is defined in CSS. For details, please see “Cascading Stylesheets” on page 33.

The UIM CONDITION element allows for the conditional display of action controls, clusters or lists on a page that is displayed within an Agenda Player (see See “CONDITION” on page 68 for more details on the condition element). To hide/display elements based on whether the page is in an Agenda Player or not, the NAME and PROPERTY attributes can only have the values CONTEXT and inWizard respectively.

```
<ACTION_SET ...>
  <CONDITION>
    <IS_TRUE NAME="CONTEXT" PROPERTY="inWizard"/>
  </CONDITION>
  ...
</ACTION_SET>
```

Figure 106. Condition example:

This indicates that the action set should be displayed only when that Action Set is on a page that is displaying within a Agenda Player.

## LOCALIZED\_MESSAGE Domain

The LOCALIZED\_MESSAGE domain allows entries in a server message catalog to be displayed on a client screen. The domain is string based but expects the string to be formatted in specific way. The Cúram Server Development Environment (SDEJ) provides support for formatting a message catalog entry in this way so it can be returned to the client. See the *Cúram Server Developers Guide* for full details on working with message catalogs.

Once the message catalog entry has been formatted on the server side it should be assigned to a field which is based on the LOCALIZED\_MESSAGE domain and returned to the client. The message entry will be displayed according to the current locale and values will be assigned to the message placeholders.

## Decision Assist: Decision Matrix Widget

### Overview

The Decision Matrix widget is a control that is used to construct questionnaires. Refer to the *Decision Assist Administration Class and Widget Overview* chapter in the *Inside Cúram Decision Assist* Guide for more details.

---

## Custom Data Conversion and Sorting

Use this information to learn about data formatting, parsing, validation, and sorting behavior in the Cúram web application.

Custom data conversion and sorting allows most aspects of the management of data in the presentation layer of Cúram applications to be customized. Customizations can control how data is formatted, parsed, validated and sorted; error reporting can also be customized and controlled. Operations are performed on data values according to a well-defined data life-cycle and, at each stage, the operations can be customized. To understand how, when, and where to customize the operations, you must first understand the operations available and how they fit into the life-cycle.

### warning: Unsupported Customizations

This chapter describes the supported mechanisms for the customization of data conversion and comparison operations. For completeness, and to aid

understanding, some operations are described, but the corresponding customization mechanisms are not documented, as customization of these operations is not supported (or not supported using the programmatic mechanisms described here).

The descriptions of the Java interfaces and classes presented here may be incomplete, as unsupported methods may be omitted from their descriptions for clarity. However, the JavaDoc documentation for these interfaces and classes may include more information and describe more comprehensive customization mechanisms, but only the mechanisms described here are supported.

## Data Conversion and Sorting Operations

There are a number of operations that are carried out on data values by the client infrastructure. Some are controlled by the domain definition options that were set in the UML model and are performed automatically, others are controlled by domain-specific plug-ins that can be overridden and customized; these plug-ins will be described later. First, the operations that are performed on the data values need to be understood:

### **format**

When data is retrieved from the application server, it is represented by a Java object appropriate to the root domain of the data. For example, a value in the SVR\_INT64 domain is represented as a `java.lang.Long` object. The *format* operation is responsible for converting these objects to their string representation, as it is the string representation that must be embedded in the XHTML stream returned to the web browser.

A format operation is only required to return a non-null string; there are no other limitations. However, each domain-specific formatter will usually return a string representation of the Java object according to the usual conventions. For example, a money value may have a currency symbol added during formatting and be limited to two significant digits after the decimal point. For most data values, the formatter should generate a string representation that can later be converted back into the original data value.

### **pre-parse**

When a user enters values in a form on an application page and submits the form to the client application, the web browser submits all of these values in string format. These string values need to be parsed to create the appropriate Java object representations, but first a *pre-parse* operation is performed to prepare the string for parsing.

The UML model supports several domain definition options that are recognized by the pre-parse operation (see the *Cúram Modeling Reference Guide* for more information on domain definition options). The domain definition options may indicate that leading and trailing whitespace characters should be trimmed from the string, that all sequences of whitespace characters should be compressed to single space characters, and that the string should be converted to upper-case. The pre-parse operation applies these options automatically to the string values and the modified string values are then ready to be parsed. The pre-parse operation is controlled and customized by setting these domain definition options in the UML model.

**parse** After the pre-parse operation has completed, the *parse* operation must convert the resulting string value into its Java object representation before it can be submitted to the application server. In general, the parse operation is the reverse of the format operation. If the format operation



formatted a money value to a string and added a currency symbol and grouping separator (e.g., thousands separator) characters, the parse operation must be able to remove these additions and create a Java object representation of the actual money value.

All that is required of the parse operation is to produce a Java object, it does not validate that value. However, while not explicitly a validation operation, the parse operation usually needs to perform some validation to ensure that the value can be parsed correctly. For example, a date may later be determined to be invalid if it is out of range, but the parse operation must first determine what the date value is and may fail if the string does not represent a date in any recognized format.

#### **pre-validate**

Like the pre-parse operation, the *pre-validate* operation is performed to apply domain definition options defined in the UML model. However, unlike the pre-parse operation, different domain definition options are applied to data values depending on the domain. The data is not modified. String and BLOB values are tested to ensure that they do not exceed their maximum or minimum defined sizes (or lengths), while numeric values are tested to ensure that they do not exceed their maximum or minimum values. Any failures will be reported as errors. See “Converter Plug-ins” on page 272 for a detailed description of the actual validations performed.

#### **validate**

The pre-validate operation is convenient and is applied automatically, but there are situations where it may not be able to validate data sufficiently. The *validate* operation is a catch-all that allows any kind of validation to be performed that is not possible using UML domain definition options alone. For example, ID values may be tested to see if their check-digit is valid. Errors can be reported if any value does not meet such specific conditions. Data is not modified by this operation.

#### **compare**

When a list of data is returned from the server, the sort order of the values in the list is determined using the *compare* operation. This sort order is used to support the sorting of lists on application pages when users click on the column headers. The compare operation is passed two data values (in their Java object representations, *not* in their formatted string representations) and must return a positive or negative number to indicate which comes first in the sort order. Like the format operation, the compare operation is not restricted in what calculations it performs, but it will typically sort values alphabetically or numerically.

Each data conversion operation has access to information about the active user's locale and to information about the domain being processed. It is also possible for one operation to access and execute any of the operations should that be necessary. For example, a format operation might format values differently for each locale and a compare operation might invoke the format operation before making a comparison.

## **Data Conversion Life Cycle**

The CDEJ infrastructure is responsible for the retrieval of data from the application server, the display of this data, the processing of user input, and the submission of data back to the application server. This process has a well-defined life cycle. Operations at each stage in the life cycle are performed in a domain-specific manner.

Not all data goes through each stage in the life cycle. Some data is displayed but not modified or resubmitted by the user (read-only); some data is created by the user and submitted without any initial value being retrieved from the application server (write-only); and some data is retrieved, modified by the user, and then resubmitted to the application server (read-write).

In the context of the value of a single property, the life cycle for reading the value is as follows:

1. The value is fetched from the application server by invoking a business operation.
2. If the value is one of a list of values for the same property, the related values are sorted using the compare operation and the resulting sort order is recorded.
3. The value is formatted to a string representation by the format operation and is stored for later display.
4. When the page is displayed, the value is retrieved and inserted into the XHTML stream.

The life cycle for writing a value is as follows:

1. A string representation of the value is entered on a form by the user and the value submitted.
2. The domain definition options for whitespace compression and trimming and for upper-case translation are applied to the string value by the pre-parse operation. The value remains in string form.
3. If the business operation has declared the value to be mandatory, the value is checked to ensure that it is not empty or null. An error will be reported if this check fails.
4. The value is parsed from its string representation by the parse operation and the resulting native Java object replaces the string value.
5. The domain definition options for the size range, value range, and pattern match are applied by the pre-validate operation is applicable. The value is not modified by this operation. If a validation fails, an error will be reported.
6. The value is validated by the validate operation to apply any arbitrary validation rules. Again, the value is not modified by this operation and validation failures are reported.
7. The parsed and validated value is sent to the application server.

For a value that is treated as read-write, the life cycle is simply the combination of the read-only life cycle followed by the write-only life cycle.

## The Domain Hierarchy and Domain Plug-ins

At each step in data life-cycle, knowledge of a value's domain is required to ensure that the correct processing is performed. Embedding this domain information in the application is one of the tasks performed by the application code generators. With this information available, the application can invoke data conversion and comparison operations tailored for each domain.

Not only is information about each domain available at run-time, information about the relationships between these domains is also available. A model of the *domain hierarchy* is maintained in memory using tree structures and all the necessary information about how values in the domains should be processed “hangs” from these trees.

The domain hierarchy is composed of nodes implementing the `curam.util.common.domain.Domain` interface. The main methods declared in this interface are listed below. For more information see the Cúram JavaDoc documentation for this interface.

- **`getName()`**  
This method is used to get the name of this domain.
- **`getParent()`**  
This method is used to get the parent domain of this domain if it exists.
- **`getRootDomain()`**  
This method is used to get the ultimate root domain of this domain.
- **`getChildren()`**  
This method is used to get the list of children of this domain.
- **`getPlugIn()`**  
This method is used to get the named plug-in object associated with this domain.

For the purposes of writing custom data conversion and comparison operations, this interface is rarely used directly, but it is instructive of the mechanism by which custom code is integrated into an application.

Each domain has a unique name: the name defined for it in the UML model. As domains can be derived from other domains, parent-children relationships exist, and these are also represented. Also, the root domain (the ultimate ancestor of any domain) is readily accessible. A root domain is one that does not have a parent domain. Several root domains (for dates, strings, integers, etc.) are supported in the Cúram application, so the domain hierarchy is represented by a “forest” of separate trees, rather than a single tree. All information about a domain, other than its name and relationships to other domains, is provided via *domain plug-ins*.

As described in the list above, the `curam.util.common.domain.Domain` interface also describes a method for the retrieval of plug-ins, `getPlugIn`, that takes the name of the type of plug-in required. The method returns the plug-in configured for the domain or the equivalent plug-in configured for the nearest ancestor domain if none has been configured directly; this is the simple inheritance mechanism. Domain plug-ins are Java classes that implement the data conversion and comparison operations and other features that are specific to each domain. There are four supported plug-in types, each with a unique plug-in name:

#### **“converter”**

Converter plug-ins are responsible for implementing the format, pre-parse, parse, pre-validate, and validate operations for each domain. Converter plug-ins can be customized to influence the appearance of values on an application page, to support the parsing of new data formats, and to prevent the submission of invalid data.

#### **“comparator”**

Comparator plug-ins are responsible for implementing the compare operation for each domain. Comparator plug-ins can be customized to influence the sorting of data.

#### **“default”**

Default plug-ins are responsible for providing default values for each domain when no value is available. While this type of plug-in can be customized freely, there will rarely be any need to modify the implementations provided within the Cúram application.

### “options”

Options plug-ins are responsible for providing access to the domain definition options that were defined in the UML model. This type of plug-in is built into the client infrastructure and cannot be customized.

The mechanism used to configure the domain plug-ins exploits the domain hierarchy to simplify the configuration dramatically: very few domains need to be configured, as domains that are not configured will inherit the configuration from their ancestor domains. Each root domain needs to be configured (so that every domain has an ancestor from which it can inherit its configuration), and a small number of specialized sub-domains are also configured further (the most notable being CODETABLE\_CODE, a derivative of the root domain SVR\_STRING). In all, less than 1% of domains are directly configured, so the configuration information is very manageable. The Cúram application comes complete with plug-in implementations and configuration information for all the domains used by the reference application; modifications are only required to handle specialized custom extensions.

## Overview of Domain Plug-ins

### Common Features of Plug-ins

Domain plug-ins are just Java classes that conform to a well-defined interfaces. There is a base interface that describes common features of all domain plug-ins and more specialized interfaces for each type of plug-in. At run-time, the infrastructure co-ordinates instantiation and invocation of all plug-ins, so the process of writing plug-ins is straightforward: methods need to be implemented that perform the data conversion and comparison operations and very little else needs to be considered.

All plug-in classes implement the `curam.util.common.domain.DomainPlugIn` interface. This defines some common operations and provides access to basic information that the plug-in may require. The main methods declared in this interface are listed below. For more information see the Cúram JavaDoc documentation.

- **getName()**  
This method is used to get the name of this plug-in (one of the four plug-in names described above).
- **getLocale()**  
This method is used to get the locale associated with this plug-in instance.
- **getDomain()**  
This method is used to get the domain applicable to this plug-in instance.
- **getInstance()**  
The final method is used to get an instance of a domain plug-in; it is not invoked in custom code. Instantiation issues are described in more detail in “Plug-in Instance Management” on page 295. You should use the default implementations of these methods provided by the Cúram plug-in classes.

The methods of the `DomainPlugIn` interface do not really do anything interesting. Derived interfaces define the specific operations that each type of plug-in performs.

## Converter Plug-ins

The `DomainConverter` interface is the one most likely to be used for customizations. It defines several simple methods that perform the main data conversion operations. They are listed as follows. For more information see the *Cúram* JavaDoc documentation for this interface.

- **`format()`**

This method is used to format the given object to a string representation.

- **`parse()`**

This method is used to parse the given string representation into an object.

- **`validate()`**

This method is used to validate an object according to the domain-specific constraints. It may throw an exception if the object is invalid, but does not modify the object or return any value.

- **`getDomainClass()`**

This method returns the class object that indicates the required type of the object that is passed to the other converter methods or returned by them.

- **`getGenericLocale()`**

This method is used to get the locale to be used when formatting or parsing generic values. This should be the “en\_US” locale and you should not change this value; it does not matter if this locale is not otherwise used in your application.

- **`formatGeneric()`**

This method is used to format the given object to a generic string representation.

- **`parseGeneric()`**

This method is used to parse the given generic string representation into an object of the appropriate type for the associated domain.

As described above, the `formatGeneric` and `parseGeneric` methods are similar to the `format` and `parse` methods, but they are used when converting the values of the domain definition options entered in the UML model by developers or of values embedded in XML-based data. Domain definition option values, for example: maximum date values, minimum size values, or regular expressions used for pattern matching; are extracted from the UML model at build-time and are parsed to their Java object representations at run-time, so that they can be used when validating data entered by a user. A similar process is used when extracting values from XML data returned from the application server and when constructing XML data before it is returned to the application server. The default implementations of the `formatGeneric` and `parseGeneric` methods are sufficient for all purposes (see “Generic Parse Operations” on page 297 for information on protecting the generic parse operation from side-effects).

It is by implementing these converter methods or overriding existing implementations of them that most customizations are performed. The simple method signatures disguise the fact that, via the inherited `DomainPlugIn` interface, each method has access to the active user's locale and the full domain information if necessary.

Implementations of the pre-parse and pre-validate operations are provided for all of the root domains in the *Cúram* application. As these operations are controlled completely by the setting of domain definition options in the UML model, there is rarely any need to customize them programmatically. However, there are circumstances where custom error messages are required, so you may need to

“wrap” these operations to intercept and replace error messages (this is described in detail in “Custom Error Reporting” on page 293). These operations are defined on a separate `ClientDomainConverter` interface. They are listed as follows. For more information about these methods, see the Cúram JavaDoc documentation for this interface.

- **preParse()**

This method prepares a string for parsing by applying the relevant domain options. For example, the string may have whitespace removed or compressed, or may be converted to upper-case. The locale is used for the conversion to upper-case, if that is required.

- **preValidate()**

This method performs the standard validation checks that are controlled by the domain options specified in the UML model. The checks include the maximum and minimum size, the maximum and minimum value, and the matching of a pattern. The specific data-type of the object will determine which of these checks are appropriate. The options and comparator are available from the domain.

Access to the `ClientDomainConverter` interface is only supported for the purposes of error message interception. However, as all converter plug-ins created for use by the client infrastructure must implement this interface, you must sub-class an existing converter plug-in class (or abstract class) when creating custom converter plug-ins to inherit an appropriate implementation.

## Comparator Plug-ins

The `DomainComparator` interface is used to control sort orders and it extends the `DomainPlugIn` interface and the standard `java.util.Comparator` interface. For more information about `DomainComparator`, see the Cúram JavaDoc documentation.

The `java.util.Comparator` interface defines a `compare` method that takes two `java.lang.Object` arguments and returns an integer that is positive if the first argument comes before the second argument in the sort order, negative if it comes after, and zero if the objects are equal. (See the JavaDoc documentation for the `java.util.Comparator` interface for more details.) An `equals` method is also defined by that interface, but it is of lesser importance; all Java classes inherit an implementation of the `equals` method from `java.lang.Object` or from another ancestor class and no further implementation is necessary.

## Default Value Plug-ins

The `DomainDefault` interface is used to define default values for domains where no default value is available. The main methods in this interface are listed as follows. For more information about these methods, see the Cúram JavaDoc documentation for this interface.

- **getAssumedDefault()**

This method is used to get the default value that will be assumed when a user clears a field on a form and submits no value.

- **getDisplayedDefault()**

This method is used to get the default value that should be displayed when an input field has no initial value to display.

From the methods listed above, we can see there are two types of default value: the value assumed when no value is available to send to the application server, and the value displayed when no initial value has been defined for a form field on an application page. The two default values are often the same, but there are some cases where they need to be different.

The assumed default value is needed when a form is submitted and the form data contains no value for a field that was not defined to be mandatory. The web client never submits null data values to the application server, so it must assume some value for the field and then submit that. The assumed value is nearly always intuitive: zero for any kind of number, an empty string for any string value, or a zero date or date-time for such values. The actual assumed default values used in the Cúram application are listed in “Default Value Plug-ins” on page 280.

The displayed default value is needed when a form field has not been initialized with any other value (as is usual on forms used to create new entities). The UIM FIELD element has a USE\_DEFAULT attribute that defaults to true, so, unless that attribute is set to false, the displayed default value may be used. The displayed default value for numbers and strings is usually the same as that used as the assumed default value, but for dates and times, the current date and time is used instead of the zero date and time. Like the assumed default values, the displayed default values are likely to be sufficient for most applications, so you are unlikely to need to customize them.

There is also a third source for default values: there is a domain definition option for a default value supported in the UML model. However, if no such option is set, it is the plug-in's displayed default value that is used as a fallback, so the two can be treated in the same way. If only the displayed default value needs to be customized, it is easier to do this using the UML domain definition option rather than writing and configuring a new plug-in class, but the assumed default value can only be modified via a plug-in.

The default code used for values in a code-table domain is controlled via the application's code-table administration interface. You should not attempt to control it programmatically.

## Domain Plug-in Configuration

Domain plug-ins are configured by means of an XML configuration file. The format is simple: the file contains a domains root element; for each domain to be configured, a domain element is inserted; within that element, plug-in elements are used to specify the name of the type of plug-in and the Java class that implements the operations of that type of plug-in. The domain elements are not nested within other domain elements to reflect the domain hierarchy. The configuration information is relatively “flat”; each entry configures a separate domain and the inheritance of plug-ins is determined automatically. Here is a sample of such a configuration file:

```
<dc:domains>
  <dc:domain name="SVR_INT64">
    <dc:plug-in name="Converter" class=
      "curam.util.client.domain.convert.SvrInt64Converter"/>
    <dc:plug-in name="comparator" class=
      "curam.util.client.domain.compare.SvrInt64Comparator"/>
    <dc:plug-in name="default" class=
      "curam.util.client.domain.defaults.SvrInt64Default"/>
  </dc:domain>
  <dc:domain name="INTERNAL_ID">
    <dc:plug-in name="converter" class=
      "curam.util.client.domain.convert.InternalIDConverter"/>
  </dc:domain>
</dc:domains>
```

*Figure 107. Sample Domain Configuration*

The configuration elements are defined in the XML namespace shown above. In the example, the namespace declaration assigns the prefix “dc” to this namespace, so that prefix is used before the element names. While you *must* declare this namespace in your configuration file, you can declare it to be a default namespace and omit the prefix, or even use a different prefix, but you must not omit the namespace declaration.

The example shows the configuration of two domains (these are the actual default configurations for these domains, as provided in the out-of-the-box Cúram application). Three plug-ins are configured for the Cúram root domain SVR\_INT64. This is a complete set of plug-ins, as the “options” plug-in is built-in and is never directly configured. All descendant domains of SVR\_INT64 will inherit these plug-ins unless further configured. Such a configuration is provided for the INTERNAL\_ID domain. This domain is a descendant of SVR\_INT64, but a different converter plug-in is configured; the comparator and default plug-ins will be inherited from SVR\_INT64. This particular configuration is used within the Cúram application to override the format operation for INTERNAL\_ID values so that grouping separators are not used in the string representations of the integers. An integer formatted by the SvrInt64Converter plug-in as “1,234,567” will be formatted by the InternalIDConverter class as “1234567”. This ensures that values such as case identifiers (the CASE\_ID domain is a descendant of the INTERNAL\_ID domain) are not represented as ordinary numerical values, but as more abstract unique key values. However, sorting and the calculation of default values remains unchanged, as these plug-ins are not overridden and the inherited plug-ins will be used.

There is a master configuration file called domains-config.xml located in your CDEJ installation's lib/curam/xml/config folder. This file contains the complete domain configuration information for all of the Cúram root domains and some descendant domains. You must not make any changes to this file; it is overwritten each time the development environment is upgraded. However, the information in this file is useful when you need to make customizations. You can override or extend any configuration setting in this file using the mechanism described here.

Domain plug-in configuration follows the typical pattern used for when configuring other aspects of application components. You create configuration files, place them in component folders, and the component order determines which parts of each file take precedence when the files are merged together. A single custom configuration results and this may override or extend the master configuration without limitation. The domain elements in the configuration are merged where they have the same domain name defined in the name attribute. The plug-in elements of the merged domains are then collected and those with the same name attribute value as an existing plug-in element take precedence over that setting. New domain configurations can also be introduced. If the newly configured domain has descendant domains, they will inherit the new configuration. When configuring plug-ins, the name returned by a plug-in's getName method must match the name attribute value defined on the plug-in element in the configuration file; this helps to avoid mistakes in the configuration file.

The configuration files that you place in your component folders must be named DomainsConfig.xml (a slightly different name to the master configuration file to prevent confusion of the two). You can create one or more of these files (one in each component), but a single file is probably sufficient for most purposes. The format is just that shown in the example above. Further configuration examples are included in “Customization Guidelines” on page 284.



## Out-of-the-Box Domain Plug-ins

### Extending Existing Plug-ins

Domain plug-ins for all of the root domain definitions (and a few others) are provided in the out-of-the-box Cúram application. Rather than write your own plug-in implementation from scratch, it is far easier to extend one of these existing plug-ins. The supplied plug-ins are suitable for the majority of uses, but all can be overridden in whole or in part as necessary, or used as the basis for new plug-ins that customize the processing of values in new domains. The details of these supplied plug-ins and the behavior of their operations are described in the sections below.

Abstract plug-in classes are also provided to be used as the basis of new plug-ins. These abstract classes are used by the Cúram plug-ins themselves and provide some useful functionality that is rarely necessary to override. The abstract classes you might use are:

- `curam.util.client.domain.convert.AbstractConverter`
- `curam.util.client.domain.compare.AbstractComparator`
- `curam.util.client.domain.defaults.AbstractDefault`

Their behavior is as follows:

*Table 128. Behavior of the Abstract Plug-in Classes*

Abstract Plug-in Class	Behavior
AbstractConverter	<p>Returns the correct name for this type of plug-in: "converter".</p> <p>Formats an object that is an instance of <code>java.lang.Number</code> using the standard Java locale-specific number format. Other object types are formatted by calling their <code>toString</code> method.</p> <p>Pre-parses an object by trimming leading and trailing whitespace, compressing sequences of spaces, and converting to upper-case if specified by the UML domain definition options for the domain.</p> <p>Does not implement any parse operation.</p> <p>Pre-validates an object by checking its maximum and minimum values if these are specified by the UML domain definition options for the domain.</p> <p>Validates an object by throwing a <code>java.lang.NullPointerException</code> if an object is null, but otherwise performs no validation.</p> <p>Performs generic parsing by invoking the ordinary parse operation that must be implemented in the sub-class. See "Generic Parse Operations" on page 297 for information on protecting the generic parse operation from side-effects.</p> <p>Performs generic formatting by invoking the object's <code>toString</code> method.</p> <p>Returns the correct value for the generic locale.</p>

Table 128. Behavior of the Abstract Plug-in Classes (continued)

Abstract Plug-in Class	Behavior
AbstractComparator	Returns the correct name for this type of plug-in: "comparator".
AbstractDefault	<p>Returns the correct name for this type of plug-in: "default".</p> <p>Defines constants with suitable assumed default values for each of the root domains.</p> <p>Returns the displayed default value by looking up the default value defined in the UML domain definition options, or, if not found there, returns the assumed default value.</p> <p>Does not implement getAssumedDefault.</p>

These abstract classes are used by the Cúram plug-in classes and all extend the `curam.util.common.domain.AbstractDomainPlugIn` class. This class implements the locale and domain properties of the `DomainPlugIn` interface and also provides the plug-in instance management implementation that should be used by all plug-ins (see "Plug-in Instance Management" on page 295 for details).

While it is possible to write plug-ins from scratch, you should follow the guidelines presented in this chapter and extend either the existing plug-in classes or their abstract base classes. Other approaches cannot be supported due to the complexity of some features, such as instance management and generic parsing, that are best avoided and the default implementations used. Reusing these classes will also ensure that your code will be protected from changes to the plug-in interfaces, as default implementations of new interface methods will be inherited during upgrades and no custom code changes should be necessary.

## Converter Plug-ins

Converter plug-ins implement the format, parse, validate, and related operations. The following converter plug-ins are provided out-of-the-box. While most are pre-configured against certain domains, others are left to be configured as described in "Domain Plug-in Configuration" on page 269 (all of the plug-ins are in the `curam.util.client.domain.convert` Java package):

Table 129. Out-of-the-Box Converter Plug-ins

Domain	Converter Plug-in Class
SVR_BLOB	SvrBlobConverter
SVR_BOOLEAN	SvrBooleanConverter
SVR_CHAR	SvrCharConverter
SVR_DATE	SvrDateConverter
SVR_DATETIME	DateTimeConverter
CURAM_TIME	CuramTimeConverter
SVR_DOUBLE	SvrDoubleConverter
SVR_FLOAT	SvrFloatConverter
SVR_INT8	SvrInt8Converter
SVR_INT16	SvrInt16Converter
SVR_INT32	SvrInt32Converter

Table 129. Out-of-the-Box Converter Plug-ins (continued)

Domain	Converter Plug-in Class
SVR_INT64	SvrInt64Converter
INTERNAL_ID	InternalIDConverter
SVR_MONEY	SvrMoneyConverter
SVR_STRING	SvrStringConverter
SVR_UNBOUNDED_STRING	SvrStringConverter
LOCALIZED_MESSAGE	LocalizedMessageConverter
CODETABLE_CODE	CodeTableCodeConverter
N/A	SvrInt8BareConverter
N/A	SvrInt16BareConverter
N/A	SvrInt32BareConverter
N/A	SvrInt64BareConverter

The format operations of these plug-ins determine the string representations of data values that appear on application pages. The format operations behave as follows:

Table 130. Behavior of the Format Operations

Plug-in Class	Formatting Behavior
SvrBlobConverter	Formatted as base-64 encoded strings. The base-64 encoding scheme is defined in RFC 2045.
SvrBooleanConverter	Formatted as the string values true or false. These values are not locale-aware. Cúram application pages rarely display formatted Boolean values directly, instead, check-boxes are used or values are translated to locale-specific strings.
SvrCharConverter	Formatted as Unicode characters, not as numbers.
SvrDateConverter	Formatted using the application date format. If the format includes month or day names, these are localized using the active user's locale. If the date is the system "zero" date, an empty string is returned.
DateTimeConverter	Formatted using the application date and time formats and the user's preferred time zone. If the format includes month or day names, these are localized using the active user's locale. If the date-time is the system "zero" date-time, an empty string is returned.
CuramTimeConverter	Formatted using the application time format. If the date-time is the system "zero" date-time, an empty string is returned.
SvrDoubleConverter	Formatted as numbers with grouping separator (e.g., thousands separator) and decimal point characters appropriate for the active user's locale.

Table 130. Behavior of the Format Operations (continued)

Plug-in Class	Formatting Behavior
SvrFloatConverter	Formatted in the same manner as the SvrDoubleConverter.
SvrInt8Converter	Formatted as numbers with grouping separator (e.g., thousands separator) characters appropriate for the active user's locale, but without any decimal point.
SvrInt16Converter	Formatted in the same manner as the SvrInt8Converter.
SvrInt32Converter	Formatted in the same manner as the SvrInt8Converter.
SvrInt64Converter	Formatted in the same manner as the SvrInt8Converter.
InternalIDConverter	Formatted as numbers in a non-locale-specific manner without grouping separator characters.
SvrInt8BareConverter	Formatted in the same manner as InternalIDConverter.
SvrInt16BareConverter	Formatted in the same manner as InternalIDConverter.
SvrInt32BareConverter	Formatted in the same manner as InternalIDConverter.
SvrInt64BareConverter	Formatted in the same manner as InternalIDConverter.
SvrMoneyConverter	Formatted in the same manner as the SvrDoubleConverter, but with exactly two significant digits after the decimal point.
SvrStringConverter	Formatted literally, i.e., strings are not changed by the format operation.
LocalizedMessageConverter	Formatted by decoding the message information, localizing the string indicated by the message catalog details, and replacing any encoded string arguments. The active user's locale is used throughout.
CodeTableCodeConverter	Formatted as the code description corresponding to the code value using the active user's locale and the domain's associated code-table.

Pre-parse operations are used to perform string-related operations, indicated by domain definition options set in the UML model, before the strings are parsed to their Java object representations. The operations performed are the same for all root domains and are as follows: trimming of leading whitespace, trimming of trailing whitespace, compression of sequences of whitespace characters to a single space character, and conversion to upper-case. The pre-parse operations should be customized via the domain definition options in the UML model. Customization of these options via domain plug-ins is not necessary and not supported.

Parse operations are used to interpret string values submitted from a form on an application page or via parameters to a URL and convert then to their Java object representations. The string values received from the web browser are interpreted as

being in the UTF-8 encoding. This encoding is used when creating the Unicode Java strings that are passed to the parse operations. The parse operations behave as follows:

*Table 131. Behavior of the Parse Operations*

Plug-in Class	Parsing Behavior
SvrBlobConverter	Parsed as a base-64 encoded string.
SvrBooleanConverter	Recognizes any of true, yes, or on as Boolean true values, and any of false, no, or off as Boolean false values. The parsing is not case-sensitive or locale-aware. Other values are reported as errors.
SvrCharConverter	Parsed as a single Unicode character. The presence of extra characters is reported as an error.
SvrDateConverter	Parsed using the application date format and the active user's locale.
DateTimeConverter	Parsed using the application date and time formats and the active user's locale. The user's preferred time zone is assumed.
CuramTimeConverter	Parsed using the application time format. The server's time zone is assumed.
SvrDoubleConverter	Parsed as a number with optional grouping separator characters and decimal point characters appropriate for the active user's locale.
SvrFloatConverter	Parsed in the same manner as SVR_DOUBLE values.
SvrInt8Converter	Parsed as a number with optional grouping separator characters appropriate for the active user's locale. The presence of a decimal point is treated as an error.
SvrInt16Converter	Parsed in the same manner as the SvrInt8Converter.
SvrInt32Converter	Parsed in the same manner as the SvrInt8Converter.
SvrInt64Converter	Parsed in the same manner as the SvrInt8Converter.
InternalIDConverter	Parsed in a non-locale-specific manner. Grouping separators are not permitted and for negative values the minus sign must be on the left.
SvrInt8BareConverter	Parsed in the same manner as the InternalIDConverter.
SvrInt16BareConverter	Parsed in the same manner as the InternalIDConverter.
SvrInt32BareConverter	Parsed in the same manner as the InternalIDConverter.
SvrInt64BareConverter	Parsed in the same manner as the InternalIDConverter.

Table 131. Behavior of the Parse Operations (continued)

Plug-in Class	Parsing Behavior
SvrMoneyConverter	Parsed in the same manner as SVR_DOUBLE values, but the magnitude of the values are limited to 1e13 to avoid the possibility of rounding errors.
SvrStringConverter	Parsed literally, i.e., strings are not changed by the parse operation.
LocalizedMessageConverter	Parsed literally in the same manner as the SvrStringConverter. Localized messages are not supported as input values, so this parser is never invoked.
CodeTableCodeConverter	Parsed literally as a code value in the domain's associated code-table. An error is reported if the code is not defined in that code-table.

Pre-validate operations are used to perform validation checks, indicated by domain definition options set in the UML model, after values have been parsed to their Java object representations. The checks performed are not the same for all domains. The possible validation checks are: maximum size (length), minimum size (length), maximum value, minimum value, and pattern match. The maximum and minimum values are checked using the compare operation. The pre-validate checks applied as follows:

Table 132. Behavior of the Pre-Validate Operations

Plug-in Class	Max./Min. Size	Max./Min Value	Pattern Match
SvrBlobConverter	Yes	No	No
SvrBooleanConverter	No	Yes	No
SvrCharConverter	No	Yes	No
SvrDateConverter	No	Yes	No
DateTimeConverter	No	Yes	No
CuramTimeConverter	No	Yes	No
SvrDoubleConverter	No	Yes	No
SvrFloatConverter	No	Yes	No
SvrInt8Converter	No	Yes	No
SvrInt16Converter	No	Yes	No
SvrInt32Converter	No	Yes	No
SvrInt64Converter	No	Yes	No
InternalIDConverter	No	Yes	No
SvrInt8BareConverter	No	Yes	No
SvrInt16BareConverter	No	Yes	No
SvrInt32BareConverter	No	Yes	No
SvrInt64BareConverter	No	Yes	No
SvrMoneyConverter	No	Yes	No
LocalizedMessageConverter	Yes	No	Yes

Table 132. Behavior of the Pre-Validate Operations (continued)

Plug-in Class	Max./Min. Size	Max./Min Value	Pattern Match
SvrStringConverter	Yes	No	Yes
CodeTableCodeConverter	Yes	No	No

The pre-validate operations should be customized via the domain definition options in the UML model. Customization of these options via domain plug-ins is not necessary and not supported.

The default implementations of the validate operations do not perform any extra validations.

## Comparator Plug-ins

Comparator plug-ins implement the compare operations that determine the sort order of lists of values. Comparator plug-ins are provided for the following domains (all of the plug-ins are in the `curam.util.client.domain.compare` package):

Table 133. Out-of-the-Box Comparator Plug-ins

Domain	Plug-in Class	Behavior
SVR_BLOB	SvrBlobComparator	Not sorted, as there is no useful sort order for these non-human-readable values.
SVR_BOOLEAN	SvrBooleanComparator	Sorted with Boolean true values before false values.
SVR_CHAR	SvrCharComparator	Sorted strictly numerically with no locale-aware processing.
SVR_DATE	SvrDateComparator	Sorted chronologically with the earliest date first.
SVR_DATETIME	SvrDateTimeComparator	Sorted chronologically with the earliest date-time first.
CURAM_TIME	CuramTimeComparator	Sorted chronologically with the earliest time first. CURAM_TIME is based on the SVR_DATETIME domain, so values may included date information, but for comparisons, the date part is ignored and only the time part is used to determine the sort order.
SVR_DOUBLE	SvrDoubleComparator	Sorted numerically; smallest value first.
SVR_FLOAT	SvrFloatComparator	Sorted in the same manner as SVR_DOUBLE values.
SVR_INT8	SvrInt8Comparator	Sorted in the same manner as SVR_DOUBLE values.
SVR_INT16	SvrInt16Comparator	Sorted in the same manner as SVR_DOUBLE values.

Table 133. Out-of-the-Box Comparator Plug-ins (continued)

Domain	Plug-in Class	Behavior
SVR_INT32	SvrInt32Comparator	Sorted in the same manner as SVR_DOUBLE values.
SVR_INT64	SvrInt64Comparator	Sorted in the same manner as SVR_DOUBLE values.
SVR_MONEY	SvrMoneyComparator	Sorted in the same manner as SVR_DOUBLE values.
SVR_STRING	SvrStringComparator	Sorted lexicographically based on the numeric Unicode value of each character in the string. The comparison is not locale-aware.
SVR_STRING	SvrStringCaseInsensitiveComparator	Sorted identically to SvrStringComparator except the case is ignored.
SVR_STRING	SvrStringLocaleAwareComparator	Sorted according to the sorting rules defined by Unicode Collation Algorithm for the locale. See “Localized (Cultural-aware) string sorting” on page 279 for details.
SVR_UNBOUNDED_STRING	SvrStringComparator	Sorted in the same manner as SVR_STRING values.
CODETABLE_CODE	CodeTableCodeComparator	Sorted according to the defined code-table sort order for the code values. If the defined sort orders are equal, the code descriptions are sorted lexicographically based on the numeric Unicode value of each character in the string. The comparison is not locale-aware.
CODETABLE_CODE	CodeTableCodeCaseInsensitiveComparator	Sorted identically to CodeTableCodeComparator except case is ignored.
CODETABLE_CODE	CodeTableCodeLocaleAwareComparator	Similar to the above, but the comparison of code descriptions uses the sorting rules defined by Unicode Collation Algorithm for the locale. See “Localized (Cultural-aware) string sorting” on page 279 for details.

The SvrStringComparator and CodeTableCodeComparator classes are configured by default to sort values in the SVR\_STRING and CODETABLE\_CODE domains respectively. If locale-aware sorting is required, the default plug-in configuration can be overridden to use the SvrStringLocaleAwareComparator and



CodeTableCodeLocaleAwareComparator classes instead. If case-insensitive sorting is required, override using SvrStringCaseInsensitiveComparator and CodeTableCodeCaseInsensitiveComparator. See “Domain Plug-in Configuration” on page 269 above for details on overriding the default plug-in configuration. Using these locale-aware comparators, lists will be sorted according to the expected sorting rules of the active locale. However, applying these sorting rules takes more time, so there will be some performance degradation. The implementation of locale-aware sorting uses Java's built-in sorting rules, so the availability of correct sorting rules for each locale depends on the Java JRE being used.

#### **Localized (Cultural-aware) string sorting:**

When sorting the textual strings, Unicode Collation Algorithm implementation is used to ensure the sort order expected by the users in different cultural environments.

The sorting order depends on both the current user locale and the so called collation strength. This strength is configurable to ensure the exact requirements for different languages and applications.

In order to change the default strength the application property 'curam.collator.strength' should be set to one of the valid values summarized in the table Table 134 below.

'curam.collator.strength' is a static property and requires a server restart upon changing.

*Table 134. Collation strength summary*

'curam.collator.strength'	Strength Name	Description
1	PRIMARY	Alphabetical sorting which accounts for the base letter differences.
2	SECONDARY	Diacritic sort order which takes into account character accents.
3	TERTIARY	Character case based refinement of the sort order.  This is the default value of the 'curam.collator.strength' and also the fall-back value where the set value cannot be interpreted.
4	QUATERNARY	Used to ignore punctuation when setting the sort order, and to account for minor differences. This level should also be used when sorting Japanese text according to JIS X 4061 standard.
5	IDENTICAL	The tie-breaking level, the character code point values are compared at this stage.

**Note:** If any value beyond the acceptable range is entered for the 'curam.collator.strength', a runtime fall-back to the default strength will occur. The notification of this will be recorded in the application server logs.

**Note:** As the collation strength is increased this can have an impact on performance.

## Default Value Plug-ins

Default value plug-ins supply the default values used when no values are available. Default value plug-ins are provided for the following domains (all of the plug-ins are in the `curam.util.client.domain.defaults` package):

*Table 135. Out-of-the-Box Default Value Plug-ins*

Domain	Plug-in Class	Assumed Value	Displayed Value
SVR_BLOB	SvrBlobDefault	Empty BLOB	Empty BLOB
SVR_BOOLEAN	SvrBooleanDefault	False	False
SVR_CHAR	SvrCharDefault	Character zero	Character zero
SVR_DATE	SvrDateDefault	Zero date	Current date
SVR_DATETIME	SvrDateTimeDefault	Zero date-time	Current date-midnight
SVR_DATETIME	SvrDateTimeDefaultCurrTime	Zero date-time	Current date - Current time
SVR_DOUBLE	SvrDoubleDefault	Zero	Zero
SVR_FLOAT	SvrFloatDefault	Zero	Zero
SVR_INT8	SvrInt8Default	Zero	Zero
SVR_INT16	SvrInt16Default	Zero	Zero
SVR_INT32	SvrInt32Default	Zero	Zero
SVR_INT64	SvrInt64Default	Zero	Zero
SVR_MONEY	SvrMoneyDefault	Zero	Zero
SVR_STRING	SvrStringDefault	Empty string	Empty string
SVR_UNBOUNDED_STRING	SvrStringDefault	Empty string	Empty string
CODETABLE_CODE	CodeTableCodeDefault	Empty code string	Empty code string

Within the Cúram application, the zero date and time is represented as midnight on January 1,0001; this is interpreted as if no date and time has been set at all.

Also, the default value for a code-table code is an empty code string; a different mechanism is used to define default code-table codes during code-table administration.

SvrDateTimeDefault plug-in is time zone aware and the displayed value it returns is offset by the difference between the user and server time zones. The configured converter plug-in is expected to also consider time zone settings and offset the value accordingly. The end result is that the time part of date-time value is set to midnight regardless the time zone settings.

## Error Reporting

### Infrastructure Errors

There are many built-in, infrastructure errors, for which the developer can perhaps do no more than retry the page or restart the web application. If these problems persist, technical support should be notified.

These errors should be reported by keeping a copy of the error page source. Since we are in a browser environment, this is achieved by simply selecting File-->Save As... from the menu, or selecting View-->Source to bring up a text editor and then saving the document. The information in the source of the page may be useful in identifying and resolving the error.

## Exception Classes

Many customizations require the addition of exception handling and error reporting code. All the necessary infrastructure is provided to make this as simple as possible. A simple formulaic approach can be followed that will provide all of the necessary functionality. Before looking at how you can write customizations, you must first learn the necessary error reporting techniques.

All of the plug-in methods that throw exceptions, throw one of two exception types:

- `curam.util.common.domain.DomainException`
- `curam.util.client.domain.convert.ConversionException`

`ConversionException` is derived from `DomainException`, so instances of these exceptions can both be treated as `DomainException` objects when convenient. The `ConversionException` class is used for exceptions that are thrown by the methods of converter plug-ins. Unlike a `DomainException`, a `ConversionException` can be associated with a particular property of a server interface so that error messages reported to a user can indicate the label of the field in error and an error icon can be placed beside that field. The only exceptions that custom code normally needs to throw are instances of `ConversionException`, so this is the only exception class than needs to be understood to implement your own exception handling and reporting.

Conversion exceptions (and most other exceptions in the client infrastructure) carry information about the error message that needs to be reported, but not the error message itself. When an exception is thrown, the identifier of the localized error message string, the values that will be substituted for the placeholders in that string, and any causal exception object are included in the exception details. Each exception class can be associated with an error message catalog (a set of localized Java properties files) that is used when the localized message string is resolved from the message identifier. The localization and substitution steps are not performed until the message is reported to the user, so the exception can be propagated and augmented with more information for some time before the message string becomes fixed. This allows, in the case of conversion exceptions, the field label to be added automatically by the infrastructure after your custom code has thrown the exception and makes it very easy to integrate your error reporting requirements into the system.

## Custom Exception Classes

The purpose of a custom exception class is to integrate the look-up of localized message strings in a custom message catalog into the mechanism used for error reporting in the client infrastructure. If you only need one error message catalog, you will only need one custom exception class, but there is no restriction on the number of exception classes or message catalogs you can create.

Implementing custom exception handling using a custom exception class is formulaic. As the custom exception class must integrate into the existing message reporting system, only numeric message identifiers are supported for custom

exceptions and there is very little room for deviation from the prescribed approach. You cannot, for example, use literal message strings in your code, you must use references to externalized strings.

Here is an example of a custom exception class:

```
public class CustomConversionException
    extends ConversionException {

    private static final MessageLocalizer MESSAGE_LOCALIZER
        = new CatalogMessageLocalizer("custom.ErrorMessage");

    public CustomConversionException(int messageID) {
        super(messageID);
    }

    public CustomConversionException(int messageID,
                                     String[] messageArgs) {
        super(messageID, messageArgs);
    }

    public CustomConversionException(int messageID,
                                     String messageArg) {
        super(messageID, messageArg);
    }

    public MessageLocalizer getMessageLocalizer() {
        return MESSAGE_LOCALIZER;
    }
}
```

*Figure 108. Custom Exception Class*

This class extends `ConversionException` and implements a number of constructors simply by invoking the equivalent constructors in the super-class. You only need to implement the constructors that you intend to use, the rest of the constructors in the super-class can be ignored (Java classes do not inherit constructors, hence the need to re-implement them). The available constructors are described in the JavaDoc. Next, it defines a static `MessageLocalizer` field and instantiates it with a `CatalogMessageLocalizer` object that takes your custom catalog name as its argument. The `getMessageLocalizer` method then returns this static object. That is all there is to it.

When you throw exceptions of this type, you need to pass your message identifier and optional arguments to the relevant constructor. You can define constants for your numeric message identifiers in this class if you wish. Your message strings can contain placeholders such as `"%1s"`, `"%2s"`, etc., to be replaced by the argument strings (only string types are supported). For an array of arguments, `"%1s"` will be replaced by the first argument in the array (index zero), and so on. The special argument `"%0s"` can be used to represent the name of the field in error, but you will not need to provide any matching argument string for that value; it will be substituted automatically. You can also use the same placeholder several times in a single message if you want the same value to be inserted in more than one place. Here is a sample message catalog file containing a single message:

```
-200000=ERROR: The field '%0s' contains an invalid value '%1s'.
```

*Figure 109. Custom Message Catalog*

The file is a standard Java properties file where each line contains a numeric identifier and a message string separated by an equals character. A collection of

properties files with the same base name but with locale codes appended is treated as a single message catalog. The custom exception class in the example above refers to the message catalog as “custom.ErrorMessage”, so the properties files should be located on the Java classpath in the custom package folder and in files named ErrorMessage.properties, ErrorMessage\_en\_US.properties, ErrorMessage\_fr\_CA.properties, etc., as you would do for any other custom properties files. There should be one properties file for each locale that your application supports. The selection of the correct locale-specific properties file at run-time is completely automatic once you have written your custom exception class as shown above.

Ensuring that these files end up on the classpath is simply a matter of placing them in their appropriate package folders below your web application's <client-dir>/<custom>/javasource folder, where custom is the name of a custom component. (see “CDEJ Project Folder Structure” on page 11 for details). The Java source files for your custom exceptions should also be placed below the <client-dir>/<custom>/javasource folder in the appropriate folders for the package names you have used.

When throwing a custom exception, the code will look like this (assuming you have decided not to use constants for your error message identifiers):

```
throw new CustomConversionException(-200000, myInvalidValue);
```

*Figure 110. Throwing a Custom Exception*

Remember, it is not necessary to pass any argument corresponding to the “%0s” placeholder; it will be calculated and substituted automatically.

**Numeric Message Identifiers:** When creating message catalog files, try to ensure that the error numbers do not conflict with the numbers of existing Cúram error messages, as this may cause confusion when errors are being investigated. Values below -200000 should be safe to use, though conflicting numbers will not actually cause any application problems, as the message catalogs are separate from those used by the infrastructure.

If you examine the constructors of the ConversionException class, you will note that many accept a java.lang.Throwable object as the last argument. You can implement similar constructors and pass Throwable objects (usually other exception objects) to your custom exceptions when you want your custom exception to include the exception that caused it. This is often very useful as error messages for both exceptions will be reported automatically and both stack traces will be included on an application error page if the error page is required. In fact, there is no imposed limit to the length of the chain of exceptions that can be built this way; the exception that you add to your own may already contain a reference to another exception, and so on.

This example show how you can even report two separate error messages at once. Perhaps one is a generic message that states that a field does not contain a valid value and another suggests the expected format for that value. You will have to implement the appropriate constructor to support this, but the reporting mechanism is automatic.

```
throw new CustomConversionException(
    -2000000, myInvalidValue,
    new CustomConversionException(-2000003));
```

Figure 111. Throwing Multiple Exceptions

## Java Object Representations

The data conversion and comparison operations manipulate strings and other Java objects. Each value in a root domain is represented by an object of a corresponding Java class. The Java class used by a root domain is the same for all descendant domains of that root domain and cannot be changed. When customizing the operations, knowledge of the type of data being processed is important. The table below shows the Java class used for data objects for each of the root domains.

Table 136. Classes Used for Java Object Representations

Domain	Java Class
SVR_BLOB	curam.util.type.Blob
SVR_BOOLEAN	java.lang.Boolean
SVR_CHAR	java.lang.Character
SVR_DATE	curam.util.type.Date
SVR_DATETIME	curam.util.type.DateTime
SVR_DOUBLE	java.lang.Double
SVR_FLOAT	java.lang.Float
SVR_INT8	java.lang.Byte
SVR_INT16	java.lang.Short
SVR_INT32	java.lang.Integer
SVR_INT64	java.lang.Long
SVR_MONEY	curam.util.type.Money
SVR_STRING	java.lang.String
SVR_UNBOUNDED_STRING	java.lang.String
CODETABLE_CODE	curam.util.common.util.CodeItem

Though derived from SVR\_STRING, the Java class used for CODETABLE\_CODE is different to that of its parent. This is the only exception to the rule that the Java class used is the same for all descendant domains of a root domain.

## Customization Guidelines

### Where to Start

Most customizations aim to control one or more of the data conversion or sorting operations. Guidelines are provided in the following sections to show you how each of these operations can be customized. Following these guidelines will ensure that your customizations are as simple and effective as possible.

When you have written your custom plug-ins, you need to configure them and ensure that the Java classes are available at run-time. Configuration was described in “Domain Plug-in Configuration” on page 269. The Java source files for your custom plug-in classes are added to the web application in exactly the same way

as the Java source code files for your custom exception classes (see “Custom Exception Classes” on page 281): they are placed in their appropriate package folders in your <client-dir>/<custom>/javasource folder, (where <custom> is the name of a custom component).

## Custom Formatting

Custom formatting may be required when a value displayed on an application page is not in the required format. A custom formatter might be used to pad values with extra characters, so that they appear to be the same length; insert a currency symbol into money values; format numeric values without grouping separator characters; or even take a date value based on the Gregorian calendar and format it after converting it to another calendar system.

1. Identify an existing converter plug-in class that you want to customize. It will most likely be the converter that is already configured for the domain in question or inherited by it from an ancestor domain.
2. Create a new sub-class of the relevant converter plug-in and override the format method.
3. In the implementation of the method, you can perform some processing before or after invoking the super-class's method of the same name, or implement the formatting code from scratch.
4. Configure your new plug-in for the relevant domains.

The calendar scenario is somewhat unrealistic because the date selector widget would not be compatible, but inserting a currency symbol, or an analogous operation, is something that you may want to do. If multiple currencies are supported, then domains such as US\_DOLLAR\_AMOUNT or EURO\_AMOUNT might be used to represent values in each currency (though the out-of-the-box Cúram application uses a different scheme for representing money values in different currencies). Custom converter plug-ins may then be written to format money values for each of these domains by adding the appropriate currency symbol.

This example shows how a converter plug-in can be written that takes a money value and prefixes the formatted numeric value with a dollar symbol. The out-of-the-box Cúram application comes with a converter plug-in that formats money values, but without any currency symbol, so you can reuse its format operation to simplify the implementation.

```
/**
 * Converter that supports the use of a dollar symbol for
 * money values.
 */
public class USDollarConverter
    extends SvrMoneyConverter {
    public String format(Object data)
        throws ConversionException {
        return "$" + super.format(data);
    }
}
```

*Figure 112. Custom Formatting for Currency Values*

The implementation is very trivial: the super-class does all the work and returns a nicely formatted money value; the customization just adds the dollar symbol.

The configuration file for this customization is shown below. The file might also include entries for other customizations that have been made. As the comparator

and default value plug-ins have not been customized, they do not appear in the configuration. These plug-ins will be inherited from the ancestors of the US\_DOLLAR\_AMOUNT domain (probably the SVR\_MONEY domain).

```
<dc:domains xmlns:dc="http://www.curamsoftware.com/curam/util/common/domain-config">
  <dc:plug-in name="converter"
    class="custom.USDollarConverter"/>
</dc:domain>
</dc:domains>
```

Figure 113. Configuration for Custom Formatting

Values displayed on an application page (or even those passed behind the scenes in hidden page connections) may be submitted back to the web application. If you write a formatter that inserts a currency symbol, or you allow users to insert currency symbols in values that they type in, then you will need to accommodate such values in the parse operation. The next section will demonstrate the custom parse operation required to match this custom format operation.

Another common need for custom formatting is to format integer values without grouping separator characters. For example, an integer value that represents the year “2005” should probably be formatted as “2005” and not “2,005”. If the year value is represented by the YEAR\_VALUE domain and that domain is derived from the SVR\_INT16 domain, the custom format operation would look like this:

```
/**
 * Converter that formats year values without adding grouping
 * separator characters.
 */
public class YearValueConverter
    extends SvrInt16Converter {
    public String format(Object data)
        throws ConversionException {
        return data.toString();
    }
}
```

Figure 114. Custom Formatting without Grouping

This converter overrides the format method of the SvrInt16Converter class and simply converts the *data* object (a java.lang.Short) to a string. Unlike the routines used by the super-class, the toString method will not do any locale-aware formatting or add any grouping separator characters. The parse method is not overridden, so values that are entered with or without grouping separator characters will be accepted. This converter is configured in the same way that the currency symbol converter was configured.

## Custom Parsing

Custom parsing is implemented when users must enter values in a form that existing parse operations do not recognize or when some other processing must be performed on values before they are submitted to the application server. Custom parsing may be as simple as a routine that first removes a currency symbol from a numeric value before parsing it, where the currency symbol may have been entered by a user or added by a custom format operation. It could also be something more unusual: a translation of a date to another calendar system, a routine that pads string values, or an arbitrary calculation on numeric values.

1. Identify an existing converter plug-in class that you want to customize. It will most likely be the converter that is already configured for the domain in question or inherited by it from an ancestor domain.



2. Create a new sub-class of the relevant converter plug-in and override the parse method.
3. In the implementation of the method, you can perform some processing before or after invoking the super-class's method of the same name, or implement the parsing code from scratch.
4. Configure your new plug-in for the relevant domains.

The currency symbol scenario is continued in this example to complement the example shown for a custom format operation above. The example below shows the same class developed to format money values with a currency symbol; the class is now extended with a corresponding parse operation. In a case like this, you do not write separate converter plug-ins for formatting and parsing; you must implement both operations in the same converter plug-in and then associate the plug-in with the appropriate domain.

```
/**
 * Converter that supports the use of a dollar symbol for
 * money values.
 */
public class USDollarConverter
    extends SvrMoneyConverter {
    public String format(Object data)
        throws ConversionException {
        return "$" + super.format(data);
    }

    public Object parse(String data)
        throws ConversionException {
        if (data.startsWith("$")) {
            return super.parse(data.substring(1));
        }
        return super.parse(data);
    }
}
```

Figure 115. Custom Parsing for Currency Values

The value passed to the parse method is the same value that was entered by the user; it is possible that it contains no currency symbol or it might contain space characters between the currency symbol and the value. You can use the UML domain definition options to ensure that the pre-parse operation will have removed any whitespace before the currency symbol, or simply report an error if the currency symbol or a digit is not the first character. The parse method above assumes that the currency symbol is the optional first character and then leaves all other decisions up to the parse method of the super-class. This is probably the best approach, as it limits the number of formatting rules that a user needs to be aware of and keeps the code as simple as possible.

The configuration for this plug-in is unchanged from that shown for the custom format operation.

## Custom Validation

Custom validation can be performed in two ways: by setting the domain definition options in the UML model, or by implementing a validate operation in a custom converter plug-in. It is also possible to combine both ways to meet your validation requirements.

The domain definition options in the UML model are limited to a small number of validations that are described in the *Cúram Modeling Reference Guide* and

summarized in “Converter Plug-ins” on page 272 above. If the domain definition options meet your needs, you should use them in preference to any programmatic alternative. If the options meet only some of your needs, you should use them and also create a custom converter plug-in to complete the validations. If the options are not useful, you should create a custom converter plug-in and implement all the validations there. Some uses for custom validation routines might include the validation of check digits or the imposition of any other arbitrary restrictions on the permitted values.

1. Identify an existing converter plug-in class that you want to customize. It will most likely be the converter that is already configured for the domain in question or inherited by it from an ancestor domain.
2. Create a new sub-class of the relevant converter plug-in and override the `validate` method.
3. In the implementation of the method, invoke the super-class's method of the same name to perform any existing validations (if that is appropriate).
4. Complete the implementation by performing your validations and throwing an exception if any validation fails.
5. Configure your new plug-in for the relevant domains.

In this example, a new converter plug-in is created that extends the `InternalIDConverter` plug-in with a validation that only permits even numbers. The `InternalIDConverter` is derived from the `SvrInt64Converter` class that is configured for use by the `SVR_INT64` domain. Values in this domain are represented by `java.lang.Long` objects.

```
/**
 * Reports ID numbers as invalid if they are odd.
 */
public class EvenIDConverter
    extends InternalIDConverter {
    public void validate(Object data)
        throws ConversionException {
        // Perform any existing validations first.
        super.validate(data);

        if (((Long) data).longValue() % 2 != 0) {
            throw new CustomConversionException(-200010);
        }
    }
}
```

*Figure 116. Custom Validation for Odd Numbers*

The error message entry in the custom message catalog may look like this:

```
-200010=ERROR: The field '%0s' must be an even number.
```

*Figure 117. Custom Validation Failure Message*

If this validation is to be applied to the `EVEN_ID` and the `NOT_ODD_ID` domains, then the configuration will look like this:

```

<dc:domains xmlns:dc="http://www.curamsoftware.com/curam/util/common/domain-config">
  <dc:domain name="EVEN_ID">
    <dc:plug-in name="converter"
      class="custom.EvenIDConverter"/>
  </dc:domain>
  <dc:domain name="NOT_ODD_ID">
    <dc:plug-in name="converter"
      class="custom.EvenIDConverter"/>
  </dc:domain>
</dc:domains>

```

Figure 118. Configuration for Custom Validation

## Custom Sorting

When lists of values are displayed in an application page, a user can sort the list by clicking on the column headers. The sort order of the rows will be determined by the sort order of the values in the selected column. Successive clicks on a column header alternate between the forward and reverse sort order for that column. The sort order for any type of data can be customized easily, though the sort-order for code-table codes must be controlled using the code-table administration interface. The sort order is calculated when responding to a user's request, so the user's active locale is available by calling the inherited `getLocale` method and can be used to influence the sort order in a locale-specific manner.

The domain comparator plug-ins are responsible for making the comparisons that control the sort order. The sorting algorithms swap the position of values in their value lists depending on the value returned by the `compare` method of the plug-in. The comparator plug-ins used in the Cúram application behave as described in “Comparator Plug-ins” on page 277. These sort orders are simple and intuitive, but may not meet the needs of some specialized domains. In these cases, custom sort orders may be required and there is no limitation on what order can be used.

**What Values are Compared?:** All compare operations are performed by invoking the comparator plug-ins `compare` method. This takes two `java.lang.Object` arguments. The method is invoked automatically by the client infrastructure *before the values are formatted*. This means that the objects passed are of the types shown in “Java Object Representations” on page 284, not formatted string representations of the values.

In most cases, having access to Java object representations makes the comparisons much easier to perform: comparing dates and numbers is much easier when they are represented by objects that conveniently provide a `compareTo` method that returns the same values that the `compare` method must return. However, there are some situations where, for example, encoded strings are decoded by the format operation and comparing them before they are formatted is not simple or would involve the duplication of the formatting code. In these cases, it is possible to invoke the appropriate formatter and compare the results. This will be described later.

The general guidelines for implementing a custom comparator plug-in to control the sort order for a domain are as follows:

1. Create a new sub-class of the `AbstractComparator` class described in “Extending Existing Plug-ins” on page 271.
2. Implement the `compare` method to perform your custom comparison.
3. Configure your new plug-in for the relevant domains.

To illustrate this, you will see how to write a comparator that compares string values as if they were numbers. Some of the entities in the Cúram application use a string-based domain for their key values to support the use of identifiers that may not just contain digits. Sorting of these types works well in most cases, but there can be problems. Because the base domain is a string, the values are sorted lexicographically, not numerically. If the values are all of the same length, this is not a problem, but if the lengths differ, the sorting becomes confusing. For example, the string values "22" and "33" will be sorted into the order "22", "33", but if the values are "22" and "3", the sort order will be "22", "3", because the character "2" comes before the character "3" in a lexicographical sort and representations of numbers with positional digits are not recognized.

There are a number of ways to solve this problem:

- The string values could be stored in the database with leading zeros used to pad all values to the same length, this would trick the lexicographical sorting into working correctly (the lexicographical sort order for "22" and "03" is "03", "22"). If the leading zeros were not desired for display purposes, they could be stripped by the format operation and replaced by the parse operation. Legacy data, however, would need to be updated to conform to the new format.
- Write a custom comparison routine that parses the numeric values from the strings and then performs the comparison. This would work fine, but the parsing is a little complicated and it may be complicated further if the values have trailing check letters or other non-digit characters.
- Pad the value with zeros for the purposes of making the comparison, but do this inside the compare operation, so that no other application changes are necessary.

The latter solution is, perhaps, the easiest to achieve. Here is an example of a custom comparator plug-in that does this for values that are limited to no more than ten characters:

```
/**
 * Compares string values after padding them with leading
 * zeros to make the sorting work correctly for numeric
 * values. Values must not be longer than ten characters.
 */
public class IDComparator
    extends AbstractComparator {
    public int compare(Object s1, Object s2) {
        return _pad((String) s1).compareTo(_pad((String) s2));
    }

    private String _pad(String s) {
        return "0000000000".substring(0, 10 - s.length()) + s;
    }
}
```

*Figure 119. Sorting Strings Numerically*

The `_pad` method pads a value with leading zeros, so that all returned strings will be ten characters long and numeric values will be compared correctly as the positional digits will all be aligned correctly. No change needs to be made to the format or parse operations or to any existing values in the database; the sort order is entirely controlled by this simple comparator code. While the numeric values could have been parsed from the strings and a numeric comparison made, this sample code is much simpler and more efficient.

Another need for custom sorting arises when values are in an encoded form that is decoded by the format operation. In this case, sorting of the encoded form may not

be meaningful. For example, if a domain exists that uses an encoded string containing several localized messages and their locale codes like this “en|Hello|es|Hola”, calculating the sort orders for such strings is meaningless. The string could be decoded, but, as decoding must be done by the format operation, it is simpler to invoke the format operation instead and compare the values that it returns.

```
/**
 * Compares two encoded message strings using their
 * formatted values.
 */
public class MessageComparator
    extends AbstractComparator {
    public int compare(Object value1, Object value2) {
        final DomainConverter converter;

        try {
            converter = ((ClientDomain) getDomain())
                .getConverter(getLocale());
            return converter.format(value1)
                .compareTo(converter.format(value2));
        } catch (Exception e) {
            // Do nothing except report the values to be equal.
            return 0;
        }
    }
}
```

*Figure 120. Sorting Formatted Values*

This code retrieves the converter plug-in that implements the format operation for the same domain as that of the values being compared. The returned converter will also be aware of the active user's locale. The exact mechanism behind this is unimportant, simply copying the code above is all that is needed. Other uses of the `ClientDomain` class are not supported. The exception handling is simple: it does nothing. The `compare` method is not declared to throw exceptions, and thrown run-time exceptions trigger an application error page, so there is not much useful error handling that can be performed. The reason that none is attempted at all is that if the converter cannot be retrieved or the format operation fails, it will be for reasons beyond the control of the comparator plug-in and these reasons will cause failures in other places that will be reported in time. In fact, the sorting operation is carried out just before the infrastructure formats all of the values ready for display, so the very next operation will detect and report the errors that may have been ignored by the comparator.

A final example shows how to make the Cúram application zero date (January 1,0001), appear after all other dates instead of before them:

```

/**
 * Compares dates, but places the zero date at the end,
 * rather than the start, or the sort order.
 */
public class ZeroDateComparator
    extends AbstractComparator {
    public int compare(Object value1, Object value2) {
        final Date date1 = (Date) value1;
        final Date date2 = (Date) value2;

        if (Date.kZeroDate.equals(date1)
            && !Date.kZeroDate.equals(date2)) {
            return -1;
        } else if (!Date.kZeroDate.equals(date1)
            && Date.kZeroDate.equals(date2)) {
            return 1;
        }
        return date1.compareTo(date2);
    }
}

```

*Figure 121. Sorting Zero Dates*

The comparator returns a negative number (the magnitude is not important) if the first date is the zero date and the second date is not the zero date to indicate that the first date comes after the second in the sort order. Likewise, a positive number is returned if the first date is not the zero date and the second date is the zero date to indicate that the order is correct. Otherwise, the dates are compared as normal. This causes the zero date to be positioned after all other dates instead of before them in the sort order.

This type of manipulation should be used with caution: the comparator plug-ins are also used during pre-validation to check a value against the maximum and minimum values defined for its domain in the UML model's domain definition options. In this case, if the UML domain definition options define a maximum date and no date is set, then the zero date will be assumed and this will appear to be later than all other dates, including the maximum date, and the pre-validation check will always fail with an error. If no maximum value is specified in the model, then this comparator will work without problems.

To override the default comparator for all dates with this new comparator, the configuration will look like this:

```

<dc:domains xmlns:dc="http://www.curamsoftware.com/curam/util/common/domain-config">
  <dc:domain name="SVR_DATE">
    <dc:plug-in name="comparator"
      class="custom.ZeroDateComparator"/>
  </dc:domain>
</dc:domains>

```

*Figure 122. Configuration for Custom Sorting*

Now, all date values for all domains that are descendants of the root SVR\_DATE domain, and values in the root domain itself, will be sorted according to the new rules. There is no need to configure any other domains, as they will all inherit this new comparator (unless, of course, a descendant domain has been configured with another comparator that will override any inherited comparator). This comparator could also be applied more selectively to descendant domains of SVR\_DATE.

## Custom Error Reporting

It is possible that a plug-in performs the operations exactly as you require, but you need to customize the error reporting. One area of the Cúram application where this may happen is in the pre-validation operation when the pattern matching option is applied. A pattern is a regular expression defined in the UML model. When this validation fails, the error reports that the data was “not in a recognized format”, as few users would be able to interpret the meaning of a regular expression if presented to them. If the format is a common and intuitive one (a phone number, say), then this message will probably suffice. However, if the format is more obscure, the error message may need to be changed to present a human-readable description of the format (correctly localized). There are two ways to achieve this:

- Remove the pattern option from the UML model and implement your own pattern match validation as you would for any type of custom validation.
- Intercept the exception from the pre-validation operation and replace it with a different exception carrying your alternative error message.

A custom validation is possible and you will just need to follow the usual guidelines for such a customization, but it is complicated by the need to access the pattern information and perform the pattern matching operation. As you would then need to report your custom error message, it is much simpler to let the existing infrastructure do all the pattern matching and just focus on the error message.

Custom error reporting is really only applicable to the `parse` and `preValidate` methods of a converter plug-in. These are the only methods that may be invoked and passed values that a user has entered and that a user may be able to correct in response to an error message. The converter plug-ins supplied with the out-of-the-box Cúram application do not report any errors from their `validate` methods, so, unless you want to customize another custom converter plug-in, the `validate` method can be ignored.

1. Identify the method that is generating the exception that carries the error message that you want to customize. The likely candidates are the converter plug-in's `parse` and `preValidate` methods.
2. Create a new sub-class of the relevant converter plug-in and override the appropriate method.
3. In the implementation of the method, invoke the super-class's method of the same name and catch any exception thrown.
4. Test the error number on the caught exception to ensure it is the one you want to override.
5. If the error number is correct, throw a new exception carrying your error message, otherwise, re-throw the caught exception, as it is not the one you wish to override.
6. Configure your new plug-in for the relevant domains.

This example shows how this might be done to override the pattern match failure message. The custom exception class described in “Custom Exception Classes” on page 281 is used.

```

/**
 * Reports that social security numbers must match the format
 * "xxx-xx-xxxx" when the regular expression defined in the
 * UML model "\d{3}\-\d{2}\-\d{4}" does not match a social
 * security number entered by a user.
 */
public class SSNConverter
    extends SvrStringConverter {
    public void preValidate(Object data)
        throws ConversionException {
        try {
            super.preValidate(data);
        } catch (ConversionException e) {
            if (e.getMessageObject().getMessageID()
                == e.ERR_CONV_NO_MATCH) {
                throw new CustomConversionException(-200001);
            }
            throw e;
        }
    }
}

```

*Figure 123. Custom Error Reporting*

The error message entry in the custom message catalog will look like this:

-200001=ERROR: The field '%0s' must use the format 'xxx-xx-xxxx'.

*Figure 124. Custom Pattern Match Failure Message*

Domains that require this converter can be configured in the same manner as shown for the other converters above.

When using the error messages interception, please keep in mind, that Cúram error messages are subject to change without notice. However, in the specific case of the pattern match failure message, the error -122128 - ERR\_CONV\_NO\_MATCH will be preserved, as the possible need to intercept this message is recognized.

## Custom Default Values

It is unlikely that you will ever need to customize a default value plug-in for a domain. The displayed default value can be customized using the respective UML domain definition option. The predefined assumed default values for the domains are probably sufficient for every need. However, in the unlikely event that you need to customize an assumed default value, the steps are little different from those for other plug-ins.

Another reason for customizing a default value plug-in is where the displayed default value is not fixed and cannot be defined in the UML model. An example of this is the use of the current date as a displayed default value.

1. Identify an existing default value plug-in class that you want to customize.
2. Create a new sub-class of the relevant default value plug-in and override the `getDisplayedDefault` method.
3. The implementation of the method should simply return a value compatible with the Java type used to represent values for the relevant root domain. These Java types are listed in “Java Object Representations” on page 284.
4. Configure your new plug-in for the relevant domains.

In this example, the displayed default value for an interest rate is calculated dynamically using a notional `CentralBank` class that somehow returns the current



interest rate.

```
/**
 * Returns the current interest rate by contacting the
 * central bank!
 */
public class InterestRateDefault
    extends SvrFloatDefault {
    public Object getDisplayedDefault()
        throws DomainException {
        try {
            return new Float(CentralBank.getInterestRate());
        } catch (Exception e) {
            throw new CustomDomainException(-200099, e);
        }
    }
}
```

*Figure 125. Custom Default Date-Time Value*

The example assumes that the `InterestRateDefault` class will be associated with a descendant of the `SVR_FLOAT` domain that requires a default value to be of the `java.lang.Float` type. By extending the `SvrFloatDefault` class, the new default value plug-in will automatically use zero as the assumed default interest rate value.

The exception handling uses a `CustomDomainException` class. As the `getDisplayedDefault` method throws a `DomainException`, and not a `ConversionException`, you could create such a custom exception class by deriving it from `DomainException` in exactly the same way as the `CustomConversionException` class was derived from `ConversionException` in “Custom Exception Classes” on page 281. You might note that, as the `DomainException` class is an ancestor of the `CustomConversionException` class that the `CustomConversionException` class could be used here instead. This will work, but you must not attempt to report a message containing the “%0s” placeholder for the field label, as automatic replacement of the field label is not supported when a `DomainException` type is expected.

The example above shows the unknown exception thrown by the `CentralBank` class being added to the new custom exception. You only need to implement the appropriate constructor to support this. The super-class already has a constructor with the same signature, so your constructor's implementation need only call that. There is no need to extract a string value or stack trace from the exception; all will be reported correctly when necessary.

## Advanced Topics

### Type Checking and Null Checking

You may have noticed that none of the examples in this chapter show the string or object values passed to the methods being checked to see if they are null or of the wrong type. The reason is that it is not necessary. The client infrastructure guarantees that no method will be called with a null value and that no conversion operation will be invoked for an object that is not compatible with the class returned by the converter plug-in's `getDomainClass` method. Your custom code need never include any error handling and reporting code for these checks.

### Plug-in Instance Management

For efficiency, a Cúram client application pools the minimum number of domain plug-in instances possible. This reduces the overhead involved in creating new

plug-in instances each time their operations are invoked, but it does impose some restrictions on the way plug-ins can be written.

Domain plug-ins maintain state information: a reference to the domain and the active user's locale. Custom code can access this state information by calling the `getDomain` and `getLocale` methods and use it as required. The potential for concurrent access to plug-ins in typical multi-threaded servers impacts the way the plug-in instances (with their state information) are managed. If concurrent requests are received from users who are using different locales, then the same plug-in instance cannot be used when servicing these requests, as only one locale value can be set in a plug-in instance. However, as any Cúram application only supports a finite number of locales, maintaining a single plug-in instance for each locale is sufficient to avoid concurrency problems or synchronization overheads. This, of course, has to be multiplied by the number of domains, as the domain information also constitutes state. The result is that each domain in the domain hierarchy accesses a pool of plug-in instances specific to that domain and each pool contains one instance of each type of plug-in for each locale.

This instance management system is entirely driven by the plug-ins themselves. Each type of plug-in can implement its own instantiation strategy most appropriate to its needs. However, to avoid over-complicating instance management, the `AbstractDomainPlugIn` class (see “Extending Existing Plug-ins” on page 271) implements the single, consistent pooling strategy that balances efficiency against other considerations.

While it would be more efficient to dispense with the domain and locale state information and pass these values to the various converter and comparator methods, this poses several other problems that make this approach less desirable:

- The method signatures would be complicated by values that may not be used.
- Some method signatures, such as the `compare` method of the `java.util.Comparator` interface would not be compatible.
- The addition of new state information in the future would break all existing implementations. Using accessor methods for state information allows the abstract super-classes to implement the accessors and the signatures of the other interface methods can remain unchanged. During an upgrade no changes would need to be made to any existing custom code that has followed the guidelines and extended these abstract super-classes or other classes derived from them.

It is this latter point that is most important, successful upgrades depend on custom code that does not attempt to implement the plug-in interfaces from scratch. This is why such an approach cannot be supported.

The pooling strategy used means that there is one main limitation on how plug-ins can be written: plug-ins must not attempt to store any state information. In short, *no customization should add fields to a plug-in class* and attempt to store information in them; concurrent application requests will probably cause such a plug-in to fail intermittently or introduce obscure bugs.

Domain plug-in classes must also provide a default constructor (i.e., a constructor that takes no arguments). However, any Java class that does not explicitly define a default constructor will automatically have one defined for it if the default constructor of an ancestor class is visible. For custom plug-in classes that extend the plug-in classes and abstract plug-in classes provided with the out-of-the-box Cúram application, no explicit default constructor is required.

## Naming Conventions

Custom domain plug-in classes may implement utility methods to support the implementation of the main interface methods. An example is the `_pad` method shown in “Custom Sorting” on page 289. To avoid inadvertently overriding another inherited method, or using a method name that conflicts with a method introduced in a later Cúram release, you should prefix such utility methods with an underscore character as shown. Underscore characters will not be used in the client infrastructure, so they will guarantee that no naming conflict will arise in the future. For similar reasons, do not create classes in packages that might conflict with Cúram package names. All Cúram packages begin with “curam”, so avoiding that name is sufficient. The examples in this chapter used the package name prefix “custom”, but this is not a requirement.

## Generic Parse Operations

The generic parse operation, performed by the `DomainConverter` interface's `parseGeneric` method, needs some explanation, so that care can be taken not to disable its operation by mistake. The generic parse operation is responsible for parsing the string representation of values defined in the UML model's domain definition options. Domain options for maximum, minimum and default values are expressed in formats that are not locale-specific, as the UML model is not locale-aware. Each of the root domains accepts values in a particular format (e.g., ISO-8601 format for `SVR_DATE` domains) and customization of this format is not supported. Therefore, the default implementations of the `parseGeneric` method must be respected.

For some domains, the format supported by the converter's parse method is the same as the format supported by the `parseGeneric` method. The default implementation of the `parseGeneric` method in the `AbstractConverter` class just calls the `parse` method (which is not implemented in this class). Therefore, if you sub-class the `AbstractConverter` class and implement a `parse` method, the same implementation will be used by the `parseGeneric` method. This may be what you require, but, if it is not, you may want to implement a different `parseGeneric` method.

All of the out-of-the-box, concrete converter classes separate the implementations of the two methods, so you can override one without changing the behavior of the other. Again, this may be what you require, but, if it is not, you may want to override both methods.

## Code-Tables

Data conversion and sorting for code-table domains should be managed via the code-table administration interface. While the client infrastructure uses the same plug-in mechanism described here to manage code-table values, the customization of code-table-related plug-ins is not supported. Code-table data is more complex to handle (formatting and parsing are not symmetrical operations as they are for other types) and all of the necessary customizations can be accomplished without resorting to programmatic means.

The formatting of code-table values is achieved by modifying the descriptions of each code. Parsing operations receive the code values and simply pass them on. Pre-parsing, pre-validation, and validation are not important. Default codes and custom sort orders are controlled entirely via the administration interface.

---

## Online Help Development

You can embed help information in the Cúram web client with the Cúram Online Help system.

The online help framework is composed of the help entries that are located within property files associated with UIM. These entries provide help about specific properties -i.e., fields and actions - that have been defined in the associated UIM file. Within these property files, help entries are situated on the line immediately following the corresponding property definition. When the online help page is generated, all field and action help definitions are listed in an easy to understand table format.

### Single Source Development

The online help is developed within UIM property files. Each property defined in a property file is immediately followed by a corresponding help definition. This enables online help developers to easily compare and update UIM properties and help entries. In addition, having application properties and help within the same file removes the need to maintain and synchronize a separate set of files for the help system.

### Integrated Localization

Online help localization is integrated with application localization. When localized properties files are created for a particular locale, those property files will contain localized entries for both UIM properties and the help properties.

### Automatic Generation

Once the help content is added into the UIM property files, online help must be generated as part of the "client" build target. At runtime online help is generated dynamically and thus does not need to be deployed separately to the main application. This aids developers in reviewing their online help pages quickly.

### Accessing the Help Page

Access to each help page is provided in a context-sensitive manner; i.e., when a user presses the help icon on an application page, it opens the corresponding help page in a new window.

### Accessibility Features

Curam online help contains accessibility features that enable the help to be accessed by users with disabilities. The following accessibility features are used:

#### Alternative Text

Alternate text allows screen readers to provide additional descriptions for non-text elements. Alternate text is provided for all help links and help buttons.

### Elements of Online Help

#### Introduction to Curam Client Pages

Full Curam developer knowledge is not necessary to develop Curam Online Help content, but a basic familiarity with the development structure is required. Client pages are installed in the webclient/components directory of the Curam installation. Each page has a UIM (User Interface Metadata) file associated with it that defines its content - links, buttons, fields. The UIM file does not contain any

actual text - it uses externalized properties files, which map property names to text strings. UIM files may also import VIM files. VIM files are in the same format as UIM files, they basically define a fragment of a UIM file. They also have properties files. The association between the UIM/VIM and the property file is simple - they have the same name, apart from the file extension.

The online help content is composed of extra entries embedded in client property files. Properties are lines of text of the form:

PropertyName=Value of Property

If a button on a page is labeled in the UIM file with the property Button.Save, the following properties file entry will exist

Button.Save=Save

To explain this in the online help, create another property called Button.Save.Help  
Button.Save.Help=Use this button to save.

The online help framework is responsible for generating this into the online help format.

## Page Descriptions

Use the Help.PageDescription property to provide a high-level overview of what the page is for. This should not be used to provide details for each field or button - this can be done elsewhere.

Help.PageDescription=This page allows you to view a clause record. Clauses describe the precedents for a decision made on an appeal and the legal articles that affect it. These clauses can be dynamically inserted into decision documents.

## Links and Actions

If there are any labeled links or action controls on the page, a help entry can be provided with a description for them. When creating help entries, the online help system will create a table for them, complete with title and abstract.

ActionControl.Label.Save=Save

ActionControl.Label.Save.Help=The Save action creates a new record from the information entered on the page.

## Fields and Columns

Help entries can also be provided for labeled fields or columns on a page. The online help system will generate a separate table for these help entries.

Field.Label.Language=Language

Field.Label.Language.Help=The language for the clause from the drop-down list of languages, e.g., English, French.

## Adding or Updating Help content

Help can be added for any new properties within the existing property file. However before updating online help it is important to read the chapter on "Domain-Specific Controls" on page 209

### Updating Help for non 'Domain Specific Controls'

In order to update the online help, the following steps should be followed:

1. **Identify the correct property file to edit, in order to update the online help:**  
The help text for a particular page in the application is contained in the property file with the same name. For example, if the online help for the 'Person Search' in the application needs to be updated then this means that

some property/properties referenced by the Person\_search.uim file will have to be customized. In this case, these properties are contained in a file named Person\_search.properties.

2. **Location where to update online help** The property file that is being updated should be modified in the 'webclient/components/custom' directory only. E.g. If the 'webclient/components/core/Person/Search/Person\_search.properties' needs to be updated, then copy this file straight in to the 'webclient/components/custom' directory. The 'Person/Search' directories don't need to be created in the custom directory.
3. Modify the relevant property file as described in the earlier sections of this chapter.
4. Build client after making all the changes. Help is built by default as part of the client build target. The help is generated dynamically at runtime and does not need to be explicitly included in the application.

### Updating Help for 'Domain Specific Controls'

The address elements for a particular type of address would be a good example of a Domain Specific Control. The field elements that are displayed on a page in the application depend on the locale that is specified. For instance the format of the address elements displayed for an address in the US would be different from those displayed in the UK. For this reason, the online help cannot be specified for each of the elements within an address. For example, in the 'Register Employer' page in the application there is a registered address and a business address. The name of the properties file which relates to this page is Employer\_registerView.properties . In order to update the online help regarding the Employer's business address and registered we could add help properties as follows:

```
# ADDING HELP HERE FOR REGISTERED ADDRESS
Field.Label.RegisteredAddress.Help=
The Employer can enter their registered address in the fields displayed.
The format of the
Employers registered address will depend on the Country in which they reside.
Field.Label.BusinessAddress=Business Address
# ADDING HELP HERE FOR BUSINESS ADDRESS
Field.Label.BusinessAddress.Help=
The Employer can enter their business address in the fields displayed.
The format of the
Employers business address will depend on the Country in which they reside.
```

---

## Maintaining Dynamic UIM Pages

Use this information to learn how to load dynamic UIM pages into the application resource store.

The way you store your screens differs depending on whether you are working in a development environment or a running system.

**Important:** Currently the development of custom dynamic UIM pages is only supported for the presentation of decision details only. Development of dynamic UIM for any purpose beyond this is not supported.

## Working in a Development Environment

In order to load a dynamic UIM page into the resource store, you must add two separate entries to the AppResource.dmx file in the custom component, each entry corresponding to a dynamic UIM file and an associated properties file.

The following is an example of how to add the *DUIMSample* dynamic UIM page to the `AppResource.dmx` file, so that it will be loaded into the application resource store at build time.

```

<row>
  <attribute name="resourceid">
    <value>1</value>
  </attribute>
  <attribute name="localeIdentifier">
    <value/>
  </attribute>
  <attribute name="name">
    <value>DUIMSample</value>
  </attribute>
  <attribute name="contentType">
    <value>text/plain</value>
  </attribute>
  <attribute name="contentDisposition">
    <value>inline</value>
  </attribute>
  <attribute name="content">
    <value>./custom/data/initial/clob/DUIMSample.uim</value>
  </attribute>
  <attribute name="internal">
    <value>0</value>
  </attribute>
  <attribute name="lastWritten">
    <value>2011-06-13-19.29.40</value>
  </attribute>
  <attribute name="versionNo">
    <value>1</value>
  </attribute>
  <attribute name="category">
    <value>RS_XML</value>
  </attribute>
</row>
<row>
  <attribute name="resourceid">
    <value>2</value>
  </attribute>
  <attribute name="localeIdentifier">
    <value/>
  </attribute>
  <attribute name="name">
    <value>DUIMSample.properties</value>
  </attribute>
  <attribute name="contentType">
    <value>text/plain</value>
  </attribute>
  <attribute name="contentDisposition">
    <value>inline</value>
  </attribute>
  <attribute name="content">
    <value>./custom/data/initial/clob/DUIMSample.properties</value>
  </attribute>
  <attribute name="internal">
    <value>0</value>
  </attribute>
  <attribute name="lastWritten">
    <value>2011-06-13-19.29.40</value>
  </attribute>
  <attribute name="versionNo">
    <value>1</value>
  </attribute>
  <attribute name="category">
    <value>RS_PROP</value>
  </attribute>
</row>

```

**Note:** The value of the *contentType* attribute specifies the location on the file system that each entry (dynamic UIM file and associated properties file) can be uploaded



from. The value of the *category* attribute in the *AppResource.dmx* categorizes a dynamic UIM page resource so that they can be distinguished from other kinds of resources in the resource store. The dynamic UIM file should be categorized (as shown in the example) as a *RS\_XML* resource. The associated properties file should be categorized as *RS\_PROP*. Each dynamic UIM resource that is added to the *AppResource.dmx* should also be given the same value so that they all belong to the same category. See the section below for details of how new dynamic UIM pages are loaded into the resource store at runtime. The value of the *localeIdentifier* attribute should be empty (as in the example) if the user's required locale is English. Otherwise the actual locale should be used as the value for this attribute for both the UIM and properties file.

## Working in a Running System

In order to navigate to the home dynamic UIM administration screen in the application, the user must do the following:

- Log into the “admin” application.
- From the shortcut menu, select the “Dynamic UIM” menu item from the “Dynamic UIM” category. This should open the home dynamic UIM administration screen

A user can maintain dynamic UIM pages in the resource store by performing the following actions:

- Add a dynamic UIM page to the Resource Store
- Edit a dynamic UIM page in the Resource Store
- Delete a dynamic UIM page from the Resource Store
- Validate a dynamic UIM page in the Resource Store

### Search for Dynamic UIM Pages by Category

In order to view the current list of dynamic UIM pages in the resource store you must perform a search based on the resource store category. This can be done from the home dynamic UIM administration screen as follows:

- Select a menu item for the drop-down list on “Category Search” field.
- Click on the “Search” button. This will return the list of dynamic UIM pages for the selected category.

### Uploading a Dynamic UIM page to the Resource Store

From the home dynamic UIM administration screen, a dynamic UIM page can be added to the resource store by doing the following

- Select the New... page level action control. This will open a modal dialog page with four mandatory fields.
- Enter the value of the page *Page ID* field. The value must be the same as the value of the *PAGE\_ID* attribute in the UIM file that is being uploaded, otherwise an error message will be displayed.
- Select the locale from the drop-down list on the *locale* field. The default is locale is English.
- Use the “Browse” button on the “UIM File” field to navigate to the dynamic UIM file that is to be uploaded to the resource store. As indicated, this is a mandatory field.
- Use the “Browse” button on the “Properties File” field to navigate to the associated properties file to upload to the resource store. As indicated, this is a mandatory field.

## Editing a Dynamic UIM page in the resource store

From the home dynamic UIM administration, a dynamic UIM page can be added to the resource store by doing the following:

- From the list of dynamic UIM pages displayed, navigate to the dynamic UIM page that you would like to edit (by Page ID), and select the “Edit...” menu item for the list action menu. This should open a modal dialog page with three fields.
- If you would like to download the current version of the dynamic UIM file and associated properties file (to be edited) from the Resource Store the locale file system, then select the “Download” button and save the zip file - containing both aforementioned files - to the file system. The dynamic UIM file and associated properties file can then be unzipped from the downloaded zip and edited as required.
- Use the “Browse” button on the “UIM File” field to navigate to the dynamic UIM file that is to be uploaded to the resource store. As indicated, this is a mandatory field.
- Use the “Browse” button on the “Properties File” field to navigate to the associated properties file to upload to the resource store. As indicated, this is a mandatory field.

## Deleting a Dynamic UIM File from the Resource Store

From the home dynamic UIM administration, a dynamic UIM page can be deleted from the resource store by doing the following:

- From the list of dynamic UIM pages displayed, navigate to the dynamic UIM page that you would like to edit (by Page ID), and select the “Delete...” menu item for the list action menu. As a result of this action a modal dialog will be displayed, with a message looking for confirmation that you want to delete the selected dynamic UIM page from the resource store.
- The Yes button should be selected to delete the dynamic UIM page from the resource store. A new search for dynamic UIM pages in the resource store should reflect the fact that this dynamic UIM page has been removed from the resource store.

## Validating a dynamic UIM file in the resource store

From the home dynamic UIM administration, a dynamic UIM page can be validated in the resource store by doing the following:

- From the list of dynamic UIM pages displayed, navigate to the dynamic UIM page that you would like to edit (by Page ID), and select the “Validate...” menu item for the list action menu. As a result of this action a modal dialog will be displayed, with a message stating whether the validation has passed or failed. If the validation fails, then the source of the error page will appear in the dialog and the full details of the error can be found in the server logs.

## Publish dynamic UIM files

The changes to the dynamic UIM files will not be made public until they are intentionally published to the resource store. This can be done by selecting the “Publish...” page action control from the home dynamic UIM administration screen. This action will open a modal dialog page asking for confirmation that the changes are to be published to the resource store.

---

## Unsupported Features in Dynamic UIM

Learn about the elements and attributes that are not supported in dynamic UIM.

## PAGE

Table 137. Unsupported PAGE Features

Name	Feature Type
FIELD	Child Element
CONTAINER	Child Element
WIDGET	Child Element
INCLUDE	Child Element
SHORTCUT_TITLE	Child Element
TAB_NAME	Child Element
JSP_SCRIPTLET	Child Element
SCRIPT	Child Element
SCRIPT_FILE	Attribute
POPUP_PAGE	Attribute
APPEND_COLON	Attribute
HIDE_CONDITIONAL_LINKS	Attribute
COMPONENT_STYLE	Attribute
TYPE	Attribute

## PAGE TITLE

For full details on the supported features of this element in static UIM, see “PAGE TITLE” on page 101.

Table 138. Unsupported PAGE\_TITLE Features

Name	Feature Type
DESCRIPTION	Child Element
ICON	Attribute

## CLUSTER

For full details on the supported features of this element in static UIM, see “CLUSTER” on page 62.

Table 139. Unsupported CLUSTER Features

Name	Feature Type	Supported/Unsupported attribute values
TITLE	Child Element	
DESCRIPTION	Child Element	
WIDGET	Child Element	
SUMMARY	Attribute	
TAB_ORDER	Attribute	

## LIST

For full details on the supported features of this element in static UIM, see “LIST” on page 89.

Table 140. Unsupported LIST Features

Name	Feature Type	Supported/Unsupported attribute values
TITLE	Child Element	
DESCRIPTION	Child Element	
FOOTER_ROW	Child Element	
ACTION_CONTROL	Child Element	
SUMMARY	Attribute	
SORTABLE	Attribute	
PAGINATED	Attribute	
DEFAULT_PAGE_SIZE	Attribute	
PAGINATION_THRESHOLD	Attribute	

## FIELD

For full details on the supported features of this element in static UIM, see “FIELD” on page 72.

Table 141. Unsupported FIELD Features

Name	Feature Type
LABEL	Child Element
SCRIPT	Child Element
EDITABLE	Attribute
LABEL_ABBREVIATION	Attribute
DESCRIPTION	Attribute
INITIAL_FOCUS	Attribute
ALT_TEXT	Attribute
CONTROL	Attribute
CONFIG	Attribute

## CONTAINER

For full details on the supported features of this element in static UIM, see “CONTAINER” on page 69.

Table 142. Unsupported CONTAINER Features

Name	Feature Type
IMAGE	Child Element
LABEL_ABBREVIATION	Attribute

## ACTION\_SET

For full details on the supported features of this element in static UIM, see “ACTION SET” on page 60.

Table 143. Unsupported ACTION\_SET Features

Name	Feature Type
CONDITION	Child Element
SEPARATOR	Child Element
TOP	Attribute
BOTTOM	Attribute

## WIDGET

For full details on the supported features of this element in static UIM, see “WIDGET” on page 108.

Table 144. Unsupported WIDGET Features

Name	Feature Type	Supported/Unsupported attribute values
WIDTH	Attribute	
WIDTH_UNITS	Attribute	
ALIGNMENT	Attribute	
HAS_CONFIRM_PAGE	Attribute	
CONFIG	Attribute	
COMPONENT_STYLE	Attribute	
TYPE	Attribute	Only the value SINGLESELECT and MULTISELECT are supported, all other values are unsupported

## ACTION\_CONTROL

For full details on the supported features of this element in static UIM, see “ACTION CONTROL” on page 56.

Table 145. Unsupported ACTION\_CONTROL Features

Name	Feature Type	Supported/Unsupported attribute values
CONNECT	Child Element	
SCRIPT	Child Element	
CONDITION	Child Element	
LABEL_ABBREVIATION	Attribute	
IMAGE	Attribute	
CONFIRM	Attribute	
DEFAULT	Attribute	
ACTION_ID	Attribute	

Table 145. Unsupported ACTION\_CONTROL Features (continued)

Name	Feature Type	Supported/Unsupported attribute values
TYPE	Attribute	<p>Only the values ACTION and SUBMIT (An action of type SUBMIT is not supported within a list action menu or a page level action menu. A list action menu is an ACTION_SET element within a LIST that has a value of 'LIST_ROW_MENU' on it's 'TYPE' attribute. A page level action menu is an ACTION_SET defined at the PAGE level. See the "ACTION SET" on page 60 for further details. All other submit actions are supported.) are supported, all other values are unsupported</p> <p>(An action of type SUBMIT is not supported within a list action menu or a page level action menu. A list action menu is an ACTION_SET element within a LIST that has a value of 'LIST_ROW_MENU' on it's 'TYPE' attribute. A page level action menu is an ACTION_SET defined at the PAGE level. See the "ACTION SET" on page 60 for further details. All other submit actions are supported.)</p>

## LINK

For full details on the supported features of this element in static UIM, see "LINK" on page 84.

Table 146. Unsupported LINK Features

Name	Feature Type
CONDITION	Child Element
PAGE_ID_REF	Attribute
SAVE_LINK	Attribute
URL	Attribute
URI_REF	Attribute
URI_SOURCE_NAME	Attribute
URI_SOURCE_PROPERTY	Attribute
SET_HIERARCHY_RETURN_PAGE	Attribute
USE_HIERARCHY_RETURN_PAGE	Attribute
HOME_PAGE	Attribute

## INLINE\_PAGE

For full details on the supported features of this element in static UIM, see “INLINE PAGE” on page 79.

*Table 147. Unsupported INLINE\_PAGE Features*

Name	Feature Type
URI_SOURCE_NAME	Attribute
URI_SOURCE_PROPERTY	Attribute

## MENU

For full details on the supported features of this element in static UIM, see “MENU” on page 93.

*Table 148. Unsupported MENU Features*

Name	Feature Type	Supported/Unsupported attribute values
CONNECT	Child Element	
MODE	Attribute	Only the value IN_PAGE_NAVIGATION is supported, all other values are unsupported.

## SERVER\_INTERFACE

For full details on the supported features of this element in static UIM, see “SERVER INTERFACE” on page 104.

*Table 149. Unsupported SERVER\_INTERFACE Features*

Name	Feature Type
ACTION_ID_PROPERTY	Attribute

## INFORMATIONAL

Only Informationals whose connections endpoints are associated with a server interface defined in the DISPLAY phase, are supported. See “INFORMATIONAL” on page 78 for more details on informationals.). Informationals with other any type of connection endpoints are not supported.

---

## UIM Support in Universal Access

Learn about the elements and attributes that have limited support or are not supported in Universal Access.

### Description

UIM Screens can be used in the Universal Access user interface. However, only a subset of UIM features support the alternate look and feel in Universal Access.

## UIM Support in UA

The following table summarizes the supported UIM elements in the Universal Access, and the contexts they are supported in.

Table 150. UIM in the Universal Access

UIM Element Name	Parent UIM Element Name	Main Content Panel Context	Modal Dialog Context	DETAILS_ROW Context	Notes
ACTION_SET	PAGE	Support for up to 2 items divided by a separator	Supported	Unsupported	The buttons will be displayed in the Universal Access look and feel.
ACTION_SET	CLUSTER	Supported	Supported	Unsupported	The buttons will be displayed in the Universal Access look and feel.
ACTION_SET	LIST	Unsupported	Unsupported	Unsupported	
ACTION_SET[@TYPE="LIST_ROW_MENU"]	LIST_ROW_MENU	Supported	Unsupported	Unsupported	The ACTION_CONTROL element <b>can</b> be used in the column of a LIST
ACTION_CONTROL	CONTAINER	Supported	Supported	Supported	
PAGE_TITLE	-	Supported	Supported	n/a	
DESCRIPTION	-	Supported	Supported	n/a	
CLUSTER	-	Supported	Supported	Supported	The collapsible behavior is <b>not</b> supported. Nesting of clusters is <b>not</b> supported.
LIST	-	Supported	Supported	Supported	The collapsible behavior is <b>not</b> supported. Paginated lists, scrollable lists and nested lists are <b>not</b> supported.
DETAILS_ROW	LIST	Supported	Supported	Supported	Nesting of expandable lists is <b>not</b> supported.



Table 150. UIM in the Universal Access (continued)

UIM Element Name	Parent UIM Element Name	Main Content Panel Context	Modal Dialog Context	DETAILS_ROW Context	Notes
FIELD	-	Support for the following input types only: text input, text area, code table drop-downs, date picker, password	Support for the following input types only: text input, text area, code table drop-downs, date picker, password	Unsupported	Code-table hierarchy and all other items not defined in the cell for Main Content Panel or Modal Dialog are <b>not</b> supported



---

## Notices

This information was developed for products and services offered in the United States.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 US*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan Ltd. 19-21, Nihonbashi-Hakozakicho, Chuo-ku Tokyo 103-8510, Japan*

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created

programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 US*

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data and client examples cited are presented for illustrative purposes only. Actual performance results may vary depending on specific configurations and operating conditions.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

---

## Privacy Policy considerations

IBM Software products, including software as a service solutions, (“Software Offerings”) may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering’s use of cookies is set forth below.

Depending upon the configurations deployed, this Software Offering may use session cookies or other similar technologies that collect each user’s name, user name, password, and/or other personally identifiable information for purposes of session management, authentication, enhanced user usability, single sign-on configuration and/or other usage tracking and/or functional purposes. These cookies or other similar technologies cannot be disabled.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM’s Privacy Policy at <http://www.ibm.com/privacy> and IBM’s Online Privacy Statement at <http://www.ibm.com/privacy/details> the section entitled “Cookies, Web Beacons and Other Technologies” and the “IBM Software Products and Software-as-a-Service Privacy Statement” at <http://www.ibm.com/software/info/product-privacy>.

---

## Trademarks

IBM, the IBM logo, and [ibm.com](http://www.ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at “ Copyright and trademark information ” at <http://www.ibm.com/legal/copytrade.shtml>.

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

Java™ and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Linux is a registered trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other names may be trademarks of their respective owners. Other company, product, and service names may be trademarks or service marks of others.





Printed in USA