

IBM Cúram Social Program Management
Version 7.0.10

Cúram Intake Developer's Guide



Note

Before using this information and the product it supports, read the information in [“Notices” on page 17](#)

Edition

This edition applies to IBM® Cúram Social Program Management v7.0.10 and to all subsequent releases unless otherwise indicated in new editions.

Licensed Materials - Property of IBM.

© **Copyright International Business Machines Corporation 2012.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

© .

Contents

Figures.....	iv
Tables.....	v
Chapter 1. Developing with Intake.....	1
Introduction.....	1
Overview.....	1
Purpose.....	1
Audience.....	1
Defining Triage.....	1
Introduction.....	1
Setting up a Triage Definition.....	1
Adding Urgent Alerts to the Rule Set.....	2
Recommending Services.....	2
Recommending Programs.....	3
Defining Screenings.....	3
Introduction.....	3
Setting up a Screening Definition.....	3
Adding Urgent Alerts to the Rule Set.....	9
Recommending Programs.....	9
Configuring Check Eligibility.....	10
Introduction.....	10
Configuring an Application Case for Eligibility Checks.....	10
Configuring the Eligibility Check Rule Set.....	10
Configuring the Results Display Page.....	11
Configuring a PCR Rule Set.....	11
Introduction.....	11
Configuring a PCR Rule Set.....	11
Mandatory Rule Attributes.....	12
Specifying Rule Set Properties Text.....	13
Configuring Authorization Rule Sets.....	13
Introduction.....	13
Intake Rule Sets.....	13
Determining the Programs to be Authorized.....	14
Writing the Authorize Application Rule Class.....	14
Determining the Clients to be Added to the Product Delivery.....	14
Writing the Client Selection Rule Class.....	14
Intake Process XML Definition.....	15
Intake Process XML Definition.....	15
Ability to allow activation of evidence which would not otherwise be activated as part of the application case authorization process.....	15
Intake Environment Variables.....	15
Application Properties.....	15
Notices.....	17
Privacy Policy considerations.....	18
Trademarks.....	18

Figures

1. For example:..... 5

Tables

1. Triage Attributes..... 2

2. Screening Attributes..... 3

3. ProgramType Attributes for a Screening..... 4

4. ProgramType Attributes for a Screening..... 10

5. Mandatory Rule Attributes for PCR Rule Sets..... 12

6. Abstract Attribute(s) To Be Implemented..... 14

7. Abstract Attribute(s) To Be Implemented..... 14

8. Intake Environment Variables..... 16

Chapter 1. Developing with Intake

An intake process definition XML document is required for Cúram Intake. Triage and screening definitions are configured in the intake process definition XML document. There are three configuration options for the application case that drive the check eligibility process: eligibility check rule set, eligibility check strategy, and the results page. A PCR rule set is required for PCR processing. Application authorization rules sets must also be configured.

Introduction

Overview

Use this information to understand the functions that Cúram Intake supports for collecting data when a client applies to an organization for benefits or services provided by that organization.

Cúram Intake provides functions to support the following intake processes:

- Application
- Triage
- Screening

Each of these processes can be used for capturing data about the client when they apply to an organization for benefits or services provided by that organization. Defining triage and screening, and the configurations that are required for each, is covered in the following documentation.

Configuring an application is covered in the *Cúram Intake Configuration Guide*.

Purpose

This document provides an overview of the Cúram Intake development process. It details key elements such as the configurations required for screening and triage as well as the rule sets which need to be configured for running PCR, checking eligibility, selecting clients, and authorizing at the application case level.

Audience

This guide is intended to be used by architects and developers interested in configuring a custom Intake solution.

Defining Triage

Introduction

Triage allows a case worker to quickly gauge a client's needs when they phone or visit by asking a core set of fundamental questions. The result allows the case worker to understand the client's situation in relation to the core needs. A triage can be performed by the case worker resulting in a list of suitable services, service providers, and programs to help meet the client's needs.

Setting up a Triage Definition

- Open the XML document which represents the intake process definition - see Appendix A.
- Create or locate an XML element `IndividualConfiguration` as a direct child of the `IntakeProcess` element.

Note: Only one IndividualConfiguration element may exist in the document.

- Create or locate an XML element Triage as a direct child of the IndividualConfiguration element previously located.
- On this element the following attributes can be specified which will define the Triage process:

Table 1. Triage Attributes.

This table describes the attributes for a triage definition:

Attribute Name	Type	Purpose
DataStore	String	This attribute specifies the name of the datastore schema to be used for the IEG script that will be executed to capture the details of the triage.
RuleSet	String	This attribute specifies the name of the CER rule set to be used to process the answers from the script into recommendations for programs and services.
RuleSetClass	String	This attribute specifies the name of the CER rule class in the CER rule set which is used to calculate the recommendations of the triage.
ScriptName	String	This attribute specifies the name of the IEG script which will be used to capture the details of the triage.
ScriptType	String	This attribute specifies the type of IEG script which will be used to capture the details of the triage.
ScriptVersion	String	This attribute specifies the type of IEG script which will be used to capture the details of the triage.

Adding Urgent Alerts to the Rule Set

To output an urgent alert from the CER rule set, the rule class defined in the triage definition should have an attribute named alertMessages. This attribute has as its type a list of rule classes of type AlertMessage. Each AlertMessage which is calculated and passed into this list will appear as an urgent alert on the Triage Result page in the application.

Recommending Services

To recommend a service from the CER rule set, the rule class specified in the triage definition should have an attribute named services. This attribute has as its type a list of rule classes which subclass the AbstractService type. Each AbstractService which is calculated and passed into this list will appear as a recommended service on the Triage Result page in the application.

Recommending Programs

To recommend a program from the CER rule set, the rule class defined as part of triage definition should have an attribute named `programs`. This attribute has as its type a list of rule classes which subclass the type `AbstractProgram`. Each `AbstractProgram` which is calculated and passed into this list will appear as a recommended program on the Triage Result page in the application.

Defining Screenings

Introduction

Screening allows a client to determine if they are potentially eligible for one or more programs based on a set of high level, guided questions. Potential eligibility for the selected programs is determined by running eligibility rules against the client's responses to the questions.

Setting up a Screening Definition

- Open the XML document which represents the intake process definition - see Appendix A.
- Create or locate an XML element `IndividualConfiguration` as a direct child of the `IntakeProcess` element. Only one `IndividualConfiguration` element may exist in the document.
- Create or locate an XML element `Screening` as a direct child of the `IndividualConfiguration` element previously located. There can be as many `Screening` elements as are required.
- On this element the following attributes can be specified which are used to define the screening process.

Table 2. Screening Attributes.

This table describes the attributes that can be set for a screening definition.

Attribute Name	Type	Purpose
Type	Code Table Entry	This attribute specifies the category of screening. The category is an entry from the <code>ScreeningCategory</code> code table. Only one screening script can be specified for each screening category, and as such this is a unique attribute.
DataStore	String	This attribute specifies the name of the data store schema to be used for the IEG script that is executed to capture the details of the screening.
RuleSet	String	This attribute specifies the name of the CER rule set to be used to process the answers from the screening script into recommendations for programs.
RuleSetClass	String	This attribute specifies the name of the CER rule class in the CER rule set which is used to calculate the recommendations of the screening.

Table 2. Screening Attributes.

This table describes the attributes that can be set for a screening definition.

(continued)

Attribute Name	Type	Purpose
ScriptName	String	This attribute specifies the name of the IEG script which is used to capture the details of the triage.
ScriptVersion	String	This attribute specifies the type of IEG script which will be used to capture the details of the triage.

Specifying whether Programs are Available Internally or Externally

- Open the XML document which represents the intake process definition - see Appendix A.
- Locate the XML element Screening which is to be defined.
- For each program that the intake process will support, create an element ProgramType as a direct child of the Screening element.
- For each program that the intake process will support, create an element ProgramType as a direct child of the Screening element.

Table 3. ProgramType Attributes for a Screening.

This table describes the attributes that can be set for a screening definition.

Attribute Name	Type	Purpose
ProgramType	Code Table Entry	This attribute should contain an entry from the code table 'ProgramType'. This is a code table which specifies a program type, e.g. medical assistance. This attribute is mandatory and must be specified.
Availability	String	This attribute should contain the value 'internal' if the program is available internally or 'external' if the program is available from a different agency.

- **DisplayStatus:** SCREENINGSTATUS: The set of statuses for which a screening should be displayed on the list pages. If a status is not listed here then screenings of that status will not be displayed in the user interface.

```
<?xml version="1.0" encoding="UTF-8"?>
<codetables package="curam.intake.codetable">
  <codetable java_identifier="SCREENINGSTATUS"
    name="SCREENINGSTATUS">
    <displaynames>
      <locale language="en">Screening Status</locale>
    </displaynames>
    <code default="true" java_identifier="IN_PROGRESS"
      status="ENABLED" value="SS19001">
      <locale language="en" country="US" sort_order="0">
        <description>In-Progress</description>
        <annotation></annotation>
      </locale>
    </code>
    <code default="false" java_identifier="COMPLETE"
      status="ENABLED" value="SS19002">
      <locale language="en" country="US" sort_order="0">
        <description>Complete</description>
        <annotation></annotation>
      </locale>
    </code>
    <code default="false" java_identifier="CANCELLED"
      status="ENABLED" value="SS19003">
      <locale language="en" country="US" sort_order="0">
        <description>Cancelled</description>
        <comments>Comments for Rejected in EN_US</comments>
        <annotation></annotation>
      </locale>
    </code>
  </codetable>
</codetables>
```

Figure 1. For example:

- Now, Please refer to the following example for guidance:

1.) Create the file CommonIntakeProcess.xml in the <EJBSERVER_HOME>\components\CommonIntake\data\initial\clob" folder.

```
<Screening DataStore="InternalApplication" RuleSet="FinancialAssistanceRuleSet"
RuleSetClass="FinancialAssistance"
  ScriptName="FinancialAssistanceApplicationScreening" ScriptVersion="V1"
type="SC19001" >
  <ProgramType availability="internal" type="PT19001"/>
  <ProgramType availability="internal" type="PT19002"/>
  <ProgramType availability="internal" type="PT19003"/>
  <DisplayStatus status="SS19002"/>
  <DisplayStatus status="SS19001"/>
</Screening>
```

2.)Following entries need to be made in the DMX files:

Note: If the dmx does not exist, then need to create a dmx file.

2.1)INTAKEPROCESSNAME.dmx - Entry of the Screening Process Name.

```
<row>
  <attribute name="intakeProcessID">
    <value>27900</value>
  </attribute>
  <attribute name="name">
    <value>CommonIntakeProcess</value>
  </attribute>
  <attribute name="state">
    <value>IPDS19002</value>
  </attribute>
  <attribute name="version">
    <value>1</value>
  </attribute>
</row>
```

2.2) INTAKEPROCESSCONFIGURATION.dmx - Entry of the process configuration.

```
<row>
  <attribute name="intakeProcessConfigurationID">
    <value>27900</value>
  </attribute>
  <attribute name="intakeProcessNameID">
    <value>27900</value>
  </attribute>
  <attribute name="optionXML">
    <value>./CommonIntake/data/initial/clob/CommonIntakeProcess.xml</value>
  </attribute>
</row>
```

```

</attribute>
</row>

```

2.3) INTAKEPROCESSROLEASSIGNMENT.dmx - Entry of the process role assignment.

```

<row>
  <attribute name="intakeProcessRoleAssignmentID">
    <value>27900</value>
  </attribute>
  <attribute name="intakeProcessID">
    <value>27900</value>
  </attribute>
  <attribute name="role">
    <value>CIAPP</value>
  </attribute>
  <attribute name="recordStatus">
    <value>RST1</value>
  </attribute>
</row>

```

2.4) IEGSCRIPTINFO.dmx - Information about where the IEG script is residing.

```

<row>
  <attribute name="scriptID">
    <value>FinancialAssistanceApplicationScreening</value>
  </attribute>
  <attribute name="type">
    <value>Screening</value>
  </attribute>
  <attribute name="scriptVersion">
    <value>V1</value>
  </attribute>
  <attribute name="name">
    <value>FinancialAssistanceApplicationScreening</value>
  </attribute>
  <attribute name="scriptDefinition">
    <value>./CommonIntake/data/initial/clob/
FinancialAssistanceApplicationScreening_V1_Screening.xml</value>
  </attribute>
  <attribute name="status">
    <value>ISS02</value>
  </attribute>
  <attribute name="versionNo">
    <value>1</value>
  </attribute>
  <attribute name="lastWritten">
    <value>SYSTIME</value>
  </attribute>
</row>

```

Note: If the dmx does not exist, then need to create a dmx file.

2.5) CREOLERULESET.dmx - Rule set information which is used to determine which products is the user eligible.

```

<row>
  <attribute name="creoleRuleSetID">
    <value>27011</value>
  </attribute>
  <attribute name="name">
    <value>FinancialAssistanceRuleSet</value>
  </attribute>
  <attribute name="ruleSetDefinition">
    <value>./../build/svr/creole.gen/Rules/components/CommonIntake/
FinancialAssistanceRuleSet.xml</value>
  </attribute>
  <attribute name="ruleSetVersion">
    <value/>
  </attribute>
  <attribute name="versionNo">
    <value>1</value>
  </attribute>
</row>

```

2.6) DATASTORESCHEMA.dmx - Datastore information which is used by the IEG script.

```
<row>
  <attribute name="schemaName">
    <value>InternalApplication</value>
  </attribute>
  <attribute name="schemaText">
    <value>./CommonIntake/data/initial/clob/InternalApplication.xsd</value>
  </attribute>
  <attribute name="versionNo">
    <value>1</value>
  </attribute>
  <attribute name="lastWritten">
    <value>SYSTIME</value>
  </attribute>
</row>
<row>
  <attribute name="schemaName">
    <value>InternalApplicationDomains</value>
  </attribute>
  <attribute name="schemaText">
    <value>./CommonIntake/data/initial/clob/InternalApplicationDomains.xsd</value>
  </attribute>
  <attribute name="versionNo">
    <value>1</value>
  </attribute>
  <attribute name="lastWritten">
    <value>SYSTIME</value>
  </attribute>
</row>
```

2.7) DATASTORESCHEMATRANSLATION.dmx - Data store schema translation information

```
<row>
  <attribute name="schemaName">
    <value>InternalApplication</value>
  </attribute>
  <attribute name="type">
    <value>DSST1</value>
  </attribute>
  <attribute name="localeIdentifier">
    <value language="en">en</value>
  </attribute>
  <attribute name="localizedText">
    <value language="en">The Internal Applications Schema</value>
  </attribute>
  <attribute name="versionNo">
    <value>1</value>
  </attribute>
  <attribute name="lastWritten">
    <value>SYSTIME</value>
  </attribute>
</row>
<row>
  <attribute name="schemaName">
    <value>InternalApplicationDomains</value>
  </attribute>
  <attribute name="type">
    <value>DSST1</value>
  </attribute>
  <attribute name="localeIdentifier">
    <value language="en">en</value>
  </attribute>
  <attribute name="localizedText">
    <value language="en">The Internal Applications Domains Schema</value>
  </attribute>
  <attribute name="versionNo">
    <value>1</value>
  </attribute>
  <attribute name="lastWritten">
    <value>SYSTIME</value>
  </attribute>
</row>
```

2.8) APPRESOURCE.dmx - Entries of various Appresource properties.

```

<row>
    <attribute name="resourceid">
    <value>19431</value>
    </attribute>
    <attribute name="localeIdentifier">
    <value/>
    </attribute>
    <attribute name="name">
    <value>financialassistance_about_you.png</value>
    </attribute>
    <attribute name="contentType">
    <value>image/png</value>
    </attribute>
    <attribute name="contentDisposition">
    <value>inline</value>
    </attribute>
    <attribute name="content">
    <value>./CommonIntake/data/initial/blob/financialassistance_about_you.png</value>
    </attribute>
    <attribute name="internal">
    <value>0</value>
    </attribute>
    <attribute name="lastWritten">
    <value>SYSTIME</value>
    </attribute>
    <attribute name="versionNo">
    <value>1</value>
    </attribute>
    <attribute name="category">
    <value>RS_IMG</value>
    </attribute>
</row>
<row>
    <attribute name="resourceid">
    <value>19432</value>
    </attribute>
    <attribute name="localeIdentifier">
    <value/>
    </attribute>
    <attribute name="name">
    <value>financialassistance_title_about_you.png</value>
    </attribute>
    <attribute name="contentType">
    <value>image/png</value>
    </attribute>
    <attribute name="contentDisposition">
    <value>inline</value>
    </attribute>
    <attribute name="content">
    <value>./CommonIntake/data/initial/blob/financialassistance_title_about_you.png</
value>
    </attribute>
    <attribute name="internal">
    <value>0</value>
    </attribute>
    <attribute name="lastWritten">
    <value>SYSTIME</value>
    </attribute>
    <attribute name="versionNo">
    <value>1</value>
    </attribute>
    <attribute name="category">
    <value>RS_IMG</value>
    </attribute>
</row>
<row>
    <attribute name="resourceid">
    <value>19433</value>
    </attribute>
    <attribute name="localeIdentifier">
    <value/>
    </attribute>
    <attribute name="name">
    <value>Application Form.pdf</value>
    </attribute>
    <attribute name="contentType">
    <value>image/png</value>
    </attribute>
    <attribute name="contentDisposition">
    <value>inline</value>
    </attribute>
    <attribute name="content">
    <value>./CommonIntake/data/initial/blob/Application Form.pdf</value>
    </attribute>
    <attribute name="internal">
    <value>0</value>
    </attribute>
    <attribute name="lastWritten">
    <value>SYSTIME</value>
    </attribute>
    <attribute name="versionNo">
    <value>1</value>
    </attribute>
    <attribute name="category">
    <value>RS_IMG</value>
    </attribute>
</row>

```

Make sure that the files mentioned in the "content" attribute is present in the location specified.

Here it is "CommonIntake\data\initial\blob\" folder

3) Following files need to be copied into clob folder:

Note: If the files do not exist then need to create a new files.

a) Screening IEG questionnaire script

For ex: Copy FinancialAssistanceApplicationScreening_V1_Screening.xml to "CommonIntake\data\initial\clob" folder

b) XSD information

For ex: Copy InternalApplication.xsd to "CommonIntake\data\initial\clob" folder

Copy InternalApplicationDomains.xsd to "CommonIntake\data\initial\clob" folder

c) Process Name XML -

For ex: Copy existing CommonIntakeProcess.xml to "CommonIntake\data\initial\clob" folder

d) Rule set XML -

For ex: Copy FinancialAssistanceRuleSet.xml to "CommonIntake\CREOLE_Rule_Sets" folder

All the files here have been copied from Intake stream to make Screening configuration.

Adding Urgent Alerts to the Rule Set

To output an urgent alert from the CER rule set, the rule class defined in the screening definition should have an attribute named `alertMessages`. This attribute has as its type a list of rule classes of type `AlertMessage`. Each `AlertMessage` which is calculated for this list appears as an urgent alert on the Triage Result page in the application.

Recommending Programs

To recommend a program from the CER rule set, the rule class defined in the screening definition should have an attribute named `programs`. This attribute has as its type a list of rule classes which subclass the type `AbstractProgram`. Each `AbstractProgram` which is calculated into this list will appear as a recommended program on the screening result page in the application.

Specifying whether Programs are Available Internally or Externally

Each program that is output from the screening may be available internally or externally. If the program is available internally, then a link to start the application script is displayed; if the program is available externally, then a link to refer the client to the external agency will be displayed. Screening results behaviour can be defined to specify whether specific programs are available internally or externally. To achieve this:

- Open the XML document which represents the intake process definition.
- Locate the XML element `Screening` which is to be defined.
- For each program that the intake process will support, create an element `ProgramType` as a direct child of the `Screening` element.

Table 4. ProgramType Attributes for a Screening.

This table describes the attributes that can be set for the ProgramType element for a screening.

Attribute Name	Type	Purpose
ProgramType	Code Table Entry	This attribute should contain an entry from the code table 'ProgramType'. This is a code table which specifies a program type, e.g. medical assistance. This attribute is mandatory and must be specified.
Availability	String	This attribute should contain the value 'internal' if the program is available internally or 'external' if the program is available from a different agency.

Configuring Check Eligibility

Introduction

The check eligibility process allows the user to execute a rule set to determine eligibility for programs applied for on the application. The eligibility rule set outputs a rules decision which can be displayed on the Eligibility Checks tab after execution. This document outlines the configurations required for this process.

Configuring an Application Case for Eligibility Checks

There are three configuration options on the application case that drive the check eligibility process.

- Eligibility Check Rule Set - the rule set used to check program eligibility. If not specified, the Check Eligibility action item is hidden from the application case tab action menu and the Eligibility Checks tab is not included on the application case
- Eligibility Check Strategy - the strategy to be used when checking a client's eligibility for programs associated with an application. This is only applicable when the Eligibility Check Rule Set option is specified. The three options available here are:
 - All
 - Programs Applied for Only
 - User Choice
- Results Display Page - this is a dynamic UIM page used to display the eligibility check results. If not specified, no information is displayed on the drop down panel of the check eligibility results page.

The user must configure the eligibility check rule set and results display page. Instructions for doing this are outlined in the following sections.

Configuring the Eligibility Check Rule Set

The eligibility check rule set must contain a rule class for each program on the application case for which eligibility can be checked. Each rule class must extend the abstract rule class, `AbstractApplicationCaseProgram`, in the `ApplicationCaseCheckEligibilityRulesInterface` rule set. The name of the rule class must correspond to the program type reference of the configured program. In the example below, the rule class is called `ProgramOne`, therefore the program reference must also be called `ProgramOne`.

Example

```
<Class extends="AbstractApplicationCaseProgram"
extendsRuleSet="ApplicationCaseCheckEligibilityRulesInterface"
name="ProgramOne ">
```

Each rule class must implement rules to populate the entitlement and decision rules attributes. If an explanation of the eligibility check needs to be displayed, it's necessary to add display rules to achieve this.

These can be added to the rule class. An annotation of `<Display/>` is required on any rules attributes to be displayed for explanation purposes on the results display page - see the *Inside Cúram Eligibility and Entitlement Using Cúram Express Rules* guide for more information.

Configuring the Results Display Page

This results display page should invoke the façade method `ApplicationCaseCheckEligibility.viewCheckEligibilityDisplayRules` to retrieve the display rules. The dynamic UIM page should contain the page parameter `appCaseEligibilityResultID` which should be passed into the façade method. The rules are returned from the façade method as XML in an attribute called `displayXML`. This attribute is used on the dynamic UIM page for displaying the data required for explanation purposes. The individual elements to be displayed to the user are retrieved using extended path expressions in the dynamic UIM page.

Example

If a display attribute called `Income` has been added to our rule set, retrieval of this information would be achieved by adding the following XML to the display rules page:

```
<FIELD
  DOMAIN="CURAM_AMOUNT"
  LABEL="Field.Label.Income">
  <CONNECT>
    <SOURCE
      EXTENDED_PATH="/DecisionDetails/ProgramOne/Income"
      NAME="DISPLAY"
      PROPERTY="displayXML"
    />
  </CONNECT>
</FIELD>
```

The first item in the `EXTENDED_PATH` is always `DecisionDetails`, with the remainder of the path pointing to the attribute in the custom rule class.

Configuring a PCR Rule Set

Introduction

This chapter provides an overview of the PCR rule set structure and details how a customer can create a PCR rule set. PCR rule sets are used to calculate a result for the priority, complexity, and risk rating for a case scenario. Each of the components which make up a PCR assessment is represented as an attribute in the PCR rule set. A rule can have an associated weighting which is added to the overall PCR calculation if it succeeds. The rules then determine the overall rating and classification of the case.

Configuring a PCR Rule Set

Each PCR Rule Set must contain a rule class which inherits from the `AbstractPCR` class. This rule class is the class which produces the PCR results to be displayed to the worker.

To create a PCR rule class, first create the rule class using the CER editor, naming the rule class appropriately.

The usage of the PCRRuleSet rule class guarantees that the required attributes are available during rules execution. For more information on setting up rule sets, see the *Cúram Express Rules Cookbook*.

A PCR rule set must inherit from the PCRRuleSet and provide an implementation for each of the six abstract attribute within the defined rule set. The description attribute is inherited from the root rule class and each solution must also provide its own implementation of this attribute.

Mandatory Rule Attributes

Table 5. Mandatory Rule Attributes for PCR Rule Sets.		
This table describes mandatory rule attributes to be used for PCR rule sets		
Rule Attribute	Type	Purpose
caseID	Number	Specified case identifier attribute for which the PCR rules execution relates to.
description	String	This attributes represents the text defining the property description. The value that this attribute contains is a reference to one or more properties in a property file containing the actual text.
priorityRate	Number	This attribute is a calculated attribute representing the relative ranking of the case against a baseline to determine a timeline for response.
priorityReason	String	This attribute represents the text defining the property priority reason. The value that this attribute contains is a reference to one or more properties in a property file containing the actual text.
complexityRate	Number	This attribute is a calculated attribute representing the ranking of a case against a baseline to determine the resource(s) required for a response.
complexityReason	String	This attributes represents the text defining the property complexity reason. The value that this attribute contains is a reference to one or more properties in a property file containing the actual text.

Table 5. Mandatory Rule Attributes for PCR Rule Sets.

This table describes mandatory rule attributes to be used for PCR rule sets

(continued)

Rule Attribute	Type	Purpose
riskRate	Number	This attribute is a calculated attribute representing the relative ranking of a case against a baseline to determine its potential impact to the agency.
riskReason	String	This attributes represents the text defining the property risk reason. The value that this attribute contains is a reference to one or more properties in a property file containing the actual text.

Specifying Rule Set Properties Text

The rule set properties text is specified by creating an entry in a localized property file as follows:

- Create a property file, for example, PCRSample.properties.
- Add each entry to the property file that will be referenced by the Rule Class attributes. The value of each of these entries is the localized text to be displayed in the application. The following example outlines an example property entry in a PCRSample.properties file and how the property is referenced by a rule set attribute:

```
# This Properties file contains resource
strings for the Sample PCR Rule set.
PCRSample.description=PCRSample
PCRSample.samplePriorityReason=Sample Priority Reason

<Attribute name="description">
  <type>
    <javaclass name="curam.creole.value.Message"/>
  </type>
  <derivation>
    <ResourceMessage
      key="PCRSample.description"
      resourceBundle="curam.pcrsample.rules.PCRSample"
    >
    </ResourceMessage>
  </derivation>
</Attribute>
```

- Add the Properties file entry to the Resource Store by updating the 'Dynamic UIM' section of the Administration Application. In the above example, this entails adding a PCRSample.properties entry in the Dynamic UIM section of the administration application, along with a corresponding page ID, a resource store category, and a properties file.

Configuring Authorization Rule Sets

Introduction

This chapter covers the rule sets used during authorization and the necessary configurations required by a custom solution.

Intake Rule Sets

There are two rule sets shipped by default with Intake:

- `ApplicationAuthorisationInterfaceRuleSet`
- `ClientSelectionInterfaceRuleSet`

These provide flexibility to customers with regard to the strategies for program authorization, namely the determination of the programs to be authorized and the clients to be added to a product delivery as part of program authorization.

Determining the Programs to be Authorized

When authorizing at the application case level, the programs to be considered must be determined using rules. This is done via the `ApplicationAuthorisationInterfaceRuleSet` rule set.

Writing the Authorize Application Rule Class

The rule class for governing application authorization must extend from the abstract class `ApplicationAuthorisationInterfaceRuleSet.AbstractApplicationCase`. Here is a description of the attribute(s) inherited from `AbstractApplicationCase`:

<i>Table 6. Abstract Attribute(s) To Be Implemented</i>		
Rule Attribute Name	Data Type	Description
programs	List of Program	The programs to be authorized on the application.

Program is an instance of the `ApplicationAuthorisationInterfaceRuleSet.Program` class. As it's optional for a product delivery to be created on authorization, `ApplicationAuthorisationInterfaceRuleSet.Program.primaryClient` is defaulted to null and `ApplicationAuthorisationInterfaceRuleSet.Program.additionalClients` is defaulted to an empty list.

A basic implementation might be the retrieval of all programs in a state of 'Pending' that are associated with the application case.

Determining the Clients to be Added to the Product Delivery

One of the configurations on a program is Client Selection Strategy. This can be one of the following:

- All
- User Selection
- Rules

The Rules strategy is governed by the `ClientSelectionInterfaceRuleSet` rule set.

Writing the Client Selection Rule Class

The rule class for governing client selection must extend from the abstract class `ClientSelectionInterfaceRuleSet.AbstractClients`. Here is a description of the attribute(s) inherited from `AbstractClients`:

<i>Table 7. Abstract Attribute(s) To Be Implemented</i>		
Rule Attribute Name	Data Type	Description
primaryClient	Client	The primary client for the product delivery being created as a result of authorization.

Client is an instance of `ClientSelectionInterfaceRuleSet.Client`.

Intake Process XML Definition

This appendix provides a high level overview of the XML definition for an intake process.

Intake Process XML Definition

```
<IntakeProcess>
  <GlobalConfiguration>
  </GlobalConfiguration>
  <IndividualConfiguration>
    <Triage DataStore="Triage" RuleSet="SampleTriageRuleSet"
      RuleSetClass="Triage" ScriptName="Triage" ScriptType="Screening"
      ScriptVersion="V1"/>
    <Screening DataStore="Screening" RuleSet="SampleScreeningRuleSet"
      RuleSetClass="ScreeningResult" ScriptName="SampleScreening"
      ScriptVersion="V1" type="SC12345">
      <DisplayStatus status="SS12345"/>
      <DisplayStatus status="SS67890"/>
    </Screening>
  </IndividualConfiguration>
</IntakeProcess>
```

Ability to allow activation of evidence which would not otherwise be activated as part of the application case authorization process.

Evidence on an application case is activated during the application case authorization process only if it has been configured for brokering to a target case. You can now customize this evidence activation process so that evidence not configured for brokering to a target case can also be activated. To achieve this, you can use the `curam.commonintake.evidencebroker.impl.CIREvidenceActivationHooks` class and implement the method `getEvidenceTypesFromOtherSources()` to return the additional evidence that needs to be activated.

Intake Environment Variables

Application Properties

This appendix describes application properties for Intake. These may be administered through the Cúram system administration application - see the Cúram System Configuration Guide for more information.

Table 8. Intake Environment Variables.

This table contains Intake environment variables.

Property Name	Description	Default
curam.intake.map.default.zoom.level	This property is used to define the initial zoom level of the Google Maps display on the Service Provider screen. Zoom levels between 0 (the lowest zoom level, in which the entire world can be seen on one map) to 21+ (down to individual buildings) are possible.	11
curam.intake.map.default.center.latitude	This property is used to define the default latitude of the center of the Google Maps display on the Service Provider screen.	-89.40570831298828

Notices

This information was developed for products and services offered in the United States.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 US

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan Ltd. 19-21, Nihonbashi-Hakozakicho, Chuo-ku Tokyo 103-8510, Japan

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 US

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data and client examples cited are presented for illustrative purposes only. Actual performance results may vary depending on specific configurations and operating conditions.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Privacy Policy considerations

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering's use of cookies is set forth below.

Depending upon the configurations deployed, this Software Offering may use session cookies or other similar technologies that collect each user's name, user name, password, and/or other personally identifiable information for purposes of session management, authentication, enhanced user usability, single sign-on configuration and/or other usage tracking and/or functional purposes. These cookies or other similar technologies cannot be disabled.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at <http://www.ibm.com/privacy> and IBM's Online Privacy Statement at <http://www.ibm.com/privacy/details> the section entitled "Cookies, Web Beacons and Other Technologies" and the "IBM Software Products and Software-as-a-Service Privacy Statement" at <http://www.ibm.com/software/info/product-privacy>.

Trademarks

IBM, the IBM logo, and [ibm.com](http://www.ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at "Copyright and trademark information" at <http://www.ibm.com/legal/copytrade.shtml>.

Adobe, the Adobe logo, PostScript, and the PostScript logo are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States, and/or other countries.

Java™ and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

The registered trademark Linux is used pursuant to a sublicense from the Linux Foundation, the exclusive licensee of Linus Torvalds, owner of the mark on a worldwide basis.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other names may be trademarks of their respective owners. Other company, product, and service names may be trademarks or service marks of others.



Part Number:

(1P) P/N: